

System Administration

SL1 version 10.2.0, rev 2

Table of Contents

Introduction	
Who Should Read This Manual?	
What's In This Manual?	
Requirements	
Global Settings	
Global Settings for API	
Global Settings for Appliances	
The Web Configuration Utility	
Global Settings for Asset Automation	
Global Settings for User Logins, Discovery, Data Collection, UI Features, and Expiration Warnings	
Global Settings for Data Retention	
Normalization and Roll-Up of Performance Data	
Collection of Raw Data	
Data Normalization and Rollup	
Example	
Storage of Raw and Rolled Up Data	
Global Settings for Inbound Email and Outbound Email	
Global Settings for Login Alert Messages	
Global Settings for Password Reset Emails	
Defining the Email Message for "I forgot my password"	
Global Settings for System Thresholds	
Global Settings for Interface Thresholds	
Settings in Silo.Conf	
Disabling the User Interface on a Database Server	
Collector Groups	
Installing, Configuring, and Licensing Data Collectors	
Technical Information About Data Collectors	
Duplicate IP Addresses	
Open Ports	
Viewing the List of Collector Groups	
Creating a Collector Group	
Pre-Deployment Questions for a Collector Group	
Capacity Planning for a Collector Group	
Defining a Collector Group	
Editing a Collector Group	
Collector Groups and Load Balancing	
Tuning Collector Groups in the silo.conf File	
Collector Affinity	
Failover for Collector Groups for Component Devices	
Collector Groups for Merged Devices	
Creating a Collector Group for Data Storage Only	
Deleting a Collector Group	
Aligning the Collector Group for A Single Device	
Aligning the Collector Group in a Device Template	
Changing the Collector Group for One or More Devices	
Managing the Host Files for a Collector Group	
Processes for Collector Groups Enabling and Disabling Concurrent PowerShell for Collector Groups	
Enabling Concurrent PowerShell on All Collector Groups	
Disabling Concurrent PowerShell on All Collector Groups	

Enabling Concurrent PowerShell on a Specific Collector Group	90
Disabling Concurrent PowerShell on a Specific Collector Group	90
Enabling and Disabling Concurrent SNMP for Collector Groups	90
Enabling and Disabling Concurrent SNMP for All Collector Groups	
Enabling and Disabling Concurrent SNMP for Collector Groups	
Daily Health Tasks	94
What is a Healthy SL1 System?	
SL1 Self-Healing	98
SL1 Self-Monitoring	98
Monitoring System Events	
Searching the System Logs	100
Deleting Entries from the System Logs	
Monitoring System Processes	101
Viewing the List of System Processes	102
Searching and Filtering the List of System Processes	
Monitoring the Status of Each Appliance	104
Monitoring User Actions and Events	
Viewing the List of Audit Logs	
Searching and Filtering the List of Audit Logs	
Special Characters	108
Generating Reports on Audit Logs	112
Monitoring the Status of Data Collectors	112
Upgrading SL1	
Reference: The System Updates Page	115
Reference: Viewing the List of Updates	116
Reference: Viewing the Log Files for Updates	118
Workflow	
Planning	
Scheduling Maintenance Windows	120
Updating SL1 Appliances to Oracle Linux	121
SL1 Release Prior to 8.1.1	
SL1 Releases Prior to 8.10.0	121
Pre-Upgrade Best Practices	
Backing Up Settings in the NextUI	122
Backing Up SSL Certificates	122
Setting the Timeout for PhoneHome Watchdog	122
Adjusting the Timeout for Staging and Deploying	
SL1 8.14 and Later Releases	123
SL1 8.12 and Prior Releases	
Running the System Status Script Before Upgrading	
Running the System Status Script on SL1 8.14.0 and Later Releases	
Running the System Status Script on SL1 8.12.x Releases	
Running the System Status Script on SL1 8.10 and Prior Releases	
Upgrading the SL1 Distributed Architecture on SL1 Versions 8.5.0 and Earlier	
Disabling Automatic Staging	
Downloading the Updates	
Importing the Updates	
Staging the Update	
Running the Pre-Upgrade Check	
All SL1 Appliances:	
Active Database Server:	
All Database Servers:	

Administration Portal:	133
Data Collectors and Message Collectors:	
Downloading and Running the Pre-Upgrade Check	
Putting All SL1 Appliances in Maintenance Mode	
Deploying the Update	
Putting All SL1 Appliances Out of Maintenance Mode	
Performing Deltaless Upgrades	
Upgrading the SL1 Distributed Architecture on SL1 versions 8.6.0 and Later	
Special Steps for SL1 8.12.0 and Earlier	
Downloading the Update	
Importing the Update	
Staging the Update	141
Automatic Staging	141
Manually Staging an Update	
Monitoring Staging	
Running the Pre-Upgrade Check for SL1 10.1 and Later	145
Running the Pre-Upgrade Check	
CentOS 5 Failure	
Collector Group Membership	146
Eligibility Failure	146
Enabled Failure	146
Free Disk-Space Failure	146
Host File Failure	147
Patch-Hook Ownership Failure	147
RPM Database Failure	147
RPM Package Failure	147
Running the Pre-Upgrade Check for SL1 8.14 and Earlier	148
All SL1 Appliances:	148
Active Database Server:	
All Database Servers:	
Administration Portal:	149
Data Collectors and Message Collectors:	150
Downloading and Running the Pre-Upgrade Check	
Putting All SL1 Appliances in Maintenance Mode	150
Deploying the Update	151
Troubleshooting System Update	
Available Commands	
Monitoring Deployment	
Putting All SL1 Appliances Out of Maintenance Mode	
Upgrading SL1 Extended Architecture	
Manual Steps for Updates to 8.4.x and Earlier Systems	
Automatically Upgrading MariaDB with a Script	
Additional Steps for MariaDB Upgrades in 10.1.x	
Manually Upgrading MariaDB	
Download RPMs to SL1 Appliances	
Manually Upgrade Two Database Servers Configured for High Availability or Disaster Recovery	
Step 1: On the Secondary Database Server	
Step 2: On the Primary Database Server	
Step 3: On the Secondary Database Server	
Manually Upgrade Three Database Servers Configured for High Availability and Disaster Recovery	
Step 1: On the Secondary Database Server	
Step 2: On the Primary Database Server	168

Step 3: On the Secondary Database Server	169
Step 4: On the Disaster Recovery Database Server	170
Manually Upgrading Standalone Database Servers, All-In-One Appliances, Data Collectors, and	
Message Collectors	171
Additional Steps for MariaDB Upgrades in 10.1.x	
Rebooting Appliances in the SL1 Distributed Stack	174
Rebooting the Administration Portal	174
Rebooting Multiple Administration Portals	174
Rebooting a Single Administration Portal	174
Rebooting Data Collectors and Message Collectors	175
Rebooting Data Collectors and Message Collectors from the Appliance Manager page	175
Rebooting Data Collectors and Message Collectors from the Command Line	
Rebooting Standalone All-In-One Appliance and Standalone Database Server	175
Rebooting Two Database Servers Configured for Disaster Recovery	176
Rebooting Two Database Servers in a High Availability Cluster	177
Rebooting Three Database Servers Configured for High Availability and Disaster Recovery	178
Restoring Settings for NextUI	
Restoring the SSL Certificate	179
Resetting the Timeout for PhoneHome Watchdog	180
Updating Default PowerPacks	
Configuring Subscription Billing	182
Monitoring and Maintaining SL1	183
Monitoring and Managing User Access	184
Viewing Information about Each Access Session	184
Deleting a User's Session	185
Viewing Lockouts and Unlocking Lockouts	186
Global Settings for Lockouts	
Audit Logs	187
Managing Scheduled Tasks	187
Viewing the List of Schedules	188
Enabling or Disabling One or More Schedules	189
Deleting One or More Schedules	190
Monitoring Overall System Usage and Statistics	190
Viewing an Overview of All Events	191
Viewing Events by Appliance and Event Source	193
Admin Notifier	
How Does the Admin Notifier Work?	196
Admin Notifier in the Classic SL1 User Interface	197
What Issues Does the Admin Notifier Monitor?	197
Diagnostic Tools	
ScienceLogic SL1 Self-Monitoring	
Viewing Information About ScienceLogic Processes	
Viewing the List of ScienceLogic Processes	
Searching and Filtering the List of ScienceLogic Processes	
Editing the Parameters of a ScienceLogic Process	
Debugging a Process and Viewing Debug Logs	
Viewing Information About Unhandled Exceptions	
Viewing the List of Unhandled Exceptions	
Searching and Filtering the list of Unhandled Exceptions	
Saving the Unhandled Exception to the Local Computer	
Viewing the Output of the System Status Script	
Viewing the Database Tables on the Database Server	213

Accessing the Database Tool	213
Disabling Normalization, Re-Enabling Normalization, and Backfilling Raw Data	
Enable Logging for Data Pull Storage Objects	
Enable	
Disable	
Controlling Log Settings	
Setting UI Developer Log Levels	
Setting UI/REST MySQL Query Log Levels	
Configuring Advanced Log Settings	
Downloading Logs from the PHP Developer Logs page	
Changing Passwords	
Disabling phpMyAdmin	
Changing the Password for the Default Account for the User Interface	223
Changing the Password for the Default Console User	.223
Changing the Password for the Web Configuration Utility	.224
Changing Database Passwords	
Configuring a New Password on Collector Appliances	
Editing Silo.Conf	
Updating the master.system settings licenses Table	
Changing the MySQL Root Password on Database Appliances	
Recovering the Root MySQL Password	
Recovering the MySQL SNMP User Account on Collector Appliance	
Changing the IP Address of an SL1 Appliance	
Changing the IP Address on an All-In-One Appliance	
Step 1. Stop the EM7 Service	
Step 2. Change the IP Address in the Configuration Files	
Step 3. Change the IP Address in the /etc/hosts File	
Step 4. Change the IP Address in the Network Interface Configuration File	
Step 5. Update the IP Address in the MySQL Database	
Step 6. Reboot the Appliance	
Changing the IP Address on a Database Server	.234
Step 1. Stop the EM7 Service	.234
Step 2. Change the IP Address in the Configuration Files	235
Step 3. Change the IP Address in the /etc/hosts File	.235
Step 4. Change the IP Address in the Network Interface Configuration File	
Step 5. Update the IP Address in the MySQL Database	
Step 5a: For Database Servers Configured with PhoneHome	
Step 5b For Clustered Database Appliances (using HA, DR, or HA+DR)	
Step 6. Reboot the Appliance	
Step 7. Change the Database Appliance IP Address in the Administration Portals, Data Collectors,	.210
and Message Collectors	240
Changing the IP Address on a Data Collector or Message Collector	
	.243
Using the Web Configuration Utility to Change the IP Address of a Data Collector or Message	0.40
Collector	
Using the Command Line to Change the IP Address of a Data Collector or Message Collector	
Changing Name Servers on an SL1 Appliance	
Changing Name Servers on an SL1 Appliance	
Installing Additional RPMs on an SL1 Appliance	
Backup Management	.249
Types of SL1 Backups	.250
Preparing for SL1 Backups	251
Creating a Backup Credential	252

Configuration Backups	
What Does a Configuration Backup Include?	
Viewing the Databases and Tables Included or Excluded from a Configuration Backup	
Defining a Configuration Backup	
Restoring a Configuration Backup	
Full Backup	
What Does a Full Backup Include?	
Defining a Full Backup	
Restoring a Full Backup	
Retaining Full Backups	
Additional Configuration for Solaris NFS Remote Shares	
DR Backup	
Defining a DR Backup	
Restoring a DR Backup	
Retaining DR Backups	
Performing Configuration Backups and Full Backups on the Disaster Recovery Database Server	
Configuration Backup on a Disaster Recovery Database Server	
Full Backup on a Disaster Recovery Database Server	
Viewing License Data	
Viewing License Information	272
Subscription Licenses	
Viewing the Subscription License Usage	275
Viewing Delivery Status	
Manually Uploading License Usage to ScienceLogic	
Downloading the Daily License Usage File	277
Manually Uploading the Daily License Usage File to ScienceLogic	
Uploading the ScienceLogic Receipt	
Data Retention Settings for Licensing	
CAC Authentication	
Prerequisites	
Importing SSL Certificates	
Extracting the Common Name from a Certificate for Authentication	
Defining the Client Certificate Chain	
Verifying SSL Certificate File Import and Resolving Issues	
Clear the SL1 Cache and Restart NGINX	
Testing the Configuration	
Special Circumstance: Multiple Levels of Intermediate Certificates	
Accessing the Appliance without CAC Authentication	
Authentication Profiles and Resources	
Authentication Profiles	
Viewing the List of Authentication Profiles	
Filtering the List of Authentication Profiles	
The "default" Authentication Profile	
Creating an Authentication Profile	
Editing an Authentication Profile	
Deleting One or More Authentication Profiles	
Authentication Resources	
Viewing the List of Authentication Resources	
Filtering the List of Authentication Resources	
The "EM7 Internal" Resource	
Creating an LDAP/AD Authentication Resource	
Creating an SSO Authentication Resource	

Editing an Authentication Resource	
Deleting an Authentication Resource	
Installing an SSL Certificate	
Certificates for ScienceLogic Servers	
Requesting a Commercial SSL Certificate	
Creating Your Own Certificate	
Installing the Certificate on an SL1 Appliance	
Managing Host Files	
Viewing the List of Host Entries	
Creating a New Host Entry	
Editing a Host Entry	
Using an Existing Host File Entry to Create a New Host File Entry (Save As)	
Deleting One or More Host Entries	

Chapter

1

Introduction

Overview

This manual describes the tasks that System Administrators who monitor and maintain the health of SL1 must perform, and the tools they can use to perform those tasks.

This chapter includes the following topics:

Who Should Read This Manual?	9
What's In This Manual?	9
Requirements	0

Who Should Read This Manual?

This manual is intended for System Administrators who must monitor and maintain the health of SL1.

This manual describes tasks in the **[System]** tab that are related to maintenance and monitoring of SL1. This manual also includes advanced tasks that are performed at the console or in an SSH session.

What's In This Manual?

This manual includes information on global settings, collector groups, upgrading SL1, health tasks, maintenance tasks, licensing, and tools for troubleshooting and debugging.

Requirements

To follow some of the steps listed in this manual, you must have administrator-level access to the console of your SL1 appliances.

Chapter

2

Global Settings

Overview

In SL1, global settings allow you to define default behavior that applies to all elements in the platform. For settings that affect devices, you can override global settings with device-level settings.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon (三).
- To view a page containing all the menu options, click the Advanced menu icon (…).

This chapter includes the following topics:

Global Settings for API	12
Global Settings for Appliances	13
Global Settings for Asset Automation	17
Global Settings for User Logins, Discovery, Data Collection, UI Features, and Expiration Warnings	18
Global Settings for Data Retention	30
Global Settings for Inbound Email and Outbound Email	38
Global Settings for Login Alert Messages	41
Global Settings for Password Reset Emails	43
Global Settings for System Thresholds	46
Global Settings for Interface Thresholds	51
Settings in Silo.Conf	58
Disabling the User Interface on a Database Server	68

Global Settings for API

The **REST API Settings** page (System > Settings > API) allows you to define global parameters that affect the behavior of the REST API. When defined, these parameters affect all interaction with the API.

NOTE: This page is available only to administrator users.

To edit the settings in the REST API Settings page:

1. Go to the **REST API Settings** page (System > Settings > API).

REST API Settings			Rese	l Guide
	request Account [[em7.edmin] Isader Support [[Esnabled (/dema.only)]	Ticket Resource Beh	and System Logn)] and-notification 1 is sent]	• •
		Save		

- 2. In the **REST API Settings** page, edit the values in one or more of the following fields:
 - Internal Request Account. Specify the user account that allows SL1 to make API requests without a password. For details on building such an API request, see the ScienceLogic API manual.
 - X-EM7-run-as Header Support. Specifies whether administrator users can make API requests using the permissions of another user without that user's password. Choices are:
 - Disabled. Administrator users cannot make API requests using the permissions of another user.
 - Enabled (Admin only). Administrator users can include the X-EM7-run-as Header to make API requests using the permissions of another user. For details on using this header, see the ScienceLogic API manual.
 - Logging. Specifies which logs SL1 will write to when tickets are created or updated using the API. Choices are:

- Transaction Logging Only (System Logs). If a ticket is created or updated using the API, SL1 will write the standard entry to the audit log that indicates a user performed a write-operation using the API. However, SL1 will not write to the ticket log for the ticket that was created or updated.
- Normal (Ticket and System Logs). If a ticket is created or updated using the API, SL1 will write to the audit log and to the ticket log for the ticket that was created or updated.
- X-EM7-suppress-logging Header Support. If Normal (Ticket and System Logs) is selected in the Logging field, this field specifies whether the X-EM7-suppress-logging header can be used when an administrator creates or updates a ticket using the API. If the X-EM7-suppress-logging header is used when creating or updating a ticket, SL1 will not write to the ticket log for the ticket that was created or updated. Choices are:
 - Disabled. The X-EM7-suppress-logging header cannot be used.
 - Enabled (Admin only). The X-EM7-suppress-logging header can be used to stop SL1 from writing to the ticket log for the ticket that was created or updated.
- Send Notification. When a ticket is created or updated, SL1 can automatically send notification emails to the ticket assignee and ticket watchers. This option specifies the conditions under which SL1 will send notification emails when tickets are created or updated using the API. Choices are:
 - Only if X-EM7-send-notification: 1 is sent. SL1 will send notification emails for a ticket only when the X-EM7-send-notification header is set to 1. For details on using this header, see the manual Using the ScienceLogic API.
 - Sent after every write operation. SL1 will send notification emails for every API request that creates or updates a ticket.
- 3. Click the **[Save]** button to save changes in this page.

Global Settings for Appliances

The **Appliance Manager** page (System > Settings > Appliances) provides for global appliance configuration and management for your entire system or stack. This includes collector group and load distribution, version information, license status, and other items that are important when you upgrade.

From the **Appliance Manager** page, you can also access the Web Configuration Utility for each ScienceLogic appliance by clicking the toolbox icon(), or you can access the database administration tool for each Database Server or All-In-One Appliance by clicking the gear icon ().

For each Database Server, Data Collector, and Message Collector, you can click on the magnifying-glass icon (
()) to view the output of the system status script for that appliance.

NOTE: The bomb icon () does not appear for Database Servers that are not configured for High Availability or Disaster Recovery. The bomb icon does not appear for Database Servers that are configured as the primary database in a High Availability or Disaster Recovery configuration.

(ppl	lance Manager Editing Applia	nce [10]		10-64-171-211-CU-RH	IP Address	(Data Collection Un	Descriptio		• •	Sav	sve e As			System St	atus Output Res	2t -	Guide
	Name	IP Address	Module Type	Collector Group	Description	Build	MariaDB	Capacity	Allocation	ID	Validated	Endpoint	Edit Date	Edit User	Create Date		E
- 4	10-64-171-200-CDB	10.64.171.200	Database	n/a	Database: 10.64.171.200	10.1.0 r2166	10.4.12	5,000	n/a	1	Yes		2020-06-25 15:39:58	em7admin	2020-06-25 15:39:58	🗟 🤹	6°
4	P 10-64-171-201-AP	10.64.171.201	Administration Portal	n/a	AP: 10.64.171.201	10.1.0 r2166		n/a	n/a	18	Yes	-	2020-06-25 16:15:03	em7admin	2020-06-25 16:10:59	a (۵ ا
4	10-64-171-203-CU-MOSS1	10.64.171.203	Data Collection Unit	CUG-MOSS	collector unit: 10.64.171.203	10.1.0 r2166	10.4.12	n/a	0	2	Yes	-	2020-06-25 16:18:28	em7admin	2020-06-25 16:09:37	3 🖉	o* (
4	10-64-171-204-CU-MOSS2	10.64.171.204	Data Collection Unit	CUG-MOSS	collector unit: 10.64.171.204	10.1.0 r2166	10.4.12	n/a	0	3	Yes	-	2020-06-25 16:23:12	em7admin	2020-06-25 16:09:38	۹ / د	۵ ک
6	10-64-171-205-CU-UsualSuspects1	10.64.171.205	Data Collection Unit	CUG-UsualSuspects	collector unit: 10.64.171.205	10.1.0 r2166	10.4.12	n/a	0	4	Yes	-	2020-06-25 16:29:15	em7admin	2020-06-25 16:09:39	3 🖉	o* (
4	10-64-171-206-CU-UsualSuspects2	10.64.171.206	Data Collection Unit	CUG-UsualSuspects	collector unit: 10.64.171.206	10.1.0 r2166	10.4.12	n/a	0	5	Yes	-	2020-06-25 16:22:13	em7admin	2020-06-25 16:09:40	۹ / د	et I
4	10-64-171-207-CU-ScrumAndCoke	10.64.171.207	Data Collection Unit	CUG-SAC	collector unit: 10.64.171.207	10.1.0 r2166	10.4.12	n/a	0	6	Yes	-	2020-06-25 16:24:17	em7admin	2020-06-25 16:09:40	3 🖉	o* (
4	10-64-171-208-CU-Shared	10.64.171.208	Data Collection Unit	CUG-Shared	collector unit: 10.64.171.208	10.1.0 r2166	10.4.12	n/a	2	7	Yes		2020-06-25 16:25:12	em7admin	2020-06-25 16:09:41	۶ / 🖌	o* (
4	10-64-171-209-CU-Knights	10.64.171.209	Data Collection Unit	CUG-Solutions3	collector unit: 10.64.171.209	10.1.0 r2166	10.4.12	n/a	89	8	Yes	-	2020-06-25 16:24:16	em7admin	2020-06-25 16:09:42	2 /	6° (
•	10-64-171-210-CU-RebelScrum	10.64.171.210	Data Collection Unit	CUG-Solutions1	collector unit: 10.64.171.210	10.1.0 r2166	10.4.12	n/a	666	9	Yes		2020-06-25 16:24:12	em7admin	2020-06-25 16:09:43	۶ 🖊 🖻	o* 1
1	P 10-64-171-211-CU-RNGs	10.64.171.211	Data Collection Unit	CUG-Shared	collector unit: 10.64.171.211	10.1.0 r2166	10.4.12	n/a	3	10	Yes	-	2020-06-25 16:26:13	em7admin	2020-06-25 16:09:44	2 🖊	o* 1
•	P 10-64-171-212-CU-Starlord	10.64.171.212	Data Collection Unit	CUG-Solutions2	collector unit: 10.64.171.212	10.1.0 r2166	10.4.12	n/a	0	11	Yes	-	2020-06-25 16:24:14	em7admin	2020-06-25 16:09:45	۶ 🖊 🖻	of I
4	P 10-64-171-213-CU-Benedict	10.64.171.213	Data Collection Unit	CUG-Benedict	collector unit: 10.64.171.213	10.1.0 r2166	10.4.12	n/a	16	12	Yes	-	2020-06-25 16:26:17	em7admin	2020-06-25 16:09:45	2 🖊	o" I
l.	P 10-64-171-214-CU-50centos	10.64.171.214	Data Collection Unit	CUG-Solutions1	collector unit: 10.64.171.214	10.1.0 r2166	10.4.12	n/a	290	13	Yes	-	2020-06-25 16:26:15	em7admin	2020-06-25 16:09:46	۶ 🖊 🖻	o* I
•	P 10-64-171-217-CU-RaceCondition1	10.64.171.217	Data Collection Unit	CUG-RaceCondition	collector unit: 10.64.171.217	10.1.0 r2166	10.4.12	n/a	0	15	Yes	-			2020-06-25 16:09:48		
6	10-64-171-218-CU-RaceCondition2	10.64.171.218	Data Collection Unit	CUG-RaceCondition	collector unit: 10.64.171.218	10.1.0 r2166	10.4.12	n/a	1	16	Yes	-	2020-06-25 16:24:15	em7admin	2020-06-25 16:09:49	Q 🖊 (o* I
r.	P 10-64-171-219-CU-RaceCondition3	10.64.171.219	Data Collection Unit	CUG-RaceCondition	collector unit: 10.64.171.219	10.1.0 r2166	10.4.12	n/a	0	17	Yes	-	2020-06-25 16:24:28	em7admin	2020-06-25 16:09:50	2 🖊	6° (
•	P 10-64-171-216-MC	10.64.171.216	Message Collection Unit	-	collector unit: 10.64.171.216	10.1.0 r2166	10.4.12	n/a	n/a	14	Yes	10.64.171.216 🎝	2020-06-25 18:38:04	em7admin	2020-06-25 16:09:47	3/	e" I
														ISelect	Astrol	~	0-

During upgrade, table cells will highlight known, pending action items that must be done to successfully complete an upgrade. This page is useful for ensuring that every Data Collector is assigned to a Collector Group before you begin an upgrade. In some cases, the Data Collector might be assigned to an empty Collector Group, if the collector is new.

This page can also be used to ensure that Data Collector load is near or below the system requirements for each collector.

To edit information about a ScienceLogic appliance:

- 1. Go to the **Appliance Manager** page (System > Settings > Appliances).
- 2. Locate the ScienceLogic appliance you want to edit. Click its wrench icon (🌮).
- 3. The fields in the top pane are populated with values from the selected ScienceLogic appliance.
- 4. You can edit one or more of the following fields:

- Host Name. Name of the ScienceLogic appliance.
- IP Address. Primary IP address for the ScienceLogic appliance

NOTE: For Data Collection Units that are part of a Phone Home configuration, ensure that the Primary IP address for the Data Collection Unit is its loopback IP.

- Module Type. This field is read-only. Possible values are:
 - All In One
 - Database
 - Administration Portal
 - Data Collection Unit
 - Message Collection Unit

NOTE: The combination appliance with a Database Server and an Administration Portal on a single appliance will appear with *Module Type* of Database. The combination appliance with a Message Collection Unit and a Data Collection Unit will appear with *Module Type* of Data Collection Unit.

- Description. Description of the ScienceLogic appliance.
- 5. You can edit two optional fields for Data Collector or Message Collector.
 - **DB User**. User name that can access the MariaDB database on the Data Collector or Message Collector.
 - **DB Password**. Password that allows access the MariaDB database on the Data Collector or Message Collector.

If you are using AWS RDS with your SL1 System, you must define the **DB User** and **DB Password** for each Data Collector or Message Collector.

NOTE: It is recommended that you vary the Data Collector and Message Collector database credentials for enhanced per-appliance security. This greatly enhances the security of your central database by disallowing a successful attack to go unnoticed on your Data Collector and then succeed without failure on the central database.

6. Click the **[Save]** button to save any changes. Click the **[Save As]** button to save your changes to a new appliance name.

The Web Configuration Utility

The Web Configuration Utility allows you to configure system-level settings for your appliances. Each appliance includes access to the Web Configuration Utility.

The Web Configuration Utility adds an additional layer of security to SL1 by segregating administrative functions from the rest of the user interface and by exposing system-level settings and diagnostic tools that might otherwise require command-line access to the appliance. The Web Configuration Utility can be accessed only through an HTTPS connection and requires its own administrator-level password.

Perform the following steps to log in to the Web Configuration Utility:

1. You can log in to the Web Configuration Utility using any web browser supported by SL1. The address of the Web Configuration Utility is in the following format:

https://ip-address-of-appliance:7700

- 2. Type the address of the Web Configuration Utility into the address bar of your browser, replacing "ipaddress-of-appliance" with the IP address or public-facing fully qualified hostname of the appliance.
- You will be prompted to type your username and password. Log in as *em7admin* with the appropriate password. The default password is *em7admin*. After logging in, the main Configuration Utility page appears:

NOTE: For better security, change your Web Configuration Utility credentials. If you leave your Web Configuration Utility credentials as the stock credentials, you greatly increase the risk that your central database could be attacked, or that you could be locked out of the Web Configuration Utility.

ScienceLogic™ Web Configuration L	tility 😤 Home	🔦 Licensing	≓ Interfaces	Device Settings	C PhoneHome	€ Logout			
	Configurat				aces.				
Licensing	≓ Interfaces	🌣 Dev	vice Settings		C PhoneHome	;			
License Information									
Capacity	Capacity : 7000 Expiration : Tue, 19 Dec 2017 05:00:00 GMT								
License Ty	License Type : Trial Organization : sliotest								

- 4. In the **Configuration Utility**, you can license a SL1 appliance, configure interfaces, and edit settings for the SL1 appliance and the Database Server if applicable.
 - For details on using the **Configuration Utility** to license a SL1 appliance, see the manual *Installation and Initial Configuration*.
 - For details on using the **Configuration Utility** to inform Data Collectors, Message Collectors, and Administration Portals when you change the IP address of a Database Server, see the section on **Changing IP Addresses**.

Global Settings for Asset Automation

The **Asset Automation** page (System > Settings > Assets) allows you to define the default behavior for all asset records.

4.00	set Automation						Reset Guide
M5:	Set Automation						Reset Guide
				_			
		Field Name					
		Data Source	•				
		Alert on change					
		Auto Update	(N/A) •				
		Sa	rc i				
	Field Name	Dynamic App then Internal	Data Source	Alert on Change No	Yes	Edit User	Edit Date 2007-12-02 14:49:40
	American Make	Dynamic App then Internal		No	Yes		2007-12-02 14:49:40
	Prividel P Serial Number			No	Yes		2007-12-02 14:49:40
	Peraing System	Dynamic App Dynamic App		No			2007-12-02 14:49:40
					Yes		
	A Host ID / SID	Dynamic App		No	Yes		2007-12-02 14:49:40
	A OS System Name	Dynamic App then Internal		No	Yes		2007-12-02 14:49:40
	A CPU Count	Dynamic App then Internal		No	Yes		2007-12-02 14:49:40
	PCPU Type/Make	Dynamic App then Internal		No	Yes		2010-01-12 14:49:40
	A CPU Speed	Dynamic App then Internal		No	Yes	em7admin	2011-01-12 17:17:12
	A Firmware / BIOS Name	Dynamic App		No	Yes		2007-12-02 14:49:40
	A Installed Memory	Dynamic App then Internal		No	Yes		2011-01-12 14:49:29
	And Disk/Drive	N/A		No			2008-01-12 14:26:29
	Asset Notes	N/A		No			2007-12-02 14:49:40
	Asset Tag	Dynamic App		No	Yes		2007-12-02 14:49:40
	Array Size	N/A		No			2007-12-02 14:49:40
	🤌 Disk Count	N/A		No			2007-12-02 14:49:40
	A Disk Size	N/A		No			2007-12-02 14:49:40
	A Method	N/A		No			2007-12-02 14:49:40
	Annual Rate	N/A		No			2007-12-02 14:49:40
	A RFID Number	N/A		No			2007-12-02 14:49:40
	A Technician	N/A		No			2007-12-02 14:49:40
	P DNS Name	N/A		No			2007-12-02 14:49:40
	A DNS Domain Name	N/A		No			2007-12-02 14:49:40
	A Profile Memo	N/A		No			2007-12-02 14:49:40
	A Facility	N/A		No			2007-12-02 14:49:40
	P Floor	N/A		No			2007-12-02 14:49:40
	A Room	N/A		No			2007-12-02 14:49:40
	A Plate	N/A		No			2007-12-02 14:49:40
29.	🔑 Panel	N/A		No			2007-12-02 14:49:40
1000	0 - ·						

For each standard asset field, you can specify:

- Whether the field can be automatically populated by SL1.
- Whether the field's value should be automatically updated by SL1.
- Whether or not SL1 should generate an event if the field's value changes.

You can define the default behavior for each standard field in the following asset pages:

- Asset Properties
- Asset Maintenance & Service
- Asset Configuration
- Asset Licenses

- Asset IP Networks
- Asset Components

The defined behavior will be applied to every asset record in SL1.

For more details on asset records and enabling automation for asset records, see the manual **Asset Management and Vendors**.

Global Settings for User Logins, Discovery, Data Collection, UI Features, and Expiration Warnings

The **Behavior Settings** page (System > Settings > Behavior) allows you to define global parameters that affect:

- User Logins
- Discovery
- Data collection
- Settings that affect the display and behavior of the user interface
- Expiration warnings for asset warranties and SSL certificates

The parameters in the **Behavior Settings** page affect all pages, devices, and discovery functionality in SL1. For most settings, you can define a one-time, manual override in the affected page. You can also override many of these settings per device. For example, you can define global parameters for nightly discovery in this page, but you can override these settings for a specific device on the **Settings** tab of the **Device Investigator** page or the **Device Properties** page (Devices> Device Manager > wrench icon) in the classic user interface.

To define or edit the settings in the **Behavior Settings** page:

- 1. Go to the **Behavior Settings** page (System > Settings > Behavior).
- 2. In the **Behavior Settings** page, edit the values in one or more of the following fields:
 - Interface URL. URL for accessing the user interface. This value should be in URL format and can be up to 64 characters in length.

NOTE: Do not include a trailing forward slash ("/") at the end of the Interface URL. When SL1 generates URLs for tickets or events (for example, in email messages), the trailing forward slash will be automatically included.

- Force Secure HTTPS. [Recommended] If enabled, forces users to use HTTPS (secure HTTP) instead of HTTP when they connect to the user interface. This eliminates the exposure of credentials between the user or API caller and the central database.
- **Password Expiration**. Specifies whether or not the password for a user account will expire and if so, when the password will expire. Choices are:
 - Disabled. Passwords do not expire or are managed externally to SL1.

- 30 Days. Passwords will expire after 30 days.
- 60 Days. Passwords will expire after 60 days.
- 90 Days. Passwords will expire after 90 days.
- 180 Days. Passwords will expire after 180 days.
- **Password Reset Interval**. The minimum amount of time that must pass before a user can change a password. For example, if the value in this field is 2 Hours, a user can change a password every two hours. This applies to users changing their own passwords and administrators changing other users' passwords. Values range from 1 hour to 24 hours, in increments of one hour.
- **Password Hash Method**. Specifies how user passwords will be encrypted for storage in the ScienceLogic database. You can choose the hashing algorithm that works best for your enterprise. Choices are:
 - SHA-512. AS of 10.2.0, this is the default value. Previous passwords will use their previous hash method until the password is changed.
 - Automatic (PHP Password API)
- **Password Minimum Length**. Specifies the minimum number of alphanumeric characters allowed for the password. You can specify any value from 1 to 99. The default value is "8" characters.
- Account Lockout Type. If a user enters incorrect login information multiple times in a row, that user will be locked out of the user interface. In this field, you can select how the lockout will be applied. Choices are:
 - Lockout by IP Address. All subsequent login attempts from the IP address will be denied once a lockout for that IP address has been identified. Use this option to isolate all access from the remote IP address for any account until a system administrator has validated the lockout and cleared it.
 - Lockout by Username and IP Address. All subsequent login attempts by this username from the IP address will be denied. This will permit other users from the same IP address to continue to access the system as long as they are not locked out.
 - Lockout by Username (default). All subsequent login attempts by this username from any IP address will be denied.
 - Disabled. Lockouts are disabled. This setting can leave your system vulnerable to attacks and as such, it is not recommended.
- Account Lockout Attempts. Number of times a user can enter incorrect login information before a lockout occurs. Choices are 1 time through 10 times.
- Login Delay. To prevent unauthorized users from using brute-force login attempts, you can set a login delay in this field. After each failed login, SL1 will not allow another attempt for the number of seconds specified in this field. Choices are:
 - Disabled. SL1 does not enforce a delay between failed logins.
 - 1 Second. After a failed login, SL1 will not allow another attempt for one second.
 - 2 seconds. After a failed login, SL1 will not allow another attempt for two seconds.

- 4 seconds. After a failed login, SL1 will not allow another attempt for four seconds.
- 8 seconds. After a failed login, SL1 will not allow another attempt for eight seconds.
- Single Instance Login (Admins). Specifies whether more than one instance of a single username can be logged in to the user interface at the same time. Defines the default behavior for users of account type "Administrator". You can specify the following types of behavior:
 - Disabled. Multiple instances of the same account name can be logged in to the user interface. There are no requirements or limitations on any of the instances. None of the instances will be automatically logged out.
 - Session can be transferred after. If you select one of these options, the second instance of a user account can log in only after the first instance of the account is inactive. In SL1, an account is considered "inactive" if the user has not performed any tasks or navigated within the user interface. You can specify how long the first instance must be inactive before the second instance can log in. When the second instance successfully logs in to the user interface, the browser where the first instance is logged in will display the following message:

"User id 'account name' logged in from a different browser and transferred this session."

NOTE: If this field is set to any value other than *disabled*, you can still override an earlier instance. If you try to log in to the user interface and there is another instance of the account already logged in to the user interface, the login page will display the following message: "User id 'account name' is already logged in to the system. To transfer the session, check 'Transfer Session' and log in."

• If you select the **Transfer Session** checkbox, this logs the first instance out of the user interface and allows the second instance to log in to the user interface.

The browser where the first instance was logged in will see the message:

"User id 'account name' logged in from a different browser and transferred this session."

- Other (manual entry). Allows you to enter a custom value, in seconds. When the first instance of a user account is inactive in the user interface for the specified number of seconds, the first instance is logged out and the second instance is allowed
- Single Instance Login (Users). Specifies whether more than one instance of a single username can be logged in to the user interface at the same time. Defines the default behavior for users of account type "User". You can specify the following types of behavior:
 - Disabled. Multiple instances of the same account name can be logged in to the user interface. There are no requirements or limitations on any of the instances. None of the instances will be automatically logged out.

Session can be transferred after. If you select one of these options, the second instance of a user account can log in only after the first instance of the account is inactive. In SL1, an account is considered "inactive" if the user has not performed any tasks or navigated within the user interface. You can specify how long the first instance must be inactive before the second instance can log in. When the second instance successfully logs in to the user interface, the browser where the first instance is logged in will display the following message:

"User id 'account name' logged in from a different browser and transferred this session."

NOTE: If this field is set to any value other than disabled, you can still override an earlier instance. If you try to log in to the user interface and there is another instance of the account already logged in to the user interface, the login page will display the following message: "User id 'account name' is already logged in to the system. To transfer the session, check 'Transfer Session' and log in."

• If you select the **Transfer Session** checkbox, this logs the first instance out of the user interface and allows the second instance to log in to the user interface.

The browser where the first instance was logged in will see the message:

"User id 'account name' logged in from a different browser and transferred this session."

- Other (manual entry). Allows you to enter a custom value, in seconds. When the first instance of a user account is inactive in the user interface for the specified number of seconds, the first instance is logged out and the second instance is allowed.
- Account Lockout Duration. Specifies how long a user will be locked out of the user interface. Choices are 1 hour – 24 hours, in one hour increments. The shorter the duration, the sooner the system is again vulnerable to a potential attack; however, a shorter duration will also allow a user to attempt to log in again without the help of a system administrator.
- Lockout Contact Information. This contact information will be displayed when a user is locked out of the user interface. Can be any combination of alphanumeric characters, up to 255 characters in length. This information should allow the user to contact his/her administrator to unlock the account.
- Login Header Title. HTML title of the login page. This text will appear at the very top of the browser on the login page.
- System Identifier. Unique name for the current SL1 system. Can be up to 128 characters in length. This field is useful for companies or organizations with multiple SL1 systems. If a value is provided in this field, SL1 will include a "system identifier" value in each event generated by the current SL1 system. This allows users to easily determine the source SL1 system associated with the event.
- **Ping & Poll Timeout (Msec.)**. This field specifies the number of milliseconds the discovery tool or availability polling will wait for a response after pinging a device. After the specified number of milliseconds have elapsed, the poll will timeout. The choices are between 100 and 5000 milliseconds.
- **SNMP Poll Timeout (Msec.)**. This field specifies the number of milliseconds the discovery tool will wait for a response after sending an SNMP query to a device. After the specified number of milliseconds have elapsed, the SNMP poll will timeout. The choices are between 100 and 5000 milliseconds.

- **SNMP Failure Retries**. This field specifies the number of times the discovery tool will try to communicate with a device after a timeout or failure. After that number of times has been met, the discovery tool will not retry unless the user manually restarts the discovery process. The choices are 0–6.
- Initially Discovered Interface Poll Rate. This field specifies the frequency with which SL1 will poll newly discovered interfaces. This setting does not affect interfaces that have been previously discovered with a different value in this field or interfaces for which the **Frequency** field has been manually edited in the Interface Properties page. Choices in this field are:
 - 1 min. SL1 will poll the newly discovered interfaces every minute.
 - 5 mins. SL1 will poll the newly discovered interfaces every five minutes. This is the default value for this field.
 - 10 mins. SL1 will poll the newly discovered interfaces every 10 minutes.
 - 15 mins. SL1 will poll the newly discovered interfaces every 15 minutes.
 - 30 mins. SL1 will poll the newly discovered interfaces every 30 minutes.
 - 60 mins. SL1 will poll the newly discovered interfaces every 60 minutes.
 - 120 mins. SL1 will poll the newly discovered interfaces every 120 minutes.
- DHCP Community Strings (Comma separated). SNMP "read only" community string to use during discovery. This is required only if DHCP servers and devices use a different SNMP community string than other devices in the network. If the community string specified in the Discovery Control Panel page (System > Manage > Classic Discovery) does not work for DHCP devices, SL1 will automatically use the community string specified in this field.
- Strip FQDN From Inbound Email Device Name. In Events from Email policies, specifies how SL1 will match the regular expression for device name. Choices are:
 - Enabled. SL1 will search the text string in the incoming email and match all characters up to the first period that appears in the text string. If multiple devices match the characters up to the first period (for example, my_device.1 and my_device.2), SL1 will align the event with the matching device with the highest Device ID.
 - Disabled. SL1 will search the text string in the incoming email for a match for the device name. The
 text string must include an exact match to the regular expression (defined in the Events from Email
 policy), including any text following a period in the device name. If SL1 does not find an exact
 match in the incoming email, SL1 creates an entry in the system log.
- Inbound Email Alert Message. In each event policy, the First Match String and Second Match String fields specify the string or regular expression used to correlate the event with a log message. To trigger an event, the text of a log message must match the value in the First Match String and Second Match String fields in that event's policy. For Events from Email policies, this field specifies whether only the email message body will be written to the device log or whether both the email message subject and email message body will be written to the device log. Choices are:
 - Email Message Body Only. Only the email message body is written to the device log. The First Match String and Second Match String fields can examine and match only the email message body.

• *Email Message Subject and Body*. Both the email message body and the email message subject are written to the device log. The *First Match String* and *Second Match String* fields can examine and match against both the email message body.

NOTE: The global setting **Inbound Email Alert Message** affects how events are triggered. This field does not affect the **Regex Pattern** field in the Event from Email policy. The **Regex Pattern** field in an Event from Email policy specifies which device log to write to.

- Event Console Ticket Life Ring Button Behavior. Specifies how the life-ring icon (¹²⁾) in the Event Console will behave. Choices are:
 - Create/View EM7 Ticket. When you click the life-ring icon (¹²⁾) for an event in the Event Console, SL1 will display the Ticket Editor page, where you can define a ticket and automatically associate it with the selected event. This is the default behavior.
 - Create/View External Ticket. If an external ticket is aligned with an event, when you click the life-ring icon (²²) for that event (from the Event Console), SL1 spawns a new window and displays the external ticket (as specified in the force_ticket_uri field). If an external ticket is not yet aligned with an event, when you click the life-ring icon (²²) for that event, SL1 sets a "request" flag for the ticket and displays an acknowledgment that a new ticket has been requested. You can then use the "request" in run book logic, to create the ticket on the external system.

NOTE: PowerFlow integrations do not use this field.

CAUTION: If you select Create/View External Ticket in the Event Console Ticket Life Ring Button Behavior field, you can no longer create tickets from the Event Console.

- Automatic Ticketing Emails. Specifies whether ticket watchers will automatically receive email notification when a ticket is created or changes status. Choices are:
 - *Enabled*. This is the default value. When you select this option, SL1 automatically sends email notifications to all watchers when a ticket is created, assigned, or updated.
 - Disabled. When you select this option, SL1 does not automatically send email notifications to all watchers when a ticket is created, assigned, or updated.

- **Prevent Browser Saved Credentials**. This checkbox specifies whether or not the user interface will allow the browser to cache login credentials and perform auto-complete in the login page. By default, the user interface will allow browsers to cache login credentials. Choices are:
 - Selected. The user interface will not allow browsers to cache credentials and use auto-complete in the login page. Use this setting to comply with PCI DSS and other security protocols.
 - Not Selected. This is the default setting. The user interface will allow browsers to cache credentials and use auto-complete in the login page. The implementation of this functionality varies between browsers.
- **Prevent Loading Interface in External Frames**. If you select this checkbox, other pages cannot be loaded in external frames in the same browser session that includes SL1. This is a security measure, to prevent clickjacking attacks.
- Hide Perpetual License Count. Specifies whether to display the device count graph in the System Usage page (System > Monitor > System Usage). The default behavior is to hide the graph in the System Usage page. Users might find this graph useful to troubleshoot licensing issues. For a description of the System Usage page, see the Monitoring Overall System Usage and Statistics section.
- Hide "New" button on the Ticket Editor. If you select this checkbox, the Ticket Editor page will not display the [New] button. This field is unselected by default.
- *Hide "other" filesystem types*. If you select this checkbox, file systems of type "other" (which includes XFS file systems) will not be discovered and monitored. This checkbox is selected by default.
- **Display Previous Login In Footer**. If you select this checkbox, the user interface will display information about the last successful login to the user interface and the last failed login (if applicable). The user interface will display the following in the lower right of the page:

Previous Login: yyyy-mm-dd hh-mm-ss from user's IP address. **Failed Login:** yyyy-mm-dd hh-mm-ss from user's IP address.

- Ignore trap agent-addr varbind. If you select this checkbox, SL1 will align incoming SNMP trap messages with the forwarding device (last hop) instead of searching for the IP address of the originator of the trap.
- Enable Selective PowerPack Field Protection. If you select this checkbox, the following fields will not be updated when you update a PowerPack:
 - Event Policy > **Operational State**
 - Event Policy > **Event Severity**
 - Event Policy > Event Message
 - Event Policy > Occurrence Count
 - Event Policy > Occurrence Time
 - Event Policy > Expiry Delay
 - Event Policy > Detection Weight
 - Event Policy > External Event ID

- Event Policy > External Category
- Event Policy > Use multi-match
- Event Policy > Use message-match
- Event Policy > **Topology Suppression**
- Dynamic Application > Properties > Operational State
- Dynamic Application > Properties > **Poll Frequency**
- Dynamic Application > Properties > Disable Data Rollup
- Dynamic Application > Collection > Custom Attribute
- Dynamic Application > Collection > Asset / Formlink
- Dynamic Application > Collection > Change Alerting
- Dynamic Application > Collection > Hide Object
- Dynamic Application > Presentation > Active State
- Dynamic Application > Threshold > Override Threshold Value
- Dynamic Application > Threshold > Numeric Range: High
- Dynamic Application > Threshold > Numeric Range: Low
- Dynamic Application > Threshold > Threshold Value
- Device Class > Device Dashboard
- Hide "Create a Ticket" in Toolbox menu. If you select this checkbox, the Toolbox menu (three stacked horizontal lines in the upper-left corner) will not display the Create a Ticket option. This field is unselected by default.
- Enable CDP Topology. If selected, SL1 will use Cisco Discovery Protocol (CDP) for each device that supports CDP. SL1 will then generate topology maps from the discovered CDP relationships.

NOTE: CDP is a proprietary protocol developed by Cisco and is not supported by all network hardware. If your network includes both CDP enabled and non-CDP network switches and routers, the topology data reported by the CDP enabled devices might not be accurate. In SL1, if a conflict exists between the collected CDP topology data and the collected layer-2 topology data, the CDP topology data takes precedence. In some cases, the ScienceLogic layer-2 data might be more accurate. Therefore, if your network includes both CDP enabled and non-CDP network switches and routers, you might want to disable CDP topology collection. For details, see the **Views** manual.

- **Enable LLDP Topology**. If selected, SL1 will use Link Layer Discovery Protocol (LLDP) for each device that supports LLDP. SL1 will then generate topology maps from the discovered LLDP relationships.
- Enable Community String Indexing (VLAN Topology). If selected, SL1 will perform discovery of VLANs during topology collection. By default, this option is not selected because the SNMP requests used to discover VLANs might cause some types of hardware to erroneously reboot.
- **Default Country**. Specifies the country that will be selected by default in each page where the user specifies a country. The user can override this default value in each page.

- System Timezone. Specifies the default timezone for SL1. In each page where the user can select a timezone, this value will be selected by default. The user can override this default value in each page. SL1 also uses this default value to perform timezone conversions when no user timezone setting is available. For example, if SL1 sends an email to an address not associated with a user, any timestamps contained in the email will use the value from the System Timezone field. You can select from a list of all timezones. The default value is "UTC".
- **NFS Detection Disable**. If selected, this checkbox prevents SL1 from monitoring and reporting on NFS "shared" file systems. SL1 will monitor and report only on local file systems.
- Port Polling Type. Specifies how SL1 should poll devices to discover open ports. The choices are:
 - Half Open. Uses a faster TCP/IP connection method and does not appear on the device's logs.
 - Full Connect. Uses the standard TCP/IP connection to detect open ports.
- Initial Discovery Scan Level. Specifies the data to be gathered during the initial discovery session. The options are:
 - 0. Model Device Only. Discover if device is up and running and if so, discover device's make and model.
 - 1. Discover Dynamic Apps. Discovery tool will search for Dynamic Applications associated with the device. Discovery will also perform 0. Model Device Only discovery.
 - 2. Initial Population of Apps. Discovery tool will retrieve subset of data from Dynamic Applications, to save time. Discovery tool will later retrieve full sets of data from each Dynamic Application. Discovery tool will also perform 1. Discover Dynamic Apps and 0. Model Device Only.
 - 3. Discover SSL Certificates. Discovery tool will search for SSL certificates and retrieve SSL data. Discovery tool will also perform 2. Initial Population of Apps, 1. Discover Dynamic Apps, and 0. Model Device Only.
 - 4. Discover Open Ports. Discovery tool will search for open ports. Discovery tool will also perform
 3. Discover SSL Certificates, 2. Initial Population of Apps, 1. Discover Dynamic Apps, and 0.
 Model Device Only.

NOTE: If your system includes a firewall and you select option 4: Discover Open Ports, discovery may be blocked and/or may be taxing to your network.

5. Advanced Port Discovery. Discovery tool will search for open ports, using a faster TCP/IP connection method. Discovery tool will also perform 3. Discover SSL Certificates, 2. Initial Population of Apps, 1. Discover Dynamic Apps, and 0. Model Device Only.

NOTE: If your system includes a firewall and you select option 5: Advanced Port Discovery, some autodiscovered devices may remain in a pending state for some time after discovery. These devices will achieve a healthy status, but this might take several hours.

- Rediscovery Scan Level (Nightly). Specifies the data to be gathered/updated each day during the nightly discovery process. The nightly discovery process will find any changes to previously discovered devices. The Rediscovery Scan Level (Nightly) field contains the same options as the Initial Discovery Scan Level field.
- **Discovery Scan Throttle**. Specifies the amount of time a discovery process should pause between each IP address in a discovery session. Pausing discovery processes between IP addresses spreads the amount of network traffic generated by discovery over a longer period of time. The choices are:
 - Disabled. Discovery processes will not pause.
 - 1000 Msec to 10000 Msec. A discovery process will pause for a random amount of time between half the selected value and the selected value.

NOTE: The Discovery Scan Throttle setting does not affect nightly auto discovery.

- **Port Scan All IPs**. Specifies whether SL1 should scan all IP addresses on a device for open ports. The choices are:
 - 0. Disabled. SL1 will scan only the Admin Primary IP address (the IP address SL1 uses to communicate with the device) for open ports.
 - 1. Enabled. SL1 will scan all discovered IP addresses for open ports.

NOTE: The Port Scan All IPs setting affects initial discovery, nightly auto discovery, and re-discovery.

• **Port Scan Timeout**. Length of time, in milliseconds, after which SL1 should stop trying to scan an IP address for open ports and begin scanning the next IP address (if applicable). Choices are between 60,000 and 1,800,000 milliseconds.

NOTE: The Port Scan Timeout setting affects initial discovery, nightly auto discovery, and re-discovery.

- **Restart Windows Services (Agent required)**. Specifies whether SL1 should automatically restart failed Windows services that have been defined on the device with a startup type of "automatic". The choices are:
 - 0. Disabled. SL1 will not automatically restart failed Windows services that have been defined on the device with a startup type of "automatic".
 - 1. Enabled. SL1 will automatically restart failed Windows services that have been defined on the device with a startup type of "automatic".

NOTE: To use this feature, the managed device must be running the agent SNMP Informant, WMI Edition. For assistance or information on purchasing and installing this agent, please contact ScienceLogic. Users must also supply a value in the **SNMP Write** field in the **Device Properties** page for the device.

- Hostname Precedence. Specifies which name SL1 will use for each discovered device. Choices are:
 - SNMP System Name. Use the device name specified in the device's SNMP System MIB.
 - DNS Reverse Lookup. Use the device name specified in the device's reverse-lookup record.

NOTE: If SNMP System Name is selected, and SL1 cannot find an SNMP name for the device, SL1 will assign the name returned by the DNS Reverse Lookup. If SL1 cannot find a DNS Reverse Lookup name for the device, SL1 will use the device's Admin Primary IP address as the device name in SL1.

- Event Interface Name Format. Specifies the format of the network interface name that you want to appear in events. If you selected Interface Alias for the deprecated Interface Name Precedence field in a previous release of SL1, the format for existing interfaces is set to {alias}. If you selected Interface Name for the deprecated Interface Name Precedence field in a previous release of SL1, the format for existing interfaces is set to {alias}. If you selected Interface Name for the deprecated Interface Name Precedence field in a previous release of SL1, the format for existing interfaces is set to {name}. The default format is {name}. You can use a combination of string text and the following tokens to define the interface name format for events, such as string_{name}, string_{alias}, {name}{alias}, or {ifdesc}:
 - {alias}
 - ∘ {name}
 - {state}
 - {ifdescr}
 - {if_id}
 - $\circ \{did\}$
 - {ifindex}
 - {ifphysaddress}
 - ∘ {iftype}
 - {ifspeed}
 - {ifhighspeed}
 - {ifoperstatus}
 - {ifadminstatus}
- **DNS Hostnames**. If SL1 will use the DNS Reverse Lookup name as the device name (see the description of the field **Hostname Precedence**), this field specifies whether SL1 will use the fullyqualified domain name or only the hostname for each discovered device. Choices are:

- Strip Device Name (Hostname). SL1 will use only the device name as the DNS hostname for each device.
- Use Full Domain Name (FQDN). SL1 will use the fully-qualified domain name as the device name for each device.
- Event Clearing Mode. Describes how clearing an event will affect correlated events. Choices are:
 - Clear Selected Only. Clear only the selected events. If a parent event is cleared, the previously suppressed child events will appear in the **Event Console**.
 - Clear All in Group. When parent event is cleared, all child events correlated with parent event will be cleared. This is the default behavior.
- Maintenance Minimum Severity. Specifies the minimum severity required for an event to be suppressed during device maintenance and user maintenance for devices. The default value is *Healthy*, which causes all events to be suppressed. Choices are *Healthy*, *Notice*, *Minor*, *Major*, or *Critical*.
- Patch Maintenance Minimum Severity. If you schedule Device Maintenance and have defined a Patch Window within the larger maintenance interval, this field allows you to specify the event severity that will trigger the beginning of the Patch Window. The first event that both matches the severity in this field and occurs within the larger maintenance window triggers the start of the Patch Window. Choices are Healthy, Notice, Minor, Major, or Critical.
- SSL Certificate Expiry Soon. Specifies, in number of days, when SL1 should generate an event for an SSL Certificate that is about to expire. The choices range from 1 day to 9 months.
- SSL Certificate Expiry Imminent. Specifies, in number of days, when SL1 should generate a more urgent event for an SSL Certificate that is about to expire. The choices range from 1 day to 9 months.
- Asset Warranty Expiry. Specifies, in number of days, when SL1 should generate an event for an asset warranty that is about to expire. The choices range from 1 day to 9 months.
- **Domain Name Expiry**. Specifies, in number of days, when SL1 should generate an event for a domain's registration that is about to expire. The choices range from 1 day to 9 months.
- Validate Phone Number. Specifies whether or not phone numbers entered into the user interface must be in US format. Choices are:
 - Disabled. Phone numbers are not required to be in US format.
 - Enabled. Phone numbers must be in US format.
- Dashboard Maximum Series Count Per Widget. This field allows you to select the maximum number of time-series lines that can appear in a single *Multi-series Performance* widget. Choices are 8–25. Increasing this setting might cause longer load times in the [Dashboards tab] page.
- Prefer Global Device Summary Dashboard Over Category/Class. If you select this checkbox, the global default device dashboard will be displayed as the default in the Device Summary page instead of the device dashboard assigned to the device category or device class of the device. For more information about device dashboards, see the Dashboards manual.

- Enable CBQoS Collection. If selected, SL1 will collect configuration data about Class-Based Quality-of-Service (CBQoS) from interfaces that are configured for CBQoS. If selected, you can enable collection of CBQoS metrics per-interface. The collected CBQoS metrics are displayed in Device Performance reports associated with the device that contains those interfaces. This setting is disabled by default. (For more information about Device Performance reports, see the manual Monitoring Device Infrastructure Health.)
- Enable Variable Rate Interface Counters. If selected, enables more accurate collection of data from interfaces. If enabled, when SL1 retrieves data from an interface, that data is stored in the ScienceLogic database along with the timestamp associated with the exact collection time. Before normalization occurs, SL1 applies an interpolation function that spaces the data at regular time intervals. For example, suppose you have specified that SL1 should collect interface data every five minutes. However, due to network traffic across the Data Collectors, SL1 might collect data from an interface at 13:01 and then 13:05. Because the ScienceLogic normalization process expects data that has been collected every five minutes, SL1 first applies an interpolation to the data to prepare the data for normalization.
- **Enhanced OID Translation**. If selected, ensures that varbind OIDs that use multi-dimensional indexes are translated correctly. The symbolic translation of the known portion of the OID is included in the log message associated with the trap.

NOTE: Enabling the **Enhanced OID Translation** option might affect performance on large environments with a large number of traps.

- Enable Concurrent SNMP Collection. If selected, enables Concurrent SNMP Collection for all SNMP collection. Concurrent SNMP Collection allows multiple collection tasks to run at the same time with a reduced load on Data Collectors. Concurrent SNMP Collection also prevents missed polls and data gaps because collection will execute more quickly. For details see the manual SNMP Dynamic Application Development.
- **Report Size Estimation**. If selected, enables the **Row Count Estimate** field for custom reports on the Run Report page (Reports > Run Report). This field provides an estimate of the number of rows that will appear in the report before SL1 generates the report. The estimate changes based on the selections you make for the report. You can use this field to manage the size of the generated report by adding or removing items from the report as needed.
- 3. Click the [Save] button to save changes in this page.

Global Settings for Data Retention

The **Data Retention Settings** page (System > Settings > Data Retention) allows you to define parameters for log and data retention.

These settings apply to all logs and all collected data. However, you can override these system settings on a caseby-case basis. For example, you can define data-retention thresholds for a device in the **Device Thresholds** page. The settings you define for the specific device override the settings in the **Data Retention Settings** page. NOTE: For details on data roll-up and data normalization, see Normalization and Roll-Up of Performance Data.

From the **Data Retention Settings** page, you can edit how long the platform stores log entries and collected data. To edit the settings for data retention:

1. Go to the **Data Retention Settings** page (System > Settings > Data Retention).

Data Retention			
Data Retention Settings			Refresh Cuide
Collection Data Retention			
Raw Performance Data		7 days (Current 7 days)	
Hourly Rollup Performance Data	<u> </u>	90 days [Current 90 days]	
Daily Rollup Performance Data		24 months* (Current: 24 month	15"]
Configuration Data	<u> </u>	7 days (Current: 7 days)	
Journal Data		60 days [Current: 60 days]	
Bandwidth Data		31 days [Current 31 days]	
Hourly Rollup Bandwidth Data	<u>a</u>	90 days (Current: 60 days)	
Daily Rollup Bandwidth Data		24 months* (Current: 24 month	75 7
Bandwidth Billing Data	<u>a</u>	24 months* (Current: 24 month	N9 ⁷
Device Logs Age		90 days [Current: 90 days]	
Device Logs Max		10000 records (Current: 10000 rec	and 4
Bay ITSM Data			
Raw ITSM Data ITSM Service Metrics Data		31 days (Current: 21 days)	
ITSM Service Metrics Data Hourly Rollup ITSM Service Metrics Data		30 days [Current: 30 days] 90 days [Current: 50 days]	
Daily Rollup ITSM Service Metrics Data		90 days (Current: 60 days) 12 months* (Current: 12 month	
ITSM Key Metrics Data		30 days ICurrent 30 days	
Hourly Rollup ITSM Key Metrics Data		20 days (Current: 50 days)	
Daily Rollup ITSM Key Metrics Data		24 months* (Current: 24 month	
	_	<u>.</u>	Save
Subscription Data Retention			
Subscriber Device Configuration Data		6 months* (Current: 0 months	
Subscriber Device Usage Data		6 months* (Current: 6 months	
Subscriber System Configuration Data		3 months* (Current: 2 months	
Subscriber System Usage Data		3 months* (Current: 3 months	
Subscriber Device Type Data		3 months* (Current: 3 months	
Subscriber Daily Delivery Data		3 months* [Gurrent: 3 months	
	_		Save
Feature Data Retention			
Feature Configuration Data	-31	months* (Current: 0 months	
Feature Performance Data		O months* (Current: 0 months	
Feature Performance Data Aggregation		O months' (Current: 0 months	
	-	C	Save
			- 274/G
			- 1 wiews = 3-5 cells

- 2. On the **Data Retention Settings** page, you can drag sliders to change the value of each field or manually enter values in the fields to the right of the sliders. You can edit the value for one or more of the following fields:
 - Audit Logs. Number of months to retain log entries in the Audit Logs page (System > Monitor > Audit Logs). Log entries that are older than the specified number of months are automatically deleted. The default value is 3 months.
 - Event Logs. Number of days to retain event logs. Event history data is used to generate the Event
 Overview page (System > Monitor > Event Overview). Log entries that are older than the specified
 number of months are automatically deleted. The default value is 3 months.
 - Access Logs. Number of months to retain log entries in the Access Sessions page (System > Monitor > Access Logs). Log entries that are older than the specified number of months are automatically deleted. The default value is 12 months.
 - **System Logs**. Number of days to retain log entries in the **System Logs** page (System > Monitor > System Logs). Log entries that are older than the specified number of days are automatically deleted. The default value is 31 days.
 - Collection Unit Data Buffer. Number of days each Data Collector and Message Collector should store collected data. Choices are 1-10 days. Data that has been retrieved by the Database Server will be stored on the Data Collector(s) and optional Message Collector(s) for the specified number of days and then automatically deleted from the server(s). This setting does not apply to All-In-One Appliances. The default value is 2 days.

- Ad-hoc and Scheduled Reports. Number of days SL1 will retain Quick Reports and Scheduled Reports in the Scheduled Report Archive page (Scheduled Job > Report Archive > Archived Job button). Possible values are 0 - 365, in days. If you use the default value of 0, SL1 will remove files older than 30 days from the populated directory: /opt/em7/gui/ap/www/em7/libs/od_ templates/populated.
- *Raw Performance Data*. Number of days to retain performance data collected from devices. This setting applies to all performance data types, except for bandwidth data. Performance data that is older than the specified number of days is automatically deleted. This is the default system-wide value. The value in the **Device Thresholds** page for each device can override this value. The default value is 7 days.
- Hourly Rollup Performance Data. Number of days to retain hourly normalized performance data for devices. This setting applies to all performance data types, except for bandwidth data. Hourly normalized performance data that is older than the specified number of days is automatically deleted. This is the default system-wide value. The value in the **Device Thresholds** page for each device can override this value. The default value is 120 days.
- Daily Rollup Performance Data. Number of months to retain daily normalized performance data for devices. This setting applies to all performance data types, except for bandwidth data. Daily normalized performance data that is older than the specified number of months is automatically deleted. This is the default system-wide value. The value in the **Device Thresholds** page for each device can override this value. The default value is 24 months.
- **Configuration Data**. Number of days to retain data from Dynamic Applications of type "configuration". The value in the **Device Thresholds** page for each device can override this value. The default value is 7 days.
- Journal Data. Number of days to retain collected data from Dynamic Applications of type "journal". The value in the **Device Thresholds** page for each device can override this value. The default value is 60 days.
- **Bandwidth Data**. Number of days to retain bandwidth data and CBQoS data collected from each interface on a device. Bandwidth data that is older than the specified number of days is automatically deleted. The value in the **Device Thresholds** page for each device can override this value. The default value is 31 days.
- Hourly Rollup Bandwidth Data. Number of days to retain hourly normalized data and hourly normalized CBQoS data for each interface on a device. Hourly normalized data that is older than the specified number of days is automatically deleted. The value in the Device Thresholds page for each device can override this value. The default value is 90 days.
- **Daily Rollup Bandwidth Data**. Number of months to retain daily normalized data and daily normalized CBQoS data for each interface on a device. Daily normalized data that is older than the specified number of months is automatically deleted. The value in the **Device Thresholds** page for each device can override this value. The default value is 24 months.
- **Bandwidth Billing Data**. Number of months to retain data collected by each bandwidth billing policy. Bandwidth billing data that is older than the specified number of months is automatically deleted. The default value is 24 months.
- **Device Logs Age**. Number of days to retain each device log. Log records that are older than the specified number of days are automatically deleted. The value in the **Device Thresholds** page for each device can override this value. The default value is 90 days.

- **Device Logs Max**. Maximum number of records to store in each device log. When this number is exceeded, the oldest entries will be deleted. The value in the **Device Thresholds** page for each device can override this value. The default value is 10,000 records.
- **Raw ITSM Data**. Before the value for a metric in an IT Service policy is calculated, a copy of all the device data that will be aggregated is saved. This setting is the number of days to retain the unaggregated copies of device data associated with each IT Service. The default value is 31 days.
- **ITSM Service Metrics Data**. Number of days to retain values for metrics in IT Service policies. The default value is 30 days, with a maximum of 30 days.
- Hourly Rollup ITSM Service Metrics Data. Number of days to retain hourly normalized values for metrics in IT Service policies. The default value is 90 days, with a maximum of 90 days.
- Daily Rollup ITSM Service Metrics Data. Number of months to retain daily normalized values for metrics in IT Service policies. The default value is 12 months.
- *ITSM Key Metrics Data*. Number of days to retain values for key metrics in IT Service policies (Health, Availability, and Risk). The default value is 30 days, with a maximum of 30 days.
- Hourly Rollup ITSM Key Metrics Data. Number of days to retain hourly normalized values for key metrics in IT Service policies (Health, Availability, and Risk). The default value is 90 days, with a maximum of 180 days.
- Daily Rollup ITSM Key Metrics Data. Number of months to retain daily normalized values for key metrics in IT Service policies (Health, Availability, and Risk). The default value is 24 months.
- Subscriber Device Configuration Data. For users with a subscriber license. Number of months to retain the files and database tables that contain configuration information for a device. Default value is 6 months.
- **Subscriber Device Usage Data**. For users with a subscriber license. Number of months to retain the files and database tables that contain usage information for a device. Default value is 6 months.
- Subscriber System Configuration Data. For users with a subscriber license. Number of months to retain the files and database tables that contain configuration information for the SL1 system. Default value is 3 months.
- Subscriber System Usage Data. For users with a subscriber license. Number of months to retain the files and database tables that contain usage information for the SL1 system. Default value is 3 months.
- Subscriber Device Type Data. For users with a subscriber license. Number of months to retain the files and database tables that map each device to a device category, as per your subscriber license. Default value is 3 months.
- Subscriber Daily Delivery Data. For users with a subscriber license. Number of months to retain the "crunched" license usage data that is calculated each day using the Subscriber Device Configuration Data, Subscriber System Configuration Data, Subscriber System Usage Data, and Subscriber Device Type Data. SL1 will not prune data that has not yet been delivered to the ScienceLogic Licensing and Billing server. Default value is 3 months.
- 3. Click the [Save] button to save any changes to the data-retention settings.

NOTE: In SL1, normalized data does not include polling sessions that were missed or skipped. So for normalized data, null values are not included when calculating maximum values, minimum values, or average values.

TIP: You might want to retain normalized data for longer periods of time and non-normalized data for shorter periods of time. This allows you to save space and still create historical reports.

Normalization and Roll-Up of Performance Data

Normalization and roll-up are the ways in which SL1 processes collected performance data for display and storage. Note the following important distinctions:

- Raw data is the data exactly as it was collected from a device or application.
- Normalized and rolled up data is data for which SL1 has calculated summary statistics (sample size, count, maximum value, minimum value, mean value, average value, sum, and standard deviation) over a period of time.

Collector	Collected Data and Intervals
Dynamic Applications	Collects raw performance data from a device at the following intervals:
	• 1 minute
	2 minutes
	• 3 minutes
	• 5 minutes
	• 10 minutes
	• 15 minutes
	• 30 minutes
	• 1 hour
	• 2 hours
	• 6 hours
	• 12 hours
	• 24 hours
	For performance Dynamic Applications, you specify this interval in the Poll Frequency field, in the Properties Editor page (System >
	Manage > Applications > Create or use the 🥍).

Collection of Raw Data

Collector	Collected Data and Intervals
IT Services	 IT Service policies can generate raw performance data for an IT service by aggregating raw performance data from devices in the policy at the following intervals: 1 minute
	• 2 minutes
	• 3 minutes
	• 5 minutes
	• 10 minutes
	• 15 minutes
	• 30 minutes
	• 1 hour
	• 2 hours
	• 6 hours
	• 12 hours
	• 24 hours
	You can specify the interval at which the IT Service policy collects and aggregates data in the Aggregation Frequency field, in the IT Service Editor page (Registry > IT Services > IT Service Manager > Create or use the \checkmark).
Bandwidth	Collects raw bandwidth data from a network interface at the following intervals: • 1 minute
	• 5 minutes
	• 10 minutes
	• 15 minutes
	• 30 minutes
	• 60 minutes
	• 120 minutes
	You can specify the frequency at which SL1 collects raw data for a specific interface by selecting the interval in the Frequency field, in the Interface Properties page (Registry > Networks > Interfaces > interface wrench icon and select the <i>P</i> for the given interface).
Additional Performance Data	SL1 collects additional raw performance data about availability, latency, file systems, and statistics generated by monitoring policies for DNS availability, Email round-trip time, system processes, system services, port availability, web-content availability, and SOAP/XML transactions. By default, SL1 collects this data every 5 minutes.

Data Normalization and Rollup

SL1 rolls up performance data so that reports with a larger timespan do not become difficult to view and to save storage space in the database. When SL1 rolls up data, SL1 groups data into larger sets and calculates the average value for the larger set.

SL1 supports two types of rollup:

- Hourly. Groups and averages data that is collected at intervals of 60 minutes or less. SL1 rolls up data and calculates an average hourly value for each metric. Hourly samples include samples from the top of the hour to the end of the hour. For example, for an hourly rollup of data collected at 1 minute intervals between 1:00 and 2:00, the first data point would be the one collected at 01:00:00 and the last would end at 01:59:00.
- **Daily**. Daily rollup groups and averages all collected data. SL1 rolls up data and calculates an average daily value for each metric. Daily samples include samples from the beginning of the day until the end of the day. For example, for a daily rollup of data collected at 1 minute intervals, the first data point would be the one collected at 00:00:00 and the last data point would the one collected at 23:59:00.

Frequency of Raw Collection	Rollup
Every 1 minute	60 minutes, 24 hours
Every 2 minutes	60 minutes, 24 hours
Every 3 minutes	60 minutes, 24 hours
Every 5 minutes	60 minutes, 24 hours
Every 10 minutes	60 minutes, 24 hours
Every 15 minutes	60 minutes, 24 hours
Every 30 minutes	60 minutes, 24 hours
Every 60 minutes	60 minutes, 24 hours
Every 120 or longer	24 hours

SL1 rolls up raw performance data as follows:

Before SL1 normalizes date, SL1 transforms the data. To transform the data, SL1 does the following:

- For bandwidth data and data from Dynamic Applications of type "Performance", SL1 derives rates from counter metrics. The rate from counter metrics are expressed in units-per-polling_interval. For example, rates for 5 minute collections are expressed as units-per-5-minutes.
- For data from Dynamic Applications of type "Performance", SL1 evaluates presentation formulas. Counter metrics are first transformed into rates before evaluation.

NOTE: During the data transform steps, SL1 does not directly rollup the raw data in the database tables.

When SL1 rolls up data, SL1 must normalize that data, as follows:

NOTE: As a new piece of data is collected by SL1, the hourly normalization and daily normalization is calculated. SL1 does not wait for the end of an hour or the end of a day to calculate the hourly and daily normalization.

- Groups and orders the data
- Determines the sample size
- Calculates the count
- Determines the maximum value
- Determines the minimum value
- Calculates the mean value
- Calculates the average value
- Calculates the sum
- Determines the standard deviation

NOTE: In SL1, normalized data does not include polling sessions that were missed or skipped. For normalized data, null values are not included when calculating sample size, maximum values, minimum values, or average values.

Example

Suppose that every five minutes, SL1 collects data about file system usage on the device named *my_device*. As each raw data point is collected, SL1 normalizes and rolls up the collected data for file system usage for my_device. SL1 does the following:

- 1. Apply any necessary data transforms (as discussed in the previous section).
- 2. Repeat the following for both hourly normalization and daily normalization:
 - a. If this is the first data point for an hourly normalization or a daily normalization, insert summary statistics for that one data point
 - Sample size = 1
 - Average = value of new data point
 - Max = value of new data point
 - Min = value of new data point
 - Sum = value of new data point
 - \circ Standard Deviation = 0
 - b. For all subsequent data points for an hourly normalization or a daily normalization, update the summary statistics of the existing rollup bucket
- 3. If there no gaps in collection, the summary statistics for hourly normalization will represent 12 data points and the summary statistics for daily normalization will represent 288 data points.

Storage of Raw and Rolled Up Data

There are two ways you can define how long SL1 should store raw data and rolled up and normalized data:

- You can define system-wide, default settings in the **Data Retention Settings** page (System > Settings > Data Retention). These settings apply to all collected data. However, you can override these system settings in the **Device Thresholds** page (Registry > Devices > Device Manager > wrench icon > Thresholds).
- For IT Service policies, aggregated device data is saved to a new database table specifically for the IT service policy. For each IT Service policy, data is normalized and rolled up. You define the data retention settings for an individual IT Service policy in the IT Service Editor page (Registry > IT Services > IT Service Manager > Create or). These settings override the data retention settings in the Data Retention Settings page (System > Settings > Data Retention).

Global Settings for Inbound Email and Outbound Email

The **Email Settings** page (System > Settings > Email) allows you to define how SL1 will send and receive email. SL1 automatically sends email when tickets are updated, when automation actions are triggered, and to monitor email round-trip time. Email can be sent to the platform to create tickets and/or events.

From the **Email Settings** page, you can edit the global email parameters. To do so:

1. Go to the **Email Settings** page (System > Settings > Email).

Email Settings	Refresh Guide
Authorized Email Domains	your-domain-goes-here.com
System From Email Address	root@your-domain-goes-here.com
Email Formal Name	EM7 Event Notifier
Email Gateway	localhost
Email Gateway Alt.	192.168.0.2
Escalation Notify Subject	TICKET ESCALATED: #%t %M %T %F
، <u>لــــــــــــــــــــــــــــــــــــ</u>	

- 2. In the Email Settings page, you can edit the value for one or more of the following fields:
 - Authorized Email Domains. One or more SMTP domains that will be used by SL1. SL1 will use these domains to receive incoming email. This list of domains should include:
 - All domains used for loopback addresses in email round-trip monitoring policies.
 - All domains used to generate tickets from emails.
 - All domains used to receive event messages from third-party monitoring systems.

- Each entry in this field must be a fully-qualified email domain and cannot exceed 64 characters. If you include a list of domains, separate the list with commas.
- Each domain in this field must be managed by the Database Server. This means that a DNS MX record must already exist or be created for each domain specified in this field. Each DNS MX record must map the domain to the Database Server. When creating the DNS MX record, use the fully-qualified name of the Database Server as the name of the email server.
- System From Email Address. The email address from which SL1 will send all outbound email.
- **Email Formal Name**. Name that will appear in the "from" field in email messages sent from SL1. This value can be any alphanumeric value, up to 64 characters in length.
- **Email Gateway**. IP address or fully-qualified name of SL1's SMTP Relay server. If SL1 is to send outgoing messages, this field must be defined. Examples of when SL1 sends outgoing email messages are:
 - Automatically in response to Tickets from Email policies.
 - Automatically in response to changes in a ticket (ticket is assigned, edited, or resolved).
 - Automatically based on Ticket Escalation policies.
 - Automatically when executing Email Round-Trip Monitoring policies.
 - Automatically when executing Run Book policies that include email actions.
 - Automatically based on Report Jobs policies.
 - Manually, when a user selects the **Send Message** page from the ticket panel pages.

Each Database Server and All-In-One Appliance includes a built-in SMTP Relay server. The fullyqualified name of SL1 SMTP Relay server is the same as the fully-qualified name of the Database Server or All-In-One Appliance.

If SL1 cannot use its built-in SMTP relay server to route email messages directly to their destination server (for example, due to firewall rules or DNS limitations), SL1 can use another relay server. You can specify the IP address or fully-qualified name of the relay server in this field. Make sure you have configured your network to allow the Database Server or All-In-One Appliance to access this SMTP Relay server.

- Email Gateway Alt. IP address or fully-qualified name of the secondary SMTP Relay server. If the SMTP Relay server specified in the previous field fails or is unavailable, SL1 will use the secondary SMTP Relay server. Make sure you have configured your network to allow the Database Server or All-In-One Appliance to access this SMTP Relay server.
- **Escalation Notify Subject**. Default "Subject" text in emails generated by Ticket Escalation policies. This field can include any combination of variables and text. The field can include up to 64 characters, including one or more variables:

Variable	Source	Description
%1 (one)	Event	Entity type.
%2	Event	Sub-entity type.

The **Escalation Notify Subject** field can include one or more of the following variables:

Variable	Source	Description	
%3	Event Policy	Event policy ID.	
%4	Event	Text string of the user name that cleared the event.	
%5	Event	Timestamp of when event was deleted.	
%6	Event	Timestamp for event becoming active.	
%7	Event	Event severity (1-5), for compatibility with previous versions of the platform. 1=critical, 2=major, 3=minor, 4=notify, 5=healthy.	
%A	Account	Username.	
%a	Entity	IP address.	
%В	Organization	Organization billing ID.	
%b	Organization	Impacted organization.	
%С	Organization	Organization CRM ID.	
%с	Event	Event counter.	
%D	Event	Timestamp of first event occurrence.	
%d	Event	Timestamp of last event occurrence.	
%Е	Event Policy	External ID from event policy.	
%е	Event	Event ID.	
%F	Dynamic Alert	Dynamic Application alert id.	
%f	Event Policy	Specifies whether event is stateful, that is, has an associated event that will clear the current event. 1 (one) = stateful; 0 (zero) = not stateful.	
%G	Event Policy	Event Category.	
%g	Asset	Asset serial.	
%Н	Event	URL link to event.	
%h	Asset	Device ID associated with the asset.	
%l (uppercase "eye")	Dynamic Alert	Table index for a Dynamic Application.	
%i (lowercase "eye")	Asset	Asset Location.	
%7	Ticket	Ticket subject.	
%К	Asset	Asset Floor.	
%k	Asset	Asset Room.	
%M	Event	Event message.	
%m	Automation	Automation policy note.	
%N	Action	Automation action name.	
%n	Automation	Automation policy name.	
%O (uppercase "oh")	Organization	Organization name.	
%o (lowercase "oh")	Organization	Organization ID.	
%P	Asset	Asset plate.	

Variable	Source	Description
%р	Asset	Asset panel.
%Q	Asset	Asset punch.
%q	Asset	Asset zone.
%R	Event Policy	Event policy cause/action text.
%r	System	Unique ID / name for the current SL1 system.
%S	Event	Severity (Healthy - Critical).
%s	Event	Severity (0 - 4). 0=healthy, 1=notify, 2=minor, 3=major, 4=critical.
%Т	Dynamic Alert	Dynamic Application alert threshold value.
%t	Ticket	Ticket ID.
%U	Asset	Asset rack.
%υ	Asset	Asset shelf.
%∨	Dynamic Alert	Dynamic Application alert result value.
%v	Asset	Asset tag.
%W	Asset	Asset make.
%w	Asset	Asset model.
%X	Event	Entity name.
%x	Event	Entity ID.
%Y	Event	Sub-entity name.
%у	Event	Sub-entity ID.
%Z	Event	Event source (1 - 8).
%z	Event	Event source (Syslog - Group).

Global Settings for Login Alert Messages

In SL1, administrators can add a customizable click-through alert message as a security measure at logon. Users will not be able to access the system until the user click the **[OK]** button to agree to the terms and conditions of use for that system.

To add a custom login alert message to SL1:

1. Go to the Login Alert Editor page (System > Settings > Login Alert Message).

2. In the **Alert Message** field, type the text of your login alert message:

Login Alert Editor		Guide
Alert Message:	This computer network belongs to the Weyland-Yutani Corporation and may be used only by Weyland-Yutani Corporation employees and only for work- related purposes. The Weyland-Yutani Corporation reserves the right to monitor use of this network to ensure network security and to respond to specific allegations of employee misuse. Use of this network shall constitute consent to monitoring for such purposes. In addition, the <u>Weyland-Yutani</u> Corporation reserves the right to consent to a valid law enforcement request to search the network for evidence of a crime stored within the network.	
	Save	00000000000000000000000000000000000000

- 3. After entering the login alert text, click the **[Save]** button.
- 4. When a user logs in, the alert message will display:

Message from webpage	23
This computer network belongs to the Weyland-Yutani Corporation and may be used only by Weyland-Yutani Corporation employees and only for work-related purposes. The Weyland-Yutani Corporation reserves the right to monitor use of this network to ensure network security and to respond to specific allegations of employee misuse. Use of this network shall constitute consent to monitoring for such purposes. In addition, the Weyland-Yutani Corporation reserves the right to consent to a valid law enforcement request to search the network for evidence of a crime stored within the network.	
ОК	

Global Settings for Password Reset Emails

The **Password Reset Email Editor** page (Password Reset Email Editor) allows ScienceLogic administrators to define the email message that is sent to ScienceLogic users who select the "I forgot my password" option from the **Login** page.

If the user enters a valid ScienceLogic username in the **Login** page and then selects the *I* forgot my password option, SL1 will check the account information for that user. If the user's account information includes an email address, SL1 will send the user an email message. The email message will include a link that allows the user to redefine their ScienceLogic password. The new password must meet the requirements defined in the **Password Strength** field and the **Password Shadowing** field for the user account. SL1 will prompt the user to meet these requirements and display a description of those requirements.

The user can select the *l* forgot my password option up to ten times without responding to the sent email (using the link in the email to reset the password). After ten times, SL1 will no longer send another email message to the user's email address. The user can continue to select the *l* forgot my password option, but SL1 will not resend an email.

If the user's account information does not include an email address, SL1 displays the message "Password recovery is not available for your account, please contact your system administrator".

If the user does not enter a valid ScienceLogic username in the **Login** page, the *I* forgot my password option is still displayed, but SL1 does not send an email. This prevents intruders from guessing ScienceLogic account names.

If the user exceeds the number of login tries (defined in the **Behavior Settings** page), the "I forgot my password" option is not displayed in the **Login** page.

Defining the Email Message for "I forgot my password"

In the **Password Reset Email Editor** page (System > Settings > Password Reset Email), you can define the email that is sent from SL1 when an end user selects the *I* forgot my password option from the **Login** page.

To define the email message sent by SL1:

1. Go to the **Password Reset Email Editor** page (System > Settings > Password Reset Email).

Password Reset Er	nail Editor	Guide
0.1-1		
Priority: Subject:	[[High]] T EM7 %0 [automated message]	
Message:	Hallo %fo %la	
	Your password for account %A has been reset. Use the following link to log-in and choose a new password: %L	
	76L	
		10
		l
		l
	Save	l
11		I

- 2. Supply a value in each of the following fields:
 - **Priority**. This will be the priority of the email message. Choices are:
 - *High*. Emails will be marked as high priority.
 - Normal. Emails will be marked as normal priority.
 - $\circ~$ Low. Emails will be marked as low priority.
 - **Subject**. This will be the subject of the email message.
 - **Message**. This will be the body of the email message. **The body must include the variable %L**. This variable inserts the link to the page that allows the user to reset their ScienceLogic password.
- 3. You can include the following variables in the **Subject** field and the **Message** field:
 - %L (uppercase "el"). The link to the page that allows the user to reset their password.
 - %O (uppercase "oh"). The user's primary organization, as defined in the Account Permissions page for the user.

- %fn (lowercase "eff" "en"). The user's first name, as defined in the Account Permissions page for the user.
- %In (lowercase "el "en". The user's last name, as defined in the Account Permissions page for the user.
- 4. Click the **[Save]** button to save the email template.
- 5. When a user follows the link in the email, SL1 displays the **Login** page, with the message "Your account has been reset. Please create a new password." The user must then enter their new password twice. The new password is recorded in SL1 and replaces the previous (forgotten) password.

For example, you could define the following:

Subject. ScienceLogic | %O (automated message)

Message. Hello %fn %ln,

Your password for account %A has been reset.

Please use the following link to log in and choose a new password:

%L.

For the user "Keyser Soze", who is a member of the System organization, the following email would be sent:

Subject: ScienceLogic | System (automated message).

Hello Keyser Soze,

Your password for account ksoze has been reset.

Please use the following link to login and choose a new password:

https://name_or_IP_of_EM7_Administration_Portal/login.em7?prs=hash

Global Settings for System Thresholds

The **System Threshold Defaults** page (System > Settings > Thresholds > System) allows you to define global thresholds for system latency, file system usage, counter rollovers, ICMP availability, and number of component devices.

These settings apply to all devices. However, you can override these system settings on a case-by-case basis. For example, you can define thresholds for a device's file systems in the **[Thresholds]** tab of the **Device Investigator** (or the **Device Thresholds** page in the classic SL1 user interface). The settings you define for the specific device override the settings in the **System Threshold Defaults** page.

To edit the global settings for system thresholds:

1. Go to the **System Threshold Defaults** page (System > Settings > Thresholds > System).

System Threshold Defaults		Reset Guide
Operating System Thresholds		
System Latency 100 ms	[Default: 100] System Availability	[Default: 99]
Filesystem Major 88 %	[Default: 85] Filesystem Critical 96 %	[Defaul: 95]
Counter Rollover Thresholds		
Rollover Percent 20 %	[Default 20] Out-of-order Percent	[Default: 50]
ICMP Availability Thresholds		
Availability Ping Count	[Default 1] Avail Required Ping	[Default: 100]
Process Runtime 80 %	[Default: 80] Process Runtime 100 %	[Default: 100]
Component Device Thresholds		
Component Purge Timeout 0 hours	[Default: 24] Component Vanish	[Default: 1440]
	Save	

- 2. In the **System Threshold Defaults** page, you can drag sliders to change to value of each field or edit a field manually. You can edit the value for one or more of the following fields:
 - Interface Inventory Timeout. Specifies the maximum amount of time that the discovery processes will spend polling a device for the list of interfaces. After the specified time, SL1 will stop polling the device, will not model the device, and will continue with discovery. The default value is 600,000 ms (10 minutes).
 - During initial discovery, initiated from the Discovery Session Editor page (System > Manage > Classic Discovery > Create), SL1 uses the value in this field if there is no differing value specified in the **Discovery Session Editor** page.

- During re-discovery (clicking the binocular icon (A) in the Device Properties page), SL1 will use the value in this field if there no value is specified in the [Thresholds] tab of the Device Investigator (or the Device Thresholds page in the classic SL1 user interface) for the device.
- During nightly auto-discovery (run automatically by SL1 every night, to update device information), SL1 uses the value in this field if no differing value is specified in the [Thresholds] tab of the Device Investigator (or the Device Thresholds page in the classic SL1 user interface) for a device.
- Maximum Allowed Interfaces. Specifies the maximum number of interfaces per device. If a device exceeds this number of interfaces, SL1 will stop scanning the device, will not model the device, and will continue with discovery. The default value is 10,000.
 - During initial discovery, initiated from the Discovery Session Editor page (System > Manage > Classic Discovery > Create), SL1 uses the value in this field if there is no differing value specified in the Discovery Session Editor page.
 - During re-discovery (clicking the binocular icon (A) in the Device Properties page), SL1 will use the value in this field if there is no differing value is specified in the [Thresholds] tab of the Device Investigator (or the Device Thresholds page in the classic SL1 user interface) for the device.
 - During nightly auto-discovery (run automatically by SL1 every night, to update device information), SL1 uses the value in this field if no differing value is specified in the [Thresholds] tab of the Device Investigator (or the Device Thresholds page in the classic SL1 user interface) for a device.
- **System Latency**. During polling, the platform initially pings monitored devices. The value in this field is the maximum number of milliseconds for the device to respond to SL1's ping (round-trip time divided by 2). The default value is 100 ms. When the latency threshold is exceeded, SL1 generates an event for that device.
- System Availability. During polling, SL1 monitors devices for availability. Availability means the device's ability to accept connections and data from the network. The value in this field is the percent availability required of each device. The default value is 99%. When a device falls below this level of availability, SL1 generates an event for that device.

During polling, a device has two possible availability values:

- 100%. Device is up and running.
- 0%. Device is not accepting connections and data from the network.

NOTE: Component devices use a Dynamic Application collection object to measure availability. SL1 polls component devices for availability at the frequency defined in the Dynamic Application. For details, see the chapter on *Monitoring Device Availability and Latency* in the *Monitoring Device Infrastructure Health* manual.

NOTE: The Ping & Poll Timeout (Msec) setting in the Behavior Settings page (System > Settings > Behavior) affects how SL1 monitors device availability. This field specifies the number of milliseconds the discovery tool and availability polls will wait for a response after pinging a device. After the specified number of milliseconds have elapsed, the poll will timeout.

- *File System Major*. Threshold that will trigger a "low disk space" event. The default threshold is 85%. When a device has used more disk space than the specified percentage, SL1 will generate a "file system usage exceeded threshold" event with a status of "major".
- *File System Critical*. Threshold that will trigger a "low disk space" event. The default threshold is 95%. When a device has used more disk-space than the specified percentage, SL1 will generate a "file system usage exceeded threshold" event with a status of "critical".

NOTE: If you hide a file system in the **Device Hardware** page (Devices > Hardware), SL1 does not generate events for that file system.

- **Rollover Percent**. For any collected data that uses a 32-bit counter, you can specify how SL1 determines that the counter has "rolled over", that is, has reached its maximum value, is reset to zero, and restarts counting. When this happens, the collected values go from the maximum value to a lower value. However, there are multiple circumstances under which a counter value can go from a higher value to a lower value:
 - Maximum value has been exceeded and counter was reset to zero.
 - Retrieved value was manually reset to zero on the external device.
 - Data was collected out-of-order, that is, due to a slowdown somewhere in the network, two counter values were stored out of sequence.

NOTE: For 64-bit counters, when the counter values go from a higher value to a lower value, SL1 assumes that the counter has been manually reset or that the two values were collected out of order. SL1 does not assume that the counter has rolled over.

The **Rollover Percent** field allows you to specify a threshold that indicates that a 32-bit counter has reached its maximum value and restarted counting. The default value is 20%. When SL1 records a counter value that is lower than the previously collected value, the platform:

• Calculates the difference between the two counter values (the delta):

2³² - Last Collected Value + Current Collected Value

• Examines the value of the **Rollover Percent** threshold. If the delta is less than the specified percentage of the maximum possible value (2³²), SL1 concludes that the 32-bit counter rolled over.

- For example, if you specified "25" in this field, SL1 would determine if the delta is less than 25% of the maximum possible value. If the delta is less than 25% of the maximum possible value, SL1 concludes that the 32-bit counter rolled over.
- When SL1 determines a counter has rolled over, SL1 uses the delta value when displaying the data point for this poll period.

NOTE: The *Rollover Percent* field applies only to 32-bit counters. If a 64-bit counter value goes from a higher value to a lower value, the change is treated as either a manual reset or an out-of-order collection.

- **Out-of-order Percent**. For any collected data that uses a counter, you can specify how SL1 determines that data has been collected out of order. When this data is collected out of order, the collected values go from a higher value to a lower value. However, there are multiple circumstances under which a counter value can go from a higher value to a lower value:
 - Maximum value has been exceeded and counter was reset to zero (for 32-bit counters only).
 - Data was collected out-of-order, that is, due to a slowdown somewhere in the network, two counter values were stored out of sequence.
 - Retrieved value was manually reset to zero on the external device.

The **Out-of-order Percent** field allows you to specify a threshold that indicates that data has been collected out of order. The default value is 50%. When SL1 records a counter value that is lower than the previously collected value and the platform has determined that the value is not a rollover, SL1:

• Compares the current value to the last collected value:

current value / last collected value

- If the ratio of current value / last collected value is greater than the percent specified in the **Out-of-order Percent** field, SL1 concludes that the data was collected out of order.
- When SL1 determines a data point has been collected out of order, SL1 uses the following value as the current value of the data point:

last collected value - current collected value

NOTE: If a 32-bit counter value goes from the maximum value to a lower value, and the current collected value does not meet the criteria for a rollover AND the current collected value does not meet the criteria for out-of-order, SL1 concludes that the 32-bit counter was manually reset to zero (0). SL1 uses the current collected value for this data point.

NOTE: If a 64-bit counter value goes from a higher value to a lower value, and the current collected value does not meet the criteria for out-of-order, SL1 concludes that the 64-bit counter was manually reset to zero (0). SL1 uses the current collected value for this data point.

- Availability Ping Count. If you select *ICMP* in the Availability Port field in the Device Properties page (Devices > Device Manager > wrench icon) for a device, this field specifies the number of packets that should be sent during each availability check. The default value is "1".
- Avail Required Ping Percentage. If you select *ICMP* in the Availability Port field in the Device Properties page (Devices > Device Manager > wrench icon) for a device, this field specifies the percentage of packets that must be returned during an availability check for SL1 to consider the device available. The default value is "100%".
- **Process Runtime Threshold Low**. Threshold that will trigger a "process time exceeded" event. The default threshold is 80%. When a process has used more than 80% of its allowed **Run Length**, SL1 will generate a "process time exceeded threshold" event with a status of "minor".
- **Process Runtime Threshold High**. Threshold that will trigger a "process time exceeded" event. The default threshold is 100%. When a process has used 100% of its allowed **Run Length**, SL1 will generate a "process time exceeded threshold" event with a status of "major".

NOTE: Run Length is defined in the Process Manager page (System > Settings > Admin Processes).

• **Component Purge Timeout**. This field specifies the number of hours a device can be set to "vanished" before SL1 purges the component device. When a device is purged, SL1 stops trying to collect data about the component device. The purged device will not appear in reports or views on in any pages in the user interface. When a device is purged, all of its configuration data and collected data is deleted from the Database Server. If you set this value to "0", component devices are never purged. You can override this threshold for a specific device in the [Thresholds] tab of the **Device Investigator** (or the **Device Thresholds** page in the classic SL1 user interface) for the device.

NOTE: When a device is set to "vanished", all children of that device are also set to "vanished". When a device is purged, all children of that device are also purged.

- Component Vanish Timeout Mins. If SL1 cannot retrieve information from a root device about a component device, this field specifies how many minutes to wait until putting the component device into "vanish" mode. When a device is set to "vanished", SL1 stops trying to collect data about the component device. The vanished device will not appear in reports or views. The vanished device will appear in the Vanished Device Manager page. If you set this value to "0", component devices are never set to "vanished". You can override this threshold for a specific device in the [Thresholds] tab of the Device Investigator (or the Device Thresholds page in the classic SL1 user interface) for the device.
- 3. Click the [Save] button to save changes in this page.
- 4. All changes to this page are logged in the audit logs.

Global Settings for Interface Thresholds

The **Interface Thresholds Defaults** page (System > Settings > Thresholds > Interface) allows you to define global thresholds for interfaces.

The settings in the **Interface Thresholds Defaults** page apply to all interfaces. However, you can override these system settings on a case-by-case basis for each interface in the **Thresholds** tab on the **Interface Properties** page (Registry > Networks > Interfaces > interface wrench icon).

If you have specified that SL1 should monitor an interface, SL1 will collect data about the interface and also monitor performance thresholds for the interface. SL1 will use either the default thresholds defined in the **Interface Thresholds Defaults** page (System > Settings > Thresholds > Interface or the custom threshold you define in the **Thresholds** tab on the **Interface Properties** page (Registry > Networks > Interfaces > interface wrench icon). When the values for an interface exceed one or more thresholds, SL1 will generate an event.

To define global thresholds for interfaces:

1. Go to Interface Thresholds Defaults page (System > Settings > Thresholds > Interface.

old Defaults			
	Metric		Show Hidden Thresholds
	Utilization % In		·
		% Inbound Percent 65.000	[Enabled]
	Utilization % Out		
		% Outbound Percent 65.000	[Enabled]
	Bandwidth In		
		[Mbps] V	
	Bandwidth Out	Inbound Bandwidth 0.000	[Disabled] •
	Bandwidth Out	[Mbps] 🔻	
		Outbound Bandwidth 0.000	[Disabled]
	Errors % In		
		%	
		Inbound Error Percent 0.000	[Disabled] •
	Errors % Out	*	
		Outbound Error Percent 0.000	[Disabled]
	Errors In		
		pits	
		Inbound Errors 1.000	[Enabled] V
	Errors Out		
		pkts Outbound Errors 0.000	[Disabled]
	Discards % In		<u></u>
		~	
		Save	

2. The following global thresholds are defined by default in the Interface Thresholds Defaults page:

NOTE: You can specify the unit of measure for all the metrics in **Bandwidth In** and **Bandwidth Out**. You can select **bps**, **kbps**, **Mbps** (the default), or **Gbps**.

Threshold	Default Value	Default Status
Utilization % In > Inbound Percent	65.000	Enabled
Utilization % Out > Outbound Percent	65.000	Enabled
Bandwidth In > Inbound Bandwidth	0.000	Disabled
Bandwidth Out > Outbound Bandwidth	0.000	Disabled
Errors % In > Inbound Error Percent	1.000	Enabled
Errors % Out > Outbound Error Percent	1.000	Enabled
Errors In > Inbound Errors	1000.000	Enabled
Errors Out > Outbound Errors	1000.000	Enabled
Discard % In > Inbound Discard Percent	1.000	Enabled
Discards % Out > Outbound Discard Percent	1.000	Enabled
Discards In > Inbound Discards	1000.000	Enabled
Discards Out > Outbound Discards	1000.000	Enabled
Multicast % In > Rising Medium	30.000	Disabled
Multicast % In > Rising Low	20.000	Disabled
Broadcast % Out > Rising Medium	30.000	Disabled
Broadcast % Out > Rising Low	20.000	Disabled

3. Selecting the **Show Hidden Thresholds** checkbox displays the following default thresholds:

NOTE: You can specify the unit of measure for all the metrics in **Bandwidth In** and **Bandwidth Out**. You can select **bps**, **kbps**, **Mbps** (the default), or **Gbps**.

Threshold	Default Value	Default Status
Utilization % In > Rising High	0.000	Hidden
Utilization % In > Rising Medium	0.000	Hidden
Utilization % In > Rising Low	0.000	Hidden
Utilization % In > Falling Low	0.000	Hidden
Utilization % In > Falling Medium	0.000	Hidden
Utilization % In > Falling High	0.000	Hidden
Utilization % In > Inbound Percent	65.000	Enabled
Utilization % Out> Rising High	0.000	Hidden

Threshold	Default Value	Default Status
Utilization % Out > Rising Medium	0.000	Hidden
Utilization % Out > Rising Low	0.000	Hidden
Utilization % Out > Falling Low	0.000	Hidden
Utilization % Out > Falling Medium	0.000	Hidden
Utilization % Out > Falling High	0.000	Hidden
Utilization % Out > Outbound Percent	65.000	Enabled
Bandwidth In > Rising High	0.000	Hidden
Bandwidth In > Rising Medium	0.000	Hidden
Bandwidth In > Rising Low	0.000	Hidden
Bandwidth In > Falling Low	0.000	Hidden
Bandwidth In > Falling Medium	0.000	Hidden
Bandwidth In > Falling High	0.000	Hidden
Bandwidth In > Inbound Bandwidth	0.000	Disabled
Bandwidth Out > Rising High	0.000	Hidden
Bandwidth Out > Rising Medium	0.000	Hidden
Bandwidth Out > Rising Low	0.000	Hidden
Bandwidth Out > Falling Low	0.000	Hidden
Bandwidth Out > Falling Medium	0.000	Hidden
Bandwidth Out > Falling High	0.000	Hidden
Bandwidth Out > Outbound Bandwidth	0.000	Disabled
Errors % In > Rising High	0.000	Hidden
Errors % In > Rising Medium	0.000	Hidden
Errors % In > Rising Low	0.000	Hidden
Errors % In > Falling Low	0.000	Hidden
Errors % In > Falling Medium	0.000	Hidden
Errors % In > Falling High	0.000	Hidden
Errors % In > Inbound Error Percent	1.000	Enabled
Errors % Out > Rising High	0.000	Hidden
Errors % Out > Rising Medium	0.000	Hidden

Threshold	Default Value	Default Status
Errors % Out > Rising Low	0.000	Hidden
Errors % Out > Falling Low	0.000	Hidden
Errors % Out > Falling Medium	0.000	Hidden
Errors % Out > Falling High	0.000	Hidden
Errors % Out > Outbound Error Percent	1.000	Enabled
Errors In > Rising High	0.000	Hidden
Errors In > Rising Medium	0.000	Hidden
Errors In > Rising Low	0.000	Hidden
Errors In > Falling Low	0.000	Hidden
Errors In > Falling Medium	0.000	Hidden
Errors In > Falling High	0.000	Hidden
Errors In > Inbound Errors	1000.000	Enabled
Errors Out > Rising High	0.000	Hidden
Errors Out > Rising Medium	0.000	Hidden
Errors Out > Rising Low	0.000	Hidden
Errors Out > Falling Low	0.000	Hidden
Errors Out > Falling Medium	0.000	Hidden
Errors Out > Falling High	0.000	Hidden
Errors Out > Outbound Errors	1000.000	Enabled
Discards % In > Rising High	0.000	Hidden
Discards % In > Rising Medium	0.000	Hidden
Discards % In > Rising Low	0.000	Hidden
Discards % In > Falling Low	0.000	Hidden
Discards % In > Falling Medium	0.000	Hidden
Discards % In > Falling High	0.000	Hidden
Discards % In > Inbound Discard Percent	1.000	Enabled
Discards % Out > Rising High	0.000	Hidden
Discards % Out > Rising Medium	0.000	Hidden
Discards % Out > Rising Low	0.000	Hidden

Threshold	Default Value	Default Status
Discards % Out > Falling Low	0.000	Hidden
Discards % Out > Falling Medium	0.000	Hidden
Discards % Out > Falling High	0.000	Hidden
Discards % Out > Outbound Discard Percent	1.000	Enabled
Discards In > Rising High	0.000	Hidden
Discards In > Rising Medium	0.000	Hidden
Discards In > Rising Low	0.000	Hidden
Discards In > Falling Low	0.000	Hidden
Discards In > Falling Medium	0.000	Hidden
Discards In > Falling High	0.000	Hidden
Discards In > Inbound Discards	1000.000	Enabled
Discards Out > Rising High	0.000	Hidden
Discards Out > Rising Medium	0.000	Hidden
Discards Out > Rising Low	0.000	Hidden
Discards Out > Falling Low	0.000	Hidden
Discards Out > Falling Medium	0.000	Hidden
Discards Out > Falling High	0.000	Hidden
Discards Out > Outbound Discards	1000.000	Enabled
Broadcast % In > Rising High	0.000	Hidden
Broadcast % In > Rising Medium	30.000	Disabled
Broadcast % In > Rising Low	20.000	Disabled
Broadcast % In > Falling Low	0.000	Hidden
Broadcast % In > Falling Medium	0.000	Hidden
Broadcast % In > Falling High	0.000	Hidden
Broadcast % Out > Rising High	0.000	Hidden
Broadcast % Out > Rising Medium	30.000	Disabled
Broadcast % Out > Rising Low	20.000	Disabled
Broadcast % Out > Falling Low	0.000	Hidden
Broadcast % Out > Falling Medium	0.000	Hidden

Threshold	Default Value	Default Status
Broadcast % Out > Falling High	0.000	Hidden
Broadcast In > Rising High	0.000	Hidden
Broadcast In > Rising Medium	0.000	Hidden
Broadcast In > Rising Low	0.000	Hidden
Broadcast In > Falling Low	0.000	Hidden
Broadcast In > Falling Medium	0.000	Hidden
Broadcast In > Falling High	0.000	Hidden
Broadcast Out > Rising High	0.000	Hidden
Broadcast Out > Rising Medium	0.000	Hidden
Broadcast Out > Rising Low	0.000	Hidden
Broadcast Out > Falling Low	0.000	Hidden
Broadcast Out > Falling Medium	0.000	Hidden
Broadcast Out > Falling High	0.000	Hidden
Multicast % In > Rising High	0.000	Hidden
Multicast % In > Rising Medium	00.000	Hidden
Multicast % In > Rising Low	00.000	Hidden
Multicast % In > Falling Low	0.000	Hidden
Multicast % In > Falling Medium	0.000	Hidden
Multicast % In > Falling High	0.000	Hidden
Multicast % Out > Rising High	0.000	Hidden
Multicast % Out > Rising Medium	00.000	Hidden
Multicast % Out > Rising Low	00.000	Hidden
Multicast % Out > Falling Low	0.000	Hidden
Multicast % Out > Falling Medium	0.000	Hidden
Multicast % Out > Falling High	0.000	Hidden
Multicast In > Rising High	0.000	Hidden
Multicast In > Rising Medium	0.000	Hidden
Multicast In > Rising Low	0.000	Hidden
Multicast In > Falling Low	0.000	Hidden

Threshold	Default Value	Default Status
Multicast In > Falling Medium	0.000	Hidden
Multicast In > Falling High	0.000	Hidden
Multicast Out > Rising High	0.000	Hidden
Multicast Out > Rising Medium	0.000	Hidden
Multicast Out > Rising Low	0.000	Hidden
Multicast Out > Falling Low	0.000	Hidden
Multicast Out > Falling Medium	0.000	Hidden
Multicast Out > Falling High	0.000	Hidden
Unicast % In > Rising High	0.000	Hidden
Unicast % In > Rising Medium	00.000	Hidden
Unicast % In > Rising Low	00.000	Hidden
Unicast % In > Falling Low	0.000	Hidden
Unicast % In > Falling Medium	0.000	Hidden
Unicast % In > Falling High	0.000	Hidden
Unicast % Out > Rising High	0.000	Hidden
Unicast % Out > Rising Medium	00.000	Hidden
Unicast % Out > Rising Low	00.000	Hidden
Unicast % Out > Falling Low	0.000	Hidden
Unicast % Out > Falling Medium	0.000	Hidden
Unicast % Out > Falling High	0.000	Hidden
Unicast In > Rising High	0.000	Hidden
Unicast In > Rising Medium	0.000	Hidden
Unicast In > Rising Low	0.000	Hidden
Unicast In > Falling Low	0.000	Hidden
Unicast In > Falling Medium	0.000	Hidden
Unicast In > Falling High	0.000	Hidden
Unicast Out > Rising High	0.000	Hidden
Unicast Out > Rising Medium	0.000	Hidden
Unicast Out > Rising Low	0.000	Hidden

Threshold	Default Value	Default Status
Unicast Out > Falling Low	0.000	Hidden
Unicast Out > Falling Medium	0.000	Hidden
Unicast Out > Falling High	0.000	Hidden

- 4. For each threshold, you can edit the following:
 - Value. The value at which the threshold will trigger an event.
 - For thresholds that include the word *Rising*, when a value exceeds the specified value, SL1 triggers an event.
 - For thresholds that include the word *Falling*, when a value falls below the specified value, SL1 triggers an event.
 - For thresholds that do not include the word *Rising* or *Falling*, when a value exceeds the specified value, SL1 triggers an event.
 - Status. Specifies whether the threshold is active and whether the threshold will appear in the Thresholds tab on the Interface Properties page (Registry > Networks > Interfaces > interface wrench icon). Choices are:
 - Enabled. The threshold is applied to all interfaces and is monitored by SL1. The threshold appears in the **Thresholds** tab on the **Interface Properties** page (Registry > Networks > Interfaces > interface wrench icon). Users can edit the **Value** and **Status** of the threshold.
 - Disabled. The threshold is applied to all interfaces but is not monitored by SL1. The threshold appears in the Thresholds tab on the Interface Properties page (Registry > Networks > Interfaces > interface wrench icon) with a status of Disabled. In the Thresholds tab on the Interface Properties page, users can edit the Value and Status of the threshold.
 - *Hidden*. The threshold is not applied to all interfaces, and is not monitored by SL1. The threshold does not appear in the **Thresholds** tab on the **Interface Properties** page (Registry > Networks > Interfaces > interface wrench icon).
 - Unit of Measure. For all the metrics under **Bandwidth In** and **Bandwidth Out**, you can select the unit of measure. Choices are:
 - kbps
 - Mbps
 - Gbps

Settings in Silo.Conf

Every SL1 appliance has a configuration file called **silo.conf**, which contains configuration information about the appliance itself, such as the IP address, licensing information, and directory locations. The default settings in silo.conf are configured automatically when the appliance is installed. The following section describes how you can add additional, non-default settings to silo.conf.

CAUTION: ScienceLogic recommends that you do not edit the values in these files without first consulting ScienceLogic. Incorrect values can severely disrupt platform operations.

From the **Device Settings** page of the Web Configuration Utility, you can edit the **silo.conf** file and the following files:

- chrony.conf. This configuration file contains settings related to the time server (chrony.d) used by SL1.
- **chrony.d/servers.conf**. This configuration file contains additional settings for the various chrony time servers.

NOTE: All settings in these .conf files are case-sensitive.

To edit the silo.conf file:

- 1. Log in to the Web Configuration Utility. The Configuration Utilities page appears.
- 2. Click the **[Device Settings]** button. The **Settings** page appears.

ScienceLogic™ Web Configuration Utility	# Home
	Settings Configure your appliance.
Web Configuration Username em7admin Appliance Type All in One	Web Config Password (change only) Confirm Web Config Password
	Save
Edit Files chrony.conf silo.conf chrony.d/servers.conf	

3. In the Edit Files section, click **silo.conf**. The Silo.conf Editor modal page appears:

Silo.conf Editor	
[LOCAL]	
rootdir = /opt/em7	
vardir = /var/lib/em7	
logdir = /var/log/em7	
rundir = /run/em7	
paddress = 10.2.14.27	
dbdir = /data/db	
dbserver = 127.0.0.1	
dbport = 7706	
dbuser = root	
dbpasswd = em7admin	
portcheck = /usr/bin/nmap	
model_type = 1	
eventmanager = internal,api,email,syslog,trap,dynamic	
disable_itil_compliance = 1	
[SLADMIN]	
sladmin_user = em7admin	
sladmin_cred = Jz3jghaKrTn0cFmzQRSSPA_JItKECDAl8VU6Njvi828zrGgGEc99R5yV1eAtn_	
[CENTRAL]	
dbserver = 127.0.0.2	
dbport = 7706	
dbuser = root	
dbpasswd = em7admin	
	Save

- 4. For ISO installs of 10.1.0, the value for dbpassword is encrypted in the silo.conf file.
- To manually unencrypt this password:
 - Log in to the console of the Database Server or SSH to the Database Server.
 - Enter the following at the shell prompt:
 - /opt/em7/share/scripts/encrypt_decrypt_password.py --action decrypt
- To manually encrypt the password:
 - Log in to the console of the Database Server or SSH to the Database Server.
 - Enter the following at the shell prompt:

/opt/em7/share/scripts/encrypt_decrypt_password.py --action encrypt
5. You can add or edit one or more of the following settings:

• **store_timeout**. You can edit this setting in the silo.conf file on each Database Server. When the Database Server pulls collected data back from Data Collectors and Message Collectors, each piece of data (called a storage object) must be stored within a set amount of time. The default timeout for a storage object is ten seconds.

To change the timeout for all storage objects, add the following line to the silo.conf file on the Database Server:

```
store_timeout=xx
> >
where:
```

• xx is the timeout in seconds.

If you change this setting (for example, change the value to 30 seconds), you must stop and restart the high frequency, medium frequency, and low frequency data pull processes for the change to be applied.

NOTE: The store_timeout setting does not apply to All-In-One Appliances.

eventmanager. You can edit this setting in the silo.conf file on each SL1 appliance. You can modify
this default setting to allow API events to be processed on a Data Collector. The default configuration
is:

```
eventmanager = internal,dynamic,syslog,trap
```

To allow a Data Collector to process API events, change this line to:

eventmanager = internal,dynamic,syslog,trap,api

WARNING: Do not make any other changes to this setting or modify this setting on a Database Server or Data Collector.

report_memory_limit. You can edit this setting in the silo.conf file on each SL1 appliance that
provides the user interface (an Administration Portal, Database Server, or All-In-One Appliance). If
report_memory_limit is not defined in silo.conf, the default value is three gigabytes (3G). If reports
are failing to be generated due to a lack of memory, you can increase this value.

To increase report memory, add the following line to the [LOCAL] section of silo.conf on each SL1 appliance the provides the user interface for your system. In most cases, this will be the Administration Portal (for distributed system) or the All-In-One Appliance:

```
report_memory_limit=XY
where:
```

- X is a positive integer
- Y represents units. Value can be K (kilobytes), M (megabytes), or G (gigabytes),

For example, if reports are failing to be generated due to a lack of memory, you could add the following line to silo.conf:

report_memory_limit=4G

NOTE: You should add the *report_memory_limit* option to the silo.conf file on a Database Server only if there are no Administration Portals configured in your system.

NOTE: You must add the same *report_memory_limit* setting to every Administration Portal configured in your system.

- use_v1trap_envelope_addr. You can edit this setting in the silo.conf file on each Data Collectors, Data Collectors that perform message collection, and All-In-One Appliances. In environments where Network Address Translation is performed on SNMP v1 trap messages sent to SL1, you can configure the platform to read the envelope address (the address of the host sending the trap) instead of the agent address (the IP address variable sent as part of the trap). If use_v1trap_envelope_addr is not defined in silo.conf, SL1 will use the agent address for SNMP v1 trap messages.
 - To use the envelope address instead of the agent address for SNMP v1 trap messages, add the following line to the [LOCAL] section of silo.conf on Data Collectors, Data Collectors that perform message collection, and All-In-One Appliances

use_v1trap_envelope_addr=1

 To use the agent address for SNMP v1 trap messages, you can either omit the use_v1_trap_ envelope_addr setting or add the following line to the [LOCAL] section of silo.conf on Data Collectors, Data Collectors that perform message collection, and All-In-One Appliances

use_v1trap_envelope_addr=0

• **disable_itil_compliance**. You can edit this setting in the silo.conf file on each If you enable this setting on an appliance that provides the user interface (an Administration Portal, Database Server, or All-In-One Appliance), the **Ticket Console** page on that appliance will include an option to delete tickets. The option to delete tickets will appear only to users that have been granted the Ticket: Delete access hook and users of type "administrator".

To enable this setting, add the following line to the [LOCAL] section of silo.conf on the appliance that provides the user interface (Administration Portal, Database Server, or All-In-One Appliance):

disable itil compliance=1

• **suppress_ticket_link**. You can edit this setting in the silo.conf file on each SL1 appliance that provides the user interface (an Administration Portal, Database Server, or All-In-One Appliance). If you enable this setting, automatic notifications that are generated when a ticket is created or updated will not include a hyperlink to the ticket.

To enable this setting, add the following line to the [LOCAL] section of silo.conf on SL1 appliance that provides the user interface (Administration Portal, Database Server, or All-In-One Appliance):

suppress_ticket_link=1

• mailparse_interval. You can edit this setting in the silo.conf file on each Database Server or All-In-One Appliance. The mailparse_interval setting defines how frequently the mail parsing process reads email messages from the mailbox. If the mailparse_interval setting is not defined in silo.conf, the default value is 60 seconds. When an email is received by SL1, the mail parsing process on the primary Database Server or All-In-One Appliance reads the email message from the mailbox file and sends it to one of the three processes responsible for acting on that email: the event engine (for events from email), the tickets from email process, or the round-trip email collection process.

To enable this setting, add the following line to the [LOCAL] section of silo.conf on each Database Server or All-In-One Appliance:

```
mailparse_interval=X
where:
```

- X is the frequency at which the mailbox will be read, in seconds. Valid values are 15 seconds to 60 seconds.
- dynamic_collect_num_chunk_workers. You can edit this setting in the silo.conf file on each
 Database Server or All-In-One Appliance. This setting represents the number of workers that handle
 collection requests. SL1 first sorts collection requests into groups by execution environment and sends
 each group of collection requests (called a chunk) to a worker process. This worker process is called
 a chunk worker. For each chunk, a chunk worker creates the execution environment and creates a
 pool of request workers to process the collection requests. The number of chunk workers generally
 represents the number of PowerPacks that can be processed in parallel. The default value for this
 parameter is "2".

To change this setting, add the following line to the [LOCAL] section of silo.conf on each Database Server or All-In-One Appliance:

```
dynamic_collect_num_chunk_workers = [X]
where:
```

• X is the number of chunk workers

NOTE: For more information about using dynamic_collect_num_chunk_workers, see the section on Tuning the Collector Load Balancing Process in the Silo.Conf File. dynamic_collect_num_request_workers. You can edit this setting in the silo.conf file on each
Database Server or All-In-One Appliance. This setting represents the maximum number of request
workers in each worker pool and generally represents the number of collections within a PowerPack
that can be processed in parallel. The default value for this parameter is "2" or the number of cores
on the Data Collector, whichever is greater.

To change this setting, add the following line to the [LOCAL] section of silo.conf on each Database Server or All-In-One Appliance:

dynamic_collect_num_request_workers = [X]
where:

• X is the maximum number of request workers in each worker pool.

NOTE: For more information about using dynamic_collect_num_request_workers, see the section on Tuning the Collector Load Balancing Process in the Silo.Conf File.

• dynamic_collect_request_chunk_size. You can edit this setting in the silo.conf file on each Database Server or All-In-One Appliance. This setting represents the maximum number of collection requests in a chunk and controls how many collections are processed by a single pool or request workers. The default value for this parameter is "200".

To change this setting, add the following line to the [LOCAL] section of silo.conf on each Database Server or All-In-One Appliance:

```
dynamic_collect_request_chunk_size = [X]
where:
```

• X is the maximum number of collection requests in a chunk.

NOTE: For more information about using dynamic_collect_request_chunk_size, see the section on Tuning the Collector Load Balancing Process in the Silo.Conf File. read_timeout. You can edit this setting in the silo.conf file on each Database Server. This setting
controls the client read timeout for database connections to the collectors. This setting applies only to
the Enterprise Database: Collector Config Push process (config_push.py) that runs on the primary
Database Server.

WARNING: Change this value only if you are instructed to do so by ScienceLogic.

To change this setting, add the following line to the [CONFIG_PUSH] section of silo.conf on all Database Servers in your system.

```
read_timeout=X
where:
```

- X is the read timeout, in seconds.
- wait_timeout. You can edit this setting in the silo.conf file on each Database Server. This setting
 controls the server wait timeout for database connections to the collectors. This setting applies only to
 the Enterprise Database: Collector Config Push process (config_push.py) that runs on the primary
 Database Server

WARNING: Change this value only if you are instructed to do so by ScienceLogic.

To change this setting, add the following line to the [CONFIG_PUSH] section of silo.conf on all Database Servers in your system.

```
wait_timeout=X
where:
```

- X is the wait timeout, in seconds.
- write_timeout. You can edit this setting in the silo.conf file on each Database Server. This setting
 controls the client write timeout for database connections to the collectors. This setting applies only to
 the Enterprise Database: Collector Config Push process (config_push.py) that runs on the primary
 Database Server

WARNING: Change this value only if you are instructed to do so by ScienceLogic.

To change this setting, add the following line to the [CONFIG_PUSH] section of silo.conf on all Database Servers in your system.

```
write_timeout=X
where:
```

• X is the write timeout, in seconds.

• memory_limit. You can edit this setting in the silo.conf file on each Database Server. This setting controls the memory limit for the Enterprise Database: Collector Config Push process. This setting applies only to the Enterprise Database: Collector Config Push process (config_push.py) that runs on the primary Database Server

WARNING: Change this value only if you are instructed to do so by ScienceLogic.

To change this setting, add the following line to the [CONFIG_PUSH] section of silo.conf on all Database Servers in your system.

memory_limit=XY
where:

- X is a positive integer.
- Y represents units. Value can be KB (kilobytes), MB (megabytes), or GB (gigabytes).
- message_timeout. You can edit this setting in the silo.conf file on each Database Server. This setting controls the amount of time the parent Enterprise Database: Collector Config Push process will wait for a message from a child process before abandoning that process. This setting applies only to the Enterprise Database: Collector Config Push process (config_push.py) that runs on the primary Database Server

WARNING: Change this value only if you are instructed to do so by ScienceLogic.

To change this setting, add the following line to the [CONFIG_PUSH] section of silo.conf on all Database Servers in your system.

```
message_timeout=X
where:
```

• X is the write timeout, in seconds.

shutdown_timeout. You can edit this setting in the silo.conf file on each Database Server. If the
Enterprise Database: Collector Config Push process is terminated, this setting controls the amount
of time the parent configuration process will wait for its child processes to stop before terminating
itself and allowing the child processes to be inherited by init. This setting applies only to the
Enterprise Database: Collector Config Push process (config_push.py) that runs on the primary
Database Server.

WARNING: Change this value only if you are instructed to do so by ScienceLogic.

To change this setting, add the following line to the [CONFIG_PUSH] section of silo.conf on all Database Servers in your system.

shutdown_timeout=X
where:

- X is the write timeout, in seconds.
- [PROC_VIRTUAL_MEM_LIMIT]. By default, processes in SL1 have a virtual memory limit of 1 GB. You can edit this section in the silo.conf file to overwrite the existing virtual memory limit for a given process in SL1 to ensure that it does not fail by crossing its virtual memory limit.

To change this setting, add the [PROC_VIRTUAL_MEM_LIMIT] section to the silo.conf file. Below that section heading, specify the process you want to update and the new virtual memory limit for that process. Use the following format for each setting:

[process ID]=X where:

- [process ID] is the ID of the process you want to update, as found in master.system_settings_ procs.aid
- X is the new virtual memory limit, in bytes

For example, if you wanted to update a process with an ID of "12" with a new 2 GB memory limit, you would write the following under [PROC_VIRTUAL_MEM_LIMIT]:

12=2147483648

• [ADHOC_REPORT_IN_BATCH]. ad hoc reports are processed in a batch process. You can edit this section in the silo.conf file to overwrite the default timing values for certain ad hoc reporting settings.

To change these settings, under the [ADHOC_REPORT_IN_BATCH] section heading in the silo.conf file, specify the time value (in seconds) for each setting. The following settings are included in the [ADHOC_REPORT_IN_BATCH] section:

- report_execution_delay. This setting controls the amount of time between when a report is scheduled to start running and when it actually begins running. Its default value is 10.
- *ajax_start_delay*. This setting controls the amount of time elapsed before jQuery triggers the ajaxStart event. Its default value is 20.
- *ajax_stop_time*. This setting controls the amount of time elapsed before jQuery triggers the ajaxStop event after all AJAX requests have completed. Its default value is 1800.
- *ajax_frequency*. This setting controls the frequency with which jQuery fires AJAX requests. Its default value is 10.
- ajax_frequency_decreased_after. This setting controls the amount of time elapsed after which jQuery will fire AJAX requests less frequently than in the ajax_frequency setting. Its default value is 300.
- *ajax_decreased_frequency*. This setting controls the decreased frequency with which jQuery fires AJAX requests after the amount of time listed in the *ajax_frequency_decreased_after* setting has elapsed. Its default value is 60.
- report_fail_check_time. This setting controls the amount of time elapsed after which a running report will be considered to have failed. Its default value is 10800.
- auto_page_refresh. This setting controls the amount of time elapsed after which the Scheduled Report Jobs page (Report > Create Report > Scheduled Job / Report Archive) automatically refreshes. Its default value is 10.
- about_to_start_time_check. This setting controls the amount of time before a report job is scheduled to start that it will be labeled as "About to start" on the Scheduled Report Jobs page (Report > Create Report > Scheduled Job / Report Archive). Its default value is 30.
- *time_unit*. This setting controls the unit of time measurement for the ad hoc report settings. Its default value is "second".
- *ui_php_timeout*. This setting controls the amount of time elapsed after which an inactive SL1 reports session will time out. Its default value is 1800.
- 6. To save your changes, click **Save** and then close the modal window.

NOTE: All changes to the silo.conf file are logged in the SL1Database Server.

Disabling the User Interface on a Database Server

Database Servers are automatically configured to provide the user interface. If your SL1 system includes an Administration Portal, you might want to disable the user interface capability on your Database Server(s). Perform the following steps to disable the user interface capability on a Database Server:

NOTE: To complete these steps, you must be familiar with how to edit a file using the vi text editor. If you need assistance with these steps, please contact ScienceLogic Support.

- 1. Log in to the console of the Database Server or use SSH to access the server as the **em7admin** user with the appropriate password.
- 2. Execute the following command to open the firewall rules file:

sudo vi /etc/siteconfig/firewalld-rich-rules.siteconfig

3. Add following lines:

rule port port="443" protocol="tcp" reject
rule port port="80" protocol="tcp" reject

- 4. Save the file and exit the vi editor.
- 5. Execute the following commands to update and restart the firewall:

sudo /opt/em7/share/scripts/update-firewalld-conf.py

Chapter



Collector Groups

Overview

A Collector Group is a group of SL1 Data Collectors. Data Collectors retrieve data from managed devices and applications. This collection occurs during initial discovery, during nightly updates, and in response to policies defined for each managed device. The collected data is used to trigger events, display data in the user interface, and generate graphs and reports.

NOTE: System upgrades will only consider Data Collectors and Message Collectors that are members of a Collector Group.

Grouping multiple Data Collectors allows you to:

- Create a load-balanced collection system, where you can manage more devices without loss of performance. At any given time, the Data Collector with the lightest load manages the next discovered device.
- Optionally, create a redundant, high-availability system that minimizes downtime should a failure occur. If a Data Collector fails, one or more Collection servers in the Collector Group will handle collection until the problem is solved.

This chapter will describe how to create and manage Collector Groups.

NOTE: If you are using a SL1 All-In-One Appliance, most of the sections in this chapter do not apply to your system. For an All-In-One Appliance, a single, default Collector Group is included with the appliance; you cannot create any additional Collector Groups. However, you can view information about the default Collector Group. You can also create a virtual Collector Group, for data storage only. However, the other tasks described in this section do not apply to an All-In-One Appliance.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon (三).
- To view a page containing all the menu options, click the Advanced menu icon (…).

This chapter includes the following topics:

Installing, Configuring, and Licensing Data Collectors	
Technical Information About Data Collectors	
Duplicate IP Addresses	72
Open Ports	72
Viewing the List of Collector Groups	73
Creating a Collector Group	74
Pre-Deployment Questions for a Collector Group	74
Capacity Planning for a Collector Group	74
Defining a Collector Group	74
Editing a Collector Group	
Collector Groups and Load Balancing	78
Tuning Collector Groups in the silo.conf File	80
Collector Affinity	
Failover for Collector Groups for Component Devices	
Collector Groups for Merged Devices	
Creating a Collector Group for Data Storage Only	
Deleting a Collector Group	
Aligning the Collector Group for A Single Device	85
Aligning the Collector Group in a Device Template	86
Changing the Collector Group for One or More Devices	87
Managing the Host Files for a Collector Group	
Processes for Collector Groups	
Enabling and Disabling Concurrent PowerShell for Collector Groups	

Enabling Concurrent PowerShell on All Collector Groups	89
Disabling Concurrent PowerShell on All Collector Groups	90
Enabling Concurrent PowerShell on a Specific Collector Group	90
Disabling Concurrent PowerShell on a Specific Collector Group	90
Enabling and Disabling Concurrent SNMP for Collector Groups	90
Enabling and Disabling Concurrent SNMP for All Collector Groups	91
Enabling and Disabling Concurrent SNMP for Collector Groups	92

Installing, Configuring, and Licensing Data Collectors

Before you can create a Collector Group, you must install and license at least one Data Collector. For details on installation and licensing of a Data Collector, see the *Installation* manual.

After you have successfully installed, configured, and licensed a Data Collector, the platform automatically adds information about the Data Collector to the Database Server.

Technical Information About Data Collectors

You might find the following technical information about Data Collectors helpful when creating Collector Groups.

Duplicate IP Addresses

A single Collector Group **cannot** include multiple devices that use the same Admin Primary IP Address (this is the IP address the platform uses to communicate with a device). If a single Collector Group includes multiple devices that use the same Primary IP Address or use the same Secondary IP Address, the platform will generate an event. Best practice is to ensure that within a single Collector Group, all IP addresses on all devices are unique.

- During initial discovery, if a device is discovered with the same Admin Primary IP Address as a previously discovered device in the Collector Group, the later discovered device will appear in the discovery log, but will not be modeled in the platform. That is, the device will not be assigned a device ID and will not be created in the platform. The platform will generate an event specifying that a duplicate Admin Primary IP was discovered within the Collector Group.
- If you try to assign a device to a Collector Group, and the device's Admin Primary IP Address already exists in the Collector Group, the platform will display an error message, and the device will not be aligned with the Collector Group.

Open Ports

By default, Data Collectors accept connections only to the following ports:

- TCP 22 (SSH)
- TCP 53 (DNS)

- TCP 123 (NTP)
- UDP 161 (SNMP)
- UDP 162 (Inbound SNMP Trap)
- UDP 514 (Inbound Syslog)
- TCP 7700 (Web Configuration Utility)
- TCP 7707 (one-way communication from the Database Server)

For increased security, all other ports are closed.

Viewing the List of Collector Groups

To view the list of already-defined Collector Groups in your SL1 system:

1. Go to the Collector Group Management page (System > Settings > Collector Groups).

Collector Group Management Creating	g New Group					Reset Guide
	Celector Georg Hame Celector Falloure Celector Falloure Celector Falloure Celector Falloure Celector Celector College Celector Celector College Celector State Celector Celector Celector State Celector BETA (Use system/de defaa) V	Message Collector 10-64-171-216-MC 6	ectors Available For Fallover	0		
Collector Group Registry Found 9		lectors Msg Collectors	# Devices	Edit User	Edit Date	
1. CUG-Benedict	7 1	RECORD INSU CONCIONS	16	em7admin	2020-06-25 16:09:51	/ 0 ⁴
2. PCUG-MOSS	1 2	10-64-171-216-MC	0	em7admin	2020-06-25 16:09:50	/ c*
3. 🥍 CUG-RaceCondition	8 3		1	em7admin	2020-06-25 18:50:19	/ o*
4. 🥍 CUG-SAC	3 1		0	em7admin	2020-06-25 16:09:50	/ o ²
5. 🤌 CUG-Shared	6 2		125	em7admin	2020-06-25 16:09:51	🖌 🗸
6. PCUG-Solutions1	5 2		956	em7admin	2020-06-25 18:39:04	/ o*
7. 🤌 CUG-Solutions2	4 1		0	em7admin	2020-06-26 15:09:49	/ o*
8. PCUG-Solutions3	9 1		89	em7admin	2020-06-26 15:10:15	/ oʻ
9. 🥍 CUG-UsualSuspects	2 2		0	em7admin	2020-06-25 16:09:50	/ o*
hit. Al right merved.						

- 2. The **Collector Group Registry** pane displays a list of all Collector Groups in your SL1 system. For each Collector Group, the **Collector Group Management** page displays the following:
 - Name. Name of the Collector Group.
 - ID. Unique numeric identifier automatically assigned by SL1 to each Collector Group.
 - # Collectors. Number of Data Collectors in the Collector Group.
 - Msg Collector. Name of the Message Collector(s) (if any) associated with the Collector Group.
 - # Devices. Number of devices currently using the Collector Group for data collection.

- Edit User. User who created or last edited the Collector Group.
- Edit Date. Date and time the Collector Group was created or last edited.

Creating a Collector Group

You can group multiple Data Collectors into a Collector Group. Depending on the number of Data Collectors in your SL1 system, you can define one or more Collector Groups. Each Collector Group must include at least one Data Collector.

Pre-Deployment Questions for a Collector Group

Consider the following questions before creating a new Collector Group. Your responses to these questions will help you determine how to create and name your new Collector Group:

- Will your Collector Group span regionally close data centers and be configured for maximum resilience?
- Will your users be required to know your Collector Group naming scheme, or will you provide a general Collector Group for them to use as a default (and use specialized Collector Groups for distinct use cases only)?
- Will your Collector Group be structured for minimum latency to the monitored endpoints?
- Consider the following questions about the resilience of your deployment:
 - What happens to the ability to monitor if a data center hosting an entire Collector Group goes offline?
 - Is the deployment resilient and will it perform well?
 - What is your failure mode? 100% > 0% or !00% > 50% > 0%?

Capacity Planning for a Collector Group

In addition to deciding on your resiliency strategy, look at your failure mode and determine if you are allocating sufficient capacity to achieve a 100% > 50% capacity degradation on a data center failure before failing completely at 0%.

Consider the number of devices in your Collector Group and the number of Data Collectors in your Collector Group to determine if you have overloaded Data Collectors or underpowered Data Collectors.

Defining a Collector Group

To define a new Collector Group:

- 1. Go to the **Collector Group Management** page (System > Settings > Collector Groups).
- 2. In the **Collector Group Management** page, click the **[Reset]** button to clear the values from the fields in the top pane.

- 3. Go to the top pane and enter values in the following fields:
 - Collector Group Name. Name of the Collector Group.
 - **Collector Failover**. Specifies whether you want to maximize the number of devices to be managed or whether you want to maximize reliability. Your choices are:
 - Off (Maximize Manageable Devices). The Collector Group will be load-balanced only. At any given time, the Data Collector with the lightest load handles the next discovered device. If a Data Collector fails, no data will be collected from the devices aligned with the failed Data Collector until the failure is fixed.
 - On (Maximize Reliability). The Collector Group will be load-balanced and configured as a highavailability system that minimizes downtime. If one or more Data Collectors should fail, the tasks from the failed Data Collector will be distributed among the other Data Collectors in the Collector Group.
 - Generate Alert on Collector Outage. Specifies whether or not the platform should generate an event if a Data Collector has an outage.
 - Enable Concurrent SNMP Collection. Specifies whether you want to enable Concurrent SNMP Collection. Concurrent SNMP Collection uses asynchronous I/O for massive concurrency with lower system resource requirements. This means that Data Collectors can collect more data using fewer system resources. Concurrent SNMP Collection also prevents missed polls and data gaps because collection will execute more quickly. For the selected Collector Group, this field overrides the value in the **Behavior Settings** page (System > Settings > Behavior).
 - Collector Selection. Displays a list of available Data Collectors.
 - To assign an available Data Collector server to the Collector Group, simply highlight it. You can assign one or more Data Collectors to a Collector Group.
 - To assign multiple Data Collectors to the Collector Group, hold down the **<Ctrl>** key and click multiple Data Collectors.

- Message Collector. Displays a list of available Message Collectors.
 - To assign an available Message Collector to the Collector Group, simply highlight it. You can assign one or more Message Collectors to a Collector Group.
 - To assign multiple Message Collectors to the Collector Group, hold down the **<Ctrl>** key and click multiple Message Collectors.
 - Note that a single Message Collector can be used by multiple Collector Groups.

NOTE: When you align a single Message Collector with multiple Collector Groups, the single Message Collector might then be aligned with two devices (each in a separate Collector Group) that use the same primary IP address or the same secondary IP address. If this happens, SL1 will generate an event.

- Collectors Available for Failover. Applies only if you selected "On (Maximize Reliability)" in the Collector Failover field. Specifies the minimum number of Data Collectors that must be available (i.e. with a status of "Available [0]") before a Data Collector failover may occur.
 - For collector groups with only two Data Collectors, this field will contain the value "1 collector".
 - For collector groups with more than two Data Collectors, the field will contain values from a minimum of one half of the total number of Data Collectors up to a maximum of one less than the total number of Data Collectors.
 - For example, for a collector group with eight Data Collectors, the possible values in this field would be 4, 5, 6, and 7.
 - SL1 will never automatically increase the maximum number of Data Collectors that can fail in a Collector Group. For example, suppose you have a collector group with three Data Collectors. Suppose Collectors Available For Failover field is set to "2". If you add a fourth Data Collector to the collector group, SL1 will automatically set the Collectors Available For Failover field to "3" to maintain the maximum number of Data Collectors that can fail as "one". However, you can override this automatic setting by manually changing the value in the Collectors Available For Failover field.

NOTE: If you set this to half of your available Data Collectors and a 50% Data Collector outage occurs and the remaining Data Collectors are down by one, no rebalance will occur. If you specify one-third of the total number of Data Collectors, then a rebalance will be attempted until your overall capacity falls below one-third of your Data Collectors, thereby maximizing your resiliency but minimizing the opportunity for your system to enter an unproductive rebalancing loop.

CAUTION: If the number of available Data Collectors is less than the value in the Collectors Available For Failover field, SL1 will not failover within the Collector Group. SL1 will not collect any data from the devices aligned with the failed Data Collector(s) until the failure is fixed on enough Data Collector(s) to equal the value in the Collectors Available For Failover field. EM7 will generate a critical event.

- Failback Mode. Applies only if you selected On (Maximize Reliability) in the Collector Failover field. Specifies how you want collection to behave when the outage is fixed. You can specify one of the following:
 - Automatic. After the failed Data Collector is restored, SL1 will automatically redistribute datacollection tasks among the Collector Group, including the previously failed Data Collector.
 - Manual. After the failed Data Collector is restored, you will manually prompt Data Collector to redistribute data-collection tasks by clicking the lightning bolt icon (\checkmark) for the Collector Group.
- Failover Delay (minutes). Applies only if you selected On (Maximize Reliability) in the Collector Failover field. Specifies the number of minutes SL1 should wait after the outage of a Data Collector before redistributing the data-collection tasks among the other Data Collectors in the group. During this time, data will not be collected from the devices aligned with the failed Data Collector(s). The default minimum value for this field is 5 minutes.
- Failback Delay (minutes). Applies only if you selected On (Maximize Reliability) in the Collector Failover field and Automatic in the Failback Mode field. Specifies the number of minutes SL1 should wait after the failed Data Collector is restored before redistributing data-collection tasks among the Collector Group, including the previously failed Data Collector. The default minimum value for this field is 5 minutes.
- 4. Click the [Save] button to save the new Collector Group.
- 5. To assign devices to the Collector group, see the section on aligning single devices with a Collector Group and the section on aligning a device group with a Collector Group.

Editing a Collector Group

From the **Collector Group Management** page, you can edit an existing Collector Group. You can add or remove Data Collectors and change the configuration from load-balanced to failover (high availability). To edit a Collector Group:

1. Go to the **Collector Group Management** page (System > Settings > Collector Groups).

2. In the **Collector Group Management** page, go to the **Collector Group Registry** pane at the bottom of the page.

- 3. Find the Collector Group you want to edit. Click its wrench icon (\mathscr{P}) .
- 4. The fields in the top pane are populated with values from the selected Collector Group. You can edit one or more of the fields. For a description of each field, see the section on **Creating a Collector Group**.
- 5. Click the **[Save]** button to save any changes to the Collector Group.

Collector Groups and Load Balancing

To perform initial discovery, SL1 uses a single, selected Data Collector from the Collector Group. This allows you to troubleshoot discovery if there are any problems.

After each discovered device is modeled (that is, after SL1 assigns a device ID and creates the device in the database), SL1 distributes devices among the Data Collectors in the Collector Group. The newest device is assigned to the Data Collector currently managing the lightest load.

This process is known as **Collector load balancing**, and it ensures that the work performed by the Dynamic Applications aligned to the devices is evenly distributed across the Data Collectors in the Collector Group.

SL1 performs Collector load balancing in the following circumstances:

- A new Data Collector is added to a Collector Group
- New devices are discovered
- Failover or failback occurs within a Collector Group (if failover is enabled)
- A user clicks the lightning bolt icon (\mathscr{I}) for a Collector Group to manually force redistribution
- Devices in DCM or DCM-R trees will be loaded on the Data Collector currently assigned to the DCM or DCM-R tree rather than being distributed across the Collector Group. DCM or DCM-R trees will be rebalanced as an aggregate when rebalancing occurs to an available Data Collector with sufficient capacity to sustain the load.

NOTE: The lightning bolt icon (\checkmark) appears only for Collector Groups that contain more than one Data Collector. For Collector Groups with only one Data Collector, this icon is grayed out. This icon does not appear for All-In-One Appliances.

When all of the devices in a Collector Group are redistributed, SL1 will assign the devices to Data Collectors so that all Data Collectors in the collector group will spend approximately the same amount of time collecting data from devices.

Collector load balancing uses two metrics:

- Device Rating. A device's rating is the total elapsed time consumed by either 1) all of the Dynamic Applications aligned to the device, or 2) collecting metrics from the device's interfaces, whichever is greater. A Collector's load is the sum of the ratings of the devices assigned to the Collector. The balancer tries to evenly divide the work performed by Collectors by assigning devices to Collectors using the device ratings and Collector loads.
- Collector Load. The sum of the device ratings for all of the devices assigned to a collector.

SL1 performs the following steps during Collector load balancing:

- 1. Searches for all devices that are not yet assigned to a Collector Group.
- 2. Determines the load on each Data Collector by calculating the device rating for each device on a Data Collector and then summing the device ratings.
- 3. Determines the number of new devices (less than one day old) and old devices on each Data Collector.
- 4. On each Data Collector, calculates the average device rating for old devices (sum of the device ratings for all old devices divided by the number of old devices). If there are no old devices, sets the average device rating to "1" (one).
- 5. On each Data Collector, assigns the average device rating to all new devices (devices less than one day old).
- 6. Assigns each unassigned device (either devices that are not yet assigned or devices on a failed Data Collector) to the Data Collector with the lightest load. Add each newly assigned device rating to the total load for the Data Collector.

Tuning Collector Groups in the silo.conf File

With the addition of execution environments to SL1, SL1 sorts data collections in to a two-process-pool model.

SL1 sorts collection requests into groups by execution environment. These groups of collection requests are called "chunks". Each chunk contains a maximum of 200 collection requests, all of which use the same execution environment. SL1 sends each chunk to a chunk worker.

The chunk worker determines the appropriate execution environment for the chunk, deploys the execution environment, and starts a pool of request workers in the execution environment.

The request workers then process the actual collection requests contained in the chunks and perform the actual data collection.

NOTE: For more information about ScienceLogic Libraries and execution environments, see the manual *ScienceLogic Libraries and Execution Environments*.

The following settings are available in the master.system_settings_core database table for tuning globally in a stack, or *in the Silo.Conf file* for tuning locally on a single Data Collector:

Parameter Name	Description	Runtime Default
dynamic_ collect_num_ chunk_ workers	The number of chunk workers. In general, this value controls the number of PowerPacks that can be processed in parallel.	2
dynamic_ collect_num_ request_ workers	The maximum number of request workers in each worker pool. In general, this value controls the number of collections within a PowerPack that can be processed in parallel.	"2" or the number of cores on the Data Collector, whichever is greater
dynamic_ collect_ request_ chunk_size	The maximum number of collection requests in a chunk. This value controls how many collections are processed by each pool of requests workers.	200

NOTE: The database values for these parameters are "Null" by default, which specifies that SL1 should use the runtime defaults.

The maximum total number of worker processes used during a scheduled collection is generally dynamic_ collect_num_chunk_workers X dynamic_collect_num_request_workers.

There might be circumstances where adjustment is necessary to improve the performance of collection.

Example 1: Additional Environments Required

You might need to adjust the values of the collection processes when scheduled collection requires more than two environments.

Because the default number of chunk workers is "2", SL1 can simultaneously process chunks of collection requests for a maximum of two virtual environments. If the collection requests require more than two virtual environments, you can increase parallelism by setting dynamic_collect_num_chunk_workers to match the number of environments.

If you increase <code>dynamic_collect_num_chunk_workers</code>, you might want to decrease <code>dynamic_collect_num_request_workers</code> to avoid performance problems caused by too many request workers.

If you cannot increase <code>dynamic_collect_num_chunk_workers</code> because doing so would result in too many request workers, you can decrease <code>dynamic_collect_request_chunk_size</code> to give collection requests for each environment a "fairer share" of the chunk workers.

NOTE: Smaller chunk sizes require more resources to establish the virtual environments and establish more polls of request workers to process the chunks. Conversely, if you want to use fewer resources for establishing virtual environments and creating pools of request worker pools, and you want to use more resources for collection itself, increasing dynamic_collect_request_chunk_size allows more collection requests to be processed by each pool of request workers.

Example 2: Input/Output Bound Collections

You might need to adjust the values of the collection processes when collection requests are input/output (I/O) bound with relatively large latencies.

In this scenario, you can increase <code>dynamic_collect_num_request_workers</code> to improve parallelism. If you increase <code>dynamic_collect_num_request_workers</code>, you might want to decrease <code>dynamic_collect_num_chunk_workers</code> to avoid performance problems caused by too many request workers.

CAUTION: Increasing the number of collection processes will increase CPU and memory utilization on the Data Collector, so be careful when increasing the values dramatically.

Before adjusting dynamic_collect_num_request_workers, you need to know the following information:

- The number of CPU cores in the Data Collector
- The current CPU utilization of Data Collector
- The current memory utilization of Data Collector

Start by setting dynamic_collect_num_request_workers to equal the number of CPUs plus 50%. For example: with 8 cores, start by setting dynamic_collect_num_request_workers to 12. If that is insufficient, you can then try 16, 20, 24, and so forth.

If data collections are terminating early, it means that collections are not completed within the 15-minute limit. If this is the case, wait 30 minutes to see results after adjusting the collection values.

For more information about collector load and sizing, watch the video at https://www.youtube.com/watch?v=SR3zaswwkLE.

Collector Affinity

Collector Affinity specifies the Data Collectors that are allowed to run collection for Dynamic Applications aligned to component devices. You can define Collector Affinity for each Dynamic Application. Choices are:

- **Root Device Collector**. The Data Collector assigned to the root device will collect data for the Dynamic Application. This guarantees that Dynamic Applications for an entire DCM tree will be collected by a single Data Collector. You might select this option if:
 - The Dynamic Application has a cache dependency with one or more other Dynamic Applications.
 - You are unable to collect data for devices and Dynamic Applications within the same Device Component Map on multiple Data Collectors in a collector group.
 - If the Dynamic Application will consume cache produced by a Dynamic Application aligned to a non-root device (for instance, a cluster device).
- Assigned Collector. The Dynamic Application will use the Data Collector assigned to the device running the Dynamic Application. This allows Dynamic Applications that are auto-aligned to component devices during discovery to run on multiple Data Collectors. This is the default setting. You might select this option if:
 - The Dynamic Application has no cache dependencies with any other Dynamic Applications.
 - You want the Dynamic Application to be able to make parallel data requests across multiple Data Collectors in a collector group.
 - The Dynamic Application can be aligned using mechanisms other than auto-alignment during discovery (for instance, manual alignment or alignment via Device Class Templates or Run Book Actions).

Failover for Collector Groups for Component Devices

If you specified **Default** or **Root Device Collector** for Dynamic Applications, and the single Data Collector in the Collector Group for component devices fails, users must create a new Collector Group with a single Data Collector and manually move the devices from the failed Collector Group to the new Collector Group. For details on manually moving devices to a new Collector Group, see the section on **Changing the Collector Group for One or More Devices**.

Collector Groups for Merged Devices

You can merge a physical device and a component device. There are two ways to do this:

- From the Actions menu in the **Device Properties** page (Devices> Device Manager > wrench icon) for either the physical device or the component device.
- From the **Actions** menu in the **Device Manager** page (Devices > Device Manager), select Merge Devices to merge devices in bulk.

You can unmerge a component device from a physical device. You can do this in two ways:

- From the **Actions** menu in the **Device Properties** page (Devices > Device Manager > wrench icon) for either the physical device or the component device, , select *Unmerge Devices* to unmerge devices.
- From the **Actions** menu in the **Device Manager** page Devices > Device Manager), select Unmerge Devices to unmerge devices in bulk.

When you merge a physical device and a component device, the device record for the component device is no longer displayed in the user interface; the device record for the physical device is displayed in user interface pages that previously displayed the component device. For example, the physical device is displayed instead of the component device in the **Device Components** page (Devices > Device Components) and the **Component Map** page (Device Component Map). All existing and future data for both devices will be associated with the physical device.

If you manually merge a component device with a physical device, SL1 allows data for the merged component device and data from the physical device to be collected on different Data Collectors. Data that was aligned with the component device can be collected by the Collector Group for its root device. Data aligned with the physical device can be collected by a different Collector Group.

NOTE: You can merge a component device with only one physical device.

Creating a Collector Group for Data Storage Only

From the **Collector Group Management** page, you can create a **Virtual Collector Group** that serves as a storage area for all historical data from decommissioned devices.

The Virtual Collector Group will store all existing historical data from all aligned devices, but will not perform collection on those devices. The Virtual Collector Group will not contain any Data Collectors or any Message Collectors. **SL1 will stop collecting data from devices aligned with a Virtual Collector Group**.

To define a Virtual Collector Group:

1. Go to the Collector Group Management page (System > Settings > Collector Groups).

- 2. In the **Collector Group Management** page, click the **[Reset]** button to clear values from the fields in the top pane.
- 3. Go to the top pane and enter a name for the virtual Collector Group in the Collector Group Name field.
- 4. Leave all other fields set to the default values. Do not include any Data Collectors or Message Collectors in the Collector Group.
- 5. Click the **[Save]** button to save the new Collector Group.
- 6. To assign devices to the virtual Collector Group, see the section on aligning single devices with a Collector Group and the section on aligning a device group with a Collector Group.

Deleting a Collector Group

From the **Collector Group Management** page, you can delete a Collector Group. When you delete a Collector Group, those Data Collectors become available for use in other Collector Groups.

NOTE: Before you can delete a Collector Group, you must move all aligned devices to another Collector Group. For details on how to do this, see the section Changing the Collector Group for One or More Devices.

To delete a Collector Group:

1. Go to the **Collector Group Management** page (System > Settings > Collector Groups).

COUG-MOSS 1 2 10-54-171-216-MC 0 em7admin 2020-05-25 16.09 50 OUG-ReseCondition 8 3 1 em7admin 2020-05-25 18.09 19	1
Name D Extension Extension Extension Extension CUG8 Benedicit 7 1 16 em7demin 2020-00-25 16:09 50 CUG8 Aeros Condition 1 2 16-4-171-215-MIC 0 em7demin 2020-00-25 16:09 50 CUG8-Reso Condition 8 3 1 em7demin 2020-00-25 18:09 19	1
OutG-MOSS 1 2 10-54-171-215-MIC 0 em7admin 2020-68-25 16:09:50 ^{ID} CUG-Mass Condition 8 3 1 em7admin 2020-68-25 18:09:10	
PCUG-RacoCondition 8 3 1 em7edmin 2020-06-25 18:50:19	
	1
2 CUG-SAC 3 1 0 em7admin 2020-06-25 16.09:50	
P CUG-Shared 6 2 125 em7admin 2020-06-25 16.09.51	1
	1
PCUG-Solutions2 4 1 0 em7edmin 2020-06-26 15 09 49	
^P CUG-UsualSuspects 2 2 0 0 em7admin 2020-06-25 16:09:50	9

- 2. In the **Collector Group Management** page, go to the **Collector Group Registry** pane at the bottom of the page.
- 3. Find the Collector Group you want to delete. Click its bomb icon ().

Aligning the Collector Group for A Single Device

After you have defined a Collector Group, you can align devices with that Collector Group. To assign a Collector Group to a device:

1. Go to the **Device Manager** page (Devices > Device Manager).

2. In the **Device Manager** page, find the device you want to edit. Click its wrench icon (*P*). The **Device Properties** page appears:

Close	<u>P</u> roperties	T <u>h</u> resholds	<u>C</u> ollections	<u>M</u> onitors				
<u>S</u> chedule	<u>L</u> ogs	T <u>o</u> olbox	<u>I</u> nterfaces	<u>R</u> elationships	<u>T</u> ickets	Redirects	<u>N</u> otes	
Device Name	MAILSRV			Managed Type	Physical Device			
IP Address / ID	10.20.0.185 21			Category	Servers			
Class	Microsoft			Sub-Class	Windows 2000 Server			
Organization	•				0 days, 00:00:00			Windows 2000
Collection Mode	Active			Collection Time	2014-06-18 14:15:00			🔔 🖶 🔝 📶 🖶 🥜
Description Device Hostname	Hardware: x86 Family	/ 6 Model 11 Stepping	AT/AT COMPATIBLE -	So Group / Collector	CUG em7_ao_205			MAILSRV
Device Hostname								
Device Propertie	es							Organization Asset
							Actions	Reset Guide
Identification								
	Device Name			IP Address			Orea	nization
MAILS		#	[10.20.0.1	85 - verified]	•	[System		
Monitoring & I	Management							Preferences
Device	Class Microsoft Win	dows 2000 Server			2			Auto-Clear Events
							II	
SNMP Read	/Write [Cisco SNM	Pv2 - Example]	[None]		•			Accept All Logs
Availabili	ty Port [UDP]		[161 - SNMP]		🖵 🖉			
Latenc	v Port [ICMP]		▼ [ICMP]		•			Daily Port Scans
Avail+Latency	Alert [Disable]		•					
'								Auto-Update
User Mainter	nance [Disabled]		 [Maintenance Co 	ellection Enabled]	-			
Colle	ection [Enabled]		💌 [CUG]		•			Scan All IP's
Coll.	Type [Standard]		•					
Critica	I Ping [Disabled]		•					Dynamic Discovery
Dash	board None		•					
							——	Preserve Hostname
Event	Mask [Group in blo	cks every 10 minutes]	•					
			Save					Disable Asset Update
			Save					

- 3. In the **Device Properties** page, you can select a Collector Group from the **Collection** fields.
- 4. Click the **[Save]** button to save the change to the device.

Aligning the Collector Group in a Device Template

You can specify a Collector Group in a device template. Then, when you apply the device template to a device, either through discovery or when you apply the device template to a device group or selection of devices, the specified Collector Group is automatically associated with the device(s). Optionally, you can later edit the Collector Group for each device.

For more details on device templates and device groups, see the manual **Device Groups and Device Templates**.

Changing the Collector Group for One or More Devices

You can change the Collector Group for multiple devices simultaneously. This is helpful if you want to reorganize devices or Collector Groups. If you want to delete a Collector Group, you first must first move each aligned device to another Collector Group. In this situation, you might want to change the Collector Group for multiple devices simultaneously.

To change the Collector Group for multiple device simultaneously:

1. Go to the **Device Manager** page (Devices > Device Manager).

e Manager Devices Found [176]		Device					Current	Collection	Actions	Report	Reset Gui
Device Name *	IP Address	Category	Device Class Sub-class	DID		Organization	State	Group	State	Credential	Version
							>=Health 💌				
10-Forward	10.20.0.195	Servers	NET-SNMP FreeBSD	54	System		A Healthy	CUG1	Active	Cisco SNMPv2 - Ex	aV2 📾 🏹 🖏
10.20.0.108	10.20.0.108	Network Router	Cisco Systems 2501	72	System		Allealthy	CUG1	Active	Cisco SNMPv2 - Ex	
P. 10.20.0.123	10.20.0.123	Network.Router	Cisco Systems 7206VXR	112	System		/ Minor	CUG1	Active	Cisco SNMPv2 - Ex	a V2 📾 💢 🗞
10.20.0.13	10.20.0.13	Unknown	Generic SNMP	107	System		Healthy	CUG1	Active	Cisco SNMPv2 - Ex	aV2 📾 🕽 🖏
A 10.20.0.135	10.20.0.135	Network.Switche	Cisco Systems Catalyst 3508G-XL	131	System		A Healthy	CUG1	Active	Cisco SNMPv2 - Ex	a V2 📾 😂 🕅
10.20.0.141	10.20.0.141	Network.Switche	clisco Systems Catalyst WS-C6009-CatOS	118	System		A Healthy	CUG1	Active	Cisco SNMPv2 - Ex	aV2 📾 🔀 🎗
Pm 10.20.0.146	910.20.0.146	Network.Broadba	r Netopia Netopia 3346 v8.2r1	2	System		A Healthy		Active	Cisco SNMPv2 - Ex	
an 10.20.0.147	910.20.0.147	Network.Broadba	r Netopia Netopia 3381 v8.0.10	175	System		A Healthy	CUG1	Active	Cisco SNMPv2 - Ex	aV2 📾 🔀 🕅
Am 10.20.0.148	10.20.0.148	Network.Broadba	r Netopia Netopia (R3100, R45xx, R7xx0, R9	163	System		Healthy	CUG1	Active	Cisco SNMPv2 - Ex	
10.20.0.149	910.20.0.149		r Netopia R7200-T	162	System		Healthy	CUG1	Active	Cisco SNMPv2 - Ex	
Am <mark>10.20.0.151</mark>	10.20.0.151	Unknown	Generic SNMP	141	System			CUG1	Active	Cisco SNMPv2 - Ex	a V2 😸 🖏 🖏
an 10.20.0.160	10.20.0.160	Unknown	Generic SNMP	165	System		A Healthy	CUG1	Active	Cisco SNMPv2 - Ex	aV2 📾 🔀 🎕
Am <mark>10.20.0.163</mark>	10.20.0.163	Unknown	Generic SNMP	164	System			CUG1	Active	Cisco SNMPv2 - Ex	
Am 10.20.0.175	10.20.0.175	Unknown	Generic SNMP	44	System		A Healthy	CUG1	Active	Cisco SNMPv2 - Ex	aV2 📾 👯 🎗
Am10.20.0.176	10.20.0.176	Unknown	Konica Corporation OEM	41	System		1 Minor	CUG1	Active	Cisco SNMPv2 - Ex	
Am 10.20.0.190	10.20.0.190	Unknown	Generic SNMP	56	System		Minor	CUG1	Active	Cisco SNMPv2 - Ex	
Am10.20.0.191	10.20.0.191	Office.Printers	Konica Minolta Fiery X3e 22C-KM	57	System		1 Minor	CUG1	Active	Cisco SNMPv2 - Ex	
10.20.0.201	10.20.0.201	Unknown	Generic SNMP	48	System		Healthy	CUG1	Active	Cisco SNMPv2 - Ex	
2 10.20.0.208	10.20.0.208	Unknown	Generic SNMP	52	System		A Healthy	CUG1	Active	Cisco SNMPv2 - Ex	
10.20.0.209	W10.20.0.209	Telephony	Quintum Tenor	53	System		A Healthy	CUG1	Active	Cisco SNMPv2 - Ex	
10 20.0.222	10.20.0.222	Unknown	Generic SNMP	138	System			CUG1	Active	Cisco SNMPv2 - Ex	
10.20.0.26	10.20.0.26	Unknown	Generic SNMP	171	System			CUG1	Active	Cisco SNMPv2 - Ex	
10.20.0.52	10.20.0.52	Unknown	ASKEY Computer Corp. OEM	5	System			CUG1	Active	Cisco SNMPv2 - Ex	
Avr 10.20.0.59	9 10.20.0.59	Unknown	Generic SNMP	3	System		Healthy		Active	Cisco SNMPv2 - Ex	
10.20.0.61	10.20.0.61	Unknown	Generic SNMP	84	System		A Healthy	CUG1	Active	Cisco SNMPv2 - Ex	aV2 📑 👯 🕅
an 10 20 0 81	10.20.0.61	Unknown	Generic SNMP	84	System		AHealthy		Active	Cisco SIMPv2 - Ex	
ing Page: 1]										Select Action1	

- 2. In the **Device Manager** page, click on the heading for the **Collection Group** column to sort the list of devices by Collector Group.
- 3. Select the checkbox for each device that you want to move to a different Collector Group.
- 4. In the **Select Action** field (in the lower right), go to **Change Collector Group** and select a Collector Group.
- 5. Click the **[Go]** button. The selected devices will now be aligned with the selected Collector Group.

Managing the Host Files for a Collector Group

The **Host File Entry Manager** page allows you to edit and manage host files for all of your Data Collectors from a single page in the SL1 system. When you create or edit an entry in the **Host File Entry Manager** page, SL1 automatically sends an update to every Data Collector in the specified Collector Group.

The Host File Entry Manager page is helpful when:

- The SL1 system does not reside in the end-customer's domain
- The SL1 system does not have line-of-sight to an end-customer's DNS service
- A customer's DNS service cannot resolve a host name for a device that the SL1 system monitors

For details, see the section on Managing Host Files.

Processes for Collector Groups

For troubleshooting and debugging purposes, you might find it helpful to understand the ScienceLogic processes that affect a Collector Group.

NOTE: You can view the list of all processes and details for each process in the **Process Manager** page (System > Settings > Admin Processes).

- The Enterprise Database: Collector Task Manager process (em7_ctaskman) process distributes devices between Data Collectors in a Collector Group, to load-balance the collection tasks. The process runs every 60 seconds and also checks the license on each Data Collector. The Enterprise Database: Collector Task Manager process (em7_ctaskman.py) redistributes devices between collectors when:
 - A Collector Group is created.
 - A new Data Collector is added to a Collector Group.
 - Failover or failback occurs within a Collector Group.
 - A user clicks on the lightning bolt icon (🖉) for a Collector Group, to manually force redistribution.
- The Enterprise Database: Collector Data Pull processes retrieves information from each Data Collector in a Collector Group. The process pulls data from the in_storage tables on each Data Collector. The retrieved information is stored in the Database Server.
 - Enterprise Database: Collector Data Pull, High F (em7_hfpulld). Retrieves data from each Data Collector every 15 seconds (configurable).
 - Enterprise Database: Collector Data Pull, Low F (em7_lfpulld). Retrieves data from each Data Collector every five minutes.
 - Enterprise Database: Collector Data Pull, Medium (em7_mfpulld). Retrieves data from each Data Collector every 60 seconds.
- The Enterprise Database: Collector Config Push process (config_push.py) updates each Data Collector with information on system configuration, configuration of Dynamic Applications, and any new or changed policies. This process runs once every 60 seconds and checks for differences between the configuration tables on the Database Server and the configuration tables on each Data Collector. The list of tables to be synchronized is stored in master.definitions collector config tables on the Database Server.
- Asynchronous Processes (for example, discovery or programs run from the Device Toolbox page). Asynchronous processes need to be run immediately and cannot wait until the Enterprise Database: Collector Config Push process (config_push.py) runs and tells the Data Collector to run the asynchronous process. Therefore, SL1 uses a stored procedure and the EM7 Core: Task Manager process (em7) to trigger asynchronous processes on both the Database Server and Data Collector.

- If a user requests an asynchronous process, a stored procedure on the Database Server inserts a new row in the table master_logs.spool_process on the Database Server.
- Every three seconds, the EM7 Core: Task Manager process (proc_mgr.py) checks the table master_ logs.spool_process on the Database Server for new rows.
- If the asynchronous process needs to be started on a Data Collector, a stored procedure on the Database Server inserts the same row into the table master_logs.spool_process on the Data Collector.
- Every three seconds, the EM7 Core: Task Manager process (em7) checks the table master_ logs.spool process on the Data Collector for new rows.
- If the EM7 Core: Task Manager process (em7) on the Data Collector finds a new row, the specified asynchronous process is executed on the Data Collector.

Enabling and Disabling Concurrent PowerShell for Collector Groups

To improve the process of collecting data via PowerShell, you can enable Concurrent PowerShell Collection. Concurrent PowerShell Collection allows multiple collection tasks to run at the same time with a reduced load on Data Collectors. Concurrent PowerShell Collection also prevents missed polls and data gaps because collection will execute more quickly. As a result, Data Collectors can collect more data using fewer system resources.

When you use the PowerShell Collector for Concurrent PowerShell Collection, the collection process can bypass failed or paused collections, reduce collection time, and reduce the number of early terminations (sigterms) that occur with data collection. The PowerShell Collector is an independent service running as a container on a Data Collector.

You can enable one or more Collector Groups to use concurrent PowerShell collection, and you can collect metrics for concurrent PowerShell collection.

NOTE: Concurrent PowerShell Collection is for PowerShell Performance and Performance Configuration Dynamic Application types and does not include Snippet Dynamic Applications which happen to run PowerShell commands.

For more details on concurrent PowerShell collection, see the manual *Monitoring Windows Systems with PowerShell*, the chapter on *Concurrent PowerShell*.

Enabling Concurrent PowerShell on All Collector Groups

To enable concurrent PowerShell collection service for all collector groups:

- 1. Go to the **Database Tool** page (System > Tools > DB Tool).
- 2. Enter the following in the SQL Query field:

```
INSERT INTO master.system_custom_config (`field`, `field_value`) VALUES ('enable_
powershell service', '1');
```

Disabling Concurrent PowerShell on All Collector Groups

To disable concurrent PowerShell collection service for all collector groups:

- 1. Go to the **Database Tool** page (System > Tools > DB Tool).
- 2. Enter the following in the SQL Query field:

```
UPDATE master.system_custom_config SET field_value=0 where field='enable_
powershell_service';
```

Enabling Concurrent PowerShell on a Specific Collector Group

To enable concurrent PowerShell collection for a specific collector group:

- 1. Go to the **Database Tool** page (System > Tools > DB Tool).
- 2. Enter the following in the SQL Query field:

```
INSERT INTO master.system_custom_config (`field`, `field_value`, `cug_filter`)
VALUES ('enable_powershell_service_CUGx', '1', 'collector_group_ID');
```

where:

collector_group_ID is the collector group ID. You can find this value in the **Collector Group Management** page (System > Settings > Collector Groups).

Disabling Concurrent PowerShell on a Specific Collector Group

To disable concurrent PowerShell collection for a specific collector group:

- 1. Go to the **Database Tool** page (System > Tools > DB Tool).
- 2. Enter the following in the **SQL Query** field:

```
UPDATE master.system_custom_config SET field_value=0 where field='enable_
powershell service CUGx';
```

where:

collector_group_ID is the collector group ID. You can find this value in the **Collector Group Management** page (System > Settings > Collector Groups).

Enabling and Disabling Concurrent SNMP for Collector Groups

To increase the scale for SNMP collection, you can enable **Concurrent SNMP Collection**. Concurrent SNMP Collection uses the standalone container called the SL1 SNMP Collector. The SNMP Collector is an independent service that runs as a container on a Data Collector. When you enable Concurrent SNMP Collection, each Data Collector will contain four (4) SNMP Collector containers.

NOTE: On each Data Collector, SL1 will restart each of the SNMP Collector containers periodically to ensure that each container remains healthy. When one SNMP Collector container is restarted, the other three SNMP Collector containers continue to handle the workload.

With Concurrent SNMP Collection, SNMP collection tasks can run in parallel. A single failed task will not prevent other tasks from completing.

Concurrent SNMP Collection provides:

- Improved throughput for SNMP Dynamic Applications
- Reduced use of resources on each Data Collector
- More dependable collection from high-latency Devices

For more details on concurrent SNMP collection, see the manual on **SNMP Dynamic Application Development**, the chapter on Concurrent SNMP Collection.

Enabling and Disabling Concurrent SNMP for All Collector Groups

This feature is disabled by default.

To enable Concurrent SNMP Collection in SL1:

1. After installing the ScienceLogic: SNMP Collector PowerPack, go to the **Behavior Settings** page (System > Settings > Behavior):

avior Settings				Reset
Interface URL	http://em7.mydomein.com	Enable CDP Topology	Enable LLDP Topology (BETA)	
Force Secure HTTPS		Enable Community String Indexing (VLAN Topology)		
	[disabled]	Default Country	[United States]	~
Password Reset Interval		System Timezone	[LUTC]	~
Password Hash Hethod	[MD5 (legacy)]	NFS Detection Disable		
Password Mnimum Length		Port Poling Type	[Half Open]	~
	8	Initial Discovery Scan Level	[4. Advanced Port Discovery]	
Account Lockout Type	[Disable]	Rediscovery Scan Level (Nightly)	14. Advanced Part Discovery 1	
Account Lockout Attempts	[10 attempts]	Discovery Scan Throttle	[Disabled]	
Login Delay	[Disabled]	Port Scan All Pa		
Single Instance Login (Admins)	[Disabled]		[1.Enabled]	2
Single Instance Login (Users)	[Disabled]	Port Scan Timeout	[120000 Msec.]	
Account Lockout Duration	[None]	Restart Windows Services (Agent required)	[0. Disabled]	
Lockout Contact Information	820-SCHLOGIC	Hostname Precedence	[SNIIP System Name]	
Login Header Title	ero-sci-Look	Event Interface Name Format	(name)	
		DNS Hostnames	[Strip Domain Name (Hostname)]	
System Identifier		Event Clearing Mode	[Clear All in Group]	
Ping & Poll Timeout (Msec.)	[1000]	Naintenance Minimum Severity	[0.Healthy]	
SNMP Poll Timeout (Msec.)	[1000]	Patch Maintenance Minimum Severity		
SNMP Failure Retries	[1]		[0.Healthy]	8
Initially Discovered Interface Poll Rate	[5 minutes]	SSL Certificate Expiry Soon	1	2
DHCP Community Strings	sublic	SSL Certificate Expiry Imminent	[1 week]	
(Comma seperated)		Asset Warranty Expiry	[1 month]	
Strip FQDN From Inbound Email Device Name	[Enabled]	Domain Name Expiry	[1 month]	`
Inbound Email Alert Message	[Email Nessage Body Only]	Validate Phone Number	[Disabled]	`
Event Console Ticket Life Ring Button Behavior		Dashboard Maximum Series Count Per Widget	[8]	~
	[Create / View EM7 Ticket]	Responder API Base URL	[1-1	
Automatic Ticketing Emails Force Child Ticket State and Status inheritance	[Enabled]	Topology Map Rendering		
Provent Browser Saved Credentials	Display Previous Login In Footer			2
Prevent Loading Interface in External Frames		Prefer Global Device Summary Dashboard Over Category/Class		
Hide Perpetual License Usage		Enable CBQoS Collection		
Hide "New" button on the Ticket Editor	Hide "Create a Ticket" in Toolbox menu	Enable Variable Rate Interface Counters Enhanced OID Translation		
Hide "other" filesystem type		Enable Concurrent SNMP Collection (BETA)		
		Report Size Estimation		
			<u>ل</u>	

- 2. Check the Enable Concurrent SNMP Collection field.
- 3. Click [Save].

TIP: If you do not want all of your SL1 Collectors to use Concurrent SNMP Collection, you can specify which Collector Units should use it in *Enabling a Collector Group to Use Concurrent SNMP Collection*.

Enabling and Disabling Concurrent SNMP for Collector Groups

Depending on the needs of your SL1 environment, you can enable or prevent a Collector Group from using concurrent SNMP collection.

To enable Concurrent SNMP Collection with a SL1 Collector Group:

1. Go to the **Collector Group Management** Page (System > Settings > Collector Groups):

Collector Group Management Editing Group "CU	G1"			Reset Guid
Collector Group Name CUG1 Collector Falover [Off (Maximize Managable Devices)] Generate Alert On Collector Outage [Yes] Enable Concurrent SNIMP Collection (BETA] [Use systemwide default]	Collector Selection [AsimovSandboxCU1 (Devices)] Message Collector None available	Collectors Available For Fallover IVA Fallback Mode [Automate] Fallover Delay (minutes) 5 Fallback Delay (minutes) 5	Save	
Collector Group Registry Found 1 collector	Msg Collectors	# Devices Edit Us	ser	Edit Date
1. CUG1 1 1		48 em7admin	2020-05-08 18:01:53	9

2. Click the wrench icon (*P*) for the Collector Group you want to edit. The fields at the top of the page are updated with the data for that Collector Group.

- 3. Select an option in the Enable Concurrent SNMP Collection [BETA] dropdown:
 - Use system-wide default. Select this option if you want this Collector Group to use or not use Concurrent SNMP Collection based on the **Enable Concurrent SNMP Collection [BETA]** field on the **Behavior Settings** page. This is the default.
 - Yes. Select this option to enable Concurrent SNMP Collection for this Collector Group, even if you did not enable it on the **Behavior Settings** page.
 - **No**. Select this option to prevent this Collector Group from using Concurrent SNMP Collection, even if you did enable it on the **Behavior Settings** page.
- 4. Update the remaining fields as needed, and then click [Save].

Chapter

4

Daily Health Tasks

Overview

The tasks in this chapter help you monitor the health of your SL1 system. You should perform these tasks daily (or more frequently, if you require) to gather information about the overall status of your SL1 system and to maintain operational stability.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon (\equiv).
- To view a page containing all the menu options, click the Advanced menu icon (…).

This chapter includes the following topics:

What is a Healthy SL1 System? 9	95
SL1 Self-Healing	98
SL1 Self-Monitoring	98
Monitoring System Events	9 9
Searching the System Logs	00
Deleting Entries from the System Logs	01
Monitoring System Processes	21
Viewing the List of System Processes	02
Searching and Filtering the List of System Processes	02
Monitoring the Status of Each Appliance	04
Monitoring User Actions and Events	06
Viewing the List of Audit Logs	07

Searching and Filtering the List of Audit Logs	
Special Characters	
Generating Reports on Audit Logs	
Monitoring the Status of Data Collectors	

What is a Healthy SL1 System?

The following table presents a broad list of focus areas for SL1 health that are important to track for all SL1 systems. Where a specific automated check is available, it is included in the table.

Focus Area	Check	Background	Specific Operation	Result
Patch level	Version has been updated within last 12 months	Software updates are released at least quarterly and include security and stability improvements.	Quarterly manual review of available and planned software updates from ScienceLogic	Plan to keep all SL1 platforms updated within 12 months of the latest release.
Response time	API response times for standard requests are within five seconds	API response times are highly dependent on the size of the response, however all SL1 systems should respond to a simple request without delay.	/api/organization/0	Returns a response set for the "system" organization (id 0).
Central storage capacity	At least 20% of local database storage is free and available for new data	The InnoDB database file will auto- expand but never shrink. When data is removed from the database, space is made available for future use.	Support PowerPack - Support: InnoDB Size	Built-in alerts for the Support PowerPack default to 80% used for major and 90% for critical.
CPU Consumption	System CPU utilization and load average	Both Collectors and Databases can become CPU constrained, leading to	Operating system measures of CPU utilization and load average	Load average should be at or below the system's available core count. CPU utilization of a 5 min collection should not be above 80%, 70% if hyperthreading is enabled.

Focus Area	Check	Background	Specific Operation	Result
		unhealthy performance characteristics.		
Memory Consumption	Avoid swap usage	The MariaDB database will make use of available memory for caching purposes over time, but no SL1 system should require regular swapping, which can lead to extremely poor performance.	Operating system measure of swap usage	Swap usage < 50%
Performance Data Processing	The central system is keeping up with all collection processing.	It is normal to have some backlog of "MF" data, a busy system may normally have 10,000 rows or more between each processing cycle, but they should be completely processed within each cycle (backlog should not build).	Built-in MF rows-behind compared with MF object processing rate	Backlog time < 1 processing cycle
Event Processing	The central system is keeping up with all event processing.	It is normal to have some backlog of "HF" data. A busy system may normally have 10,000 rows or more between each processing	Built-in HF rows-behind compared with HF object processing rate	Backlog time < 1 processing cycle

Focus Area	Check	Background	Specific Operation	Result
		cycle, but these rows should be completely processed within each cycle (backlog should not build)		
Run Book Automation (RBA)	The central system is keeping up with all RBA processing.	The built-in RBA engine supports parallel execution and queuing of operations. This can be critical for time- sensitive notification and integration with external systems.	Built-in alerting in the RBA scheduler will notify if the system is falling behind.	No critical events starting with the following phrase: "The automation engine is still processing"
Performance Data Collection	Collection of data is completing as scheduled.	Collection that is unbalanced or overloaded, or target devices that are misconfigured or unresponsive can result in collection not completing successfully.	SL1 Operational Insights PowerPack	Check for occurrences of "sigterming" collection. The Operational Insights PowerPack makes this easy to navigate using a dashboard.
Asynchronous Message Processing	Message collection is keeping up with asynchronous syslog and SNMP trap messages.	Data Collectors, Message Collectors, and All-in-One appliances receive	Built-in alert for suppressing of messages from "spamming" devices	By default SL1 will suppress messages from devices generating at a rate of > 25/sec/device with a built-in alert.
System Maintenance	Daily maintenance tasks are completing normally	The primary daily maintenance task (scheduled nightly outside of core business hours) is to prune old data	Regular check of the system log	Daily maintenance tasks not being terminated due to an incomplete status.

Focus Area	Check	Background	Specific Operation	Result
		from the SL1 database, which is an essential activity for long term health.		
System Backup	Backups completing per schedule.	SL1 supports both configuration- only and full backups. Both should be used since they support different recovery models	Regular check of the system log	The system log will show reports of backup completion and duration.

For more information about proactive health monitoring, watch the video at https://www.youtube.com/watch?v=AHBTi zj iY.

SL1 Self-Healing

For the SL1 classic User Interface, SL1 provides three self-healing jobs that are performed on the Database Server or All-In-One Appliance. These jobs:

- automatically set "s-em7-core:s-em7-core" as the owner and group for the file "silo.log"
- automatically restart the process em7_patch_manager if it is stuck in deactivating mode
- automatically kill queries that have run for longer than 1 hour and logs each query

SL1 Self-Monitoring

SL1 includes a self-monitoring PowerPack that is included by default with SL1 releases. This PowerPack is called "ScienceLogic Support Pack".

This self-monitoring PowerPack:

- ensures all SL1 appliances are monitored and running the same version of SL1
- ensures that all SL1 appliances appear in the Device Manager page (Registry > Devices > Device Manager)
- ensures that configuration files on SL1 appliances are kept in sync
- ensures that configuration files on SL1 clusters are kept in sync
- monitors the health and configuration of MariaDB

- generates alerts when system resources like disk-space are approaching capacity
- monitors DNS entries for Database Servers and All-In-One appliances
- monitors long-running processes and queries
- monitors out-of-memory conditions
- ensures that CRM and corosync configurations are up to date
- ensures that configuration files match among HA Database Servers
- monitors crucial SL1 processes like datapull and config_push
- monitors "rows behind" situations and generates alerts
- monitors and fixes backlogs of email messages
- generates alerts if any of the following files differ:
 - /etc/my.cnf.d/silo_mysql.cnf
 - /etc/silo.conf
 - /etc/siteconfig/mysql.siteconfig
 - /etc/siteconfig/siloconf.siteconfig

Monitoring System Events

To view the entries in the System Logs:

1. Go to the **System Logs** page (System > Monitor > System Logs).

Sys	em Logs Messages Found [1,31]	7,344]			Purge	Reset Guide
			Search Message			Search
	Date Module Severity	Massana				
1.		11.PoolWorker-19: Non-digits in oid with object id: 8303, did:1336 in dynamic app:1148 when updating perfor	mance value (val None)			2
2.		11.PoolWorker-19: Non-digits in old with object id: 8305, did: 1336 in dynamic app: 1146 when updating perfor				
3.	-	11.PoolWorker-19: Non-digits in old with object id: 8307, did:1336 in dynamic app:1148 when updating perfor	N			
4.		11.PoolWorker-19: Non-digits in oid with object id: 8308, did:1336 in dynamic app:1148 when updating perfor				
5.		11.PoolWorker-29: Non-digits in old with object id: 8303. did:1331 in dynamic app:1148 when updating perfor				
6.		11.PoolWorker-29: Non-digits in oid with object id: 8307, did:1331 in dynamic app:1148 when updating perfor				
7.		11.Poo/Worker-22: Non-digits in old with object id: 8303, did:1330 in dynamic app:1148 when updating perfor				
8		11.PoolWorker-20: Non-digits in oid with object id: 8331, did:1338 in dynamic app:1158 when updating perfor				
9.		11.Poo/Worker-22: Non-digits in old with object id: 8303, did:1330 in dynamic app:1148 when updating perfor				
10.		11.PoolWorker-20: Non-digits in oid with object id: 8332, did:1338 in dynamic app:1158 when updating perfor				
		11.PoolWorker-3; Non-digits in oid with object id; 8303, did;1325 in dynamic app;1148 when updating perform				
12	2012-03-19 11:12:43 em7 ao Minor	11.PoolWorker-22: Non-digits in oid with object id: 8305, did:1330 in dynamic app:1148 when updating perfor	mance value (val:None)			
13.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-22: Non-digits in oid with object id: 8307, did:1330 in dynamic app:1148 when updating perfor	mance value (val:None)			
14.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-22: Non-digits in oid with object id: 8307, did:1330 in dynamic app:1148 when updating perfor	mance value (val:None)			
15.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-22: Non-digits in oid with object id: 8308, did:1330 in dynamic app:1148 when updating perfor	mance value (val:None)			
16.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-22: Non-digits in oid with object id: 8310, did:1330 in dynamic app:1148 when updating perfor	mance value (val:2.666666666666	667E-5)		
17.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-1: Non-digits in oid with object id: 8331, did:1328 in dynamic app:1158 when updating perform	nance value (val:None)			
18.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-3: Non-digits in oid with object id: 8307, did:1325 in dynamic app:1148 when updating perform	nance value (val:None)			[]]
19.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-3: Non-digits in oid with object id: 8310, did:1325 in dynamic app:1148 when updating perform	nance value (val:2.66666666666666	67E-5)		
20.	2012-03-19 11:12:43 em7_ao Minor	11.Poo/Worker-1: Non-digits in oid with object id: 8332, did:1328 in dynamic app:1158 when updating perform	nance value (val:None)			[7]
21.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-17: Non-digits in oid with object id: 8303, did:1337 in dynamic app:1148 when updating perfor	mance value (val:None)			
22.	2012-03-19 11:12:43 em7_ao Minor	11.Poo/Worker-17: Non-digits in oid with object id: 8307, did:1337 in dynamic app:1148 when updating perfor	mance value (val:None)			
23.	2012-03-19 11:12:43 em7_ao Minor	11.Poo/Worker-17: Non-digits in oid with object id: 8310, did:1337 in dynamic app:1148 when updating perfor	mance value (val:2.666666666666	667E-5)		
24.	2012-03-19 11:11:58 em7_ao Minor	11.PooWorker-12: Non-digits in oid with object id: 8348, did:1312 in dynamic app:1163 when updating perfor	mance value (val:None)			
25.	2012-03-19 11:11:58 em7_ao Minor	11.PoolWorker-12: Non-digits in old with object id: 8349, did:1312 in dynamic app:1163 when updating perfor	mance value (val:None)			
D.G	ewing Page: 3001 👻					
141	swing Page, sooj 💌					Delete

- 2. In the **System Logs** page, pay special attention to any log entry tagged as Critical or Major. These entries might require additional diagnostics.
- 3. For each log entry, the **System Logs** page displays:

- Date. Date and time the log entry was generated.
- Module. Name of the appliance that generated the log entry.
- Severity. Specifies the severity assigned to the log entry. The choices are:
 - Healthy
 - Notice
 - Minor
 - Major
 - Critical
- Message. Descriptive text included in the log entry.

Searching the System Logs

When viewing the **System Logs**, you might want to sort the entries by date or by log message. This is helpful when you want to view information about a specific occurrence of a system event. To search the **System Logs**:

1. Go to the **System Logs** page (System > Monitor > System Logs).

iys	em Logs Messages Found [1,31	7,344]			Purge Reset Guide
			Search Message		Search
	Date Module Severity	/ Message			
1.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-19: Non-digits in oid with object id: 8303, did:1336 in dynamic app:1148 when updating p	erformance value (val:None)		
2.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-19: Non-digits in old with object id: 8305, did:1336 in dynamic app:1148 when updating p	erformance value (val:None)		
3.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-19: Non-digits in oid with object id: 8307, did:1336 in dynamic app:1148 when updating p	erformance value (val:None)		
4.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-19: Non-digits in oid with object id: 8308, did:1336 in dynamic app:1148 when updating p	erformance value (val:None)		
5.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-29: Non-digits in oid with object id: 8303, did:1331 in dynamic app:1148 when updating p	erformance value (val:None)		
6.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-29: Non-digits in oid with object id: 8307, did:1331 in dynamic app:1148 when updating p	erformance value (val:None)		
7.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-22: Non-digits in oid with object id: 8303, did:1330 in dynamic app:1148 when updating p	erformance value (val:None)		
8.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-20: Non-digits in oid with object id: 8331, did:1338 in dynamic app:1158 when updating p	erformance value (val:None)		
9.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-22: Non-digits in old with object id: 8303, did:1330 in dynamic app:1148 when updating p	erformance value (val:None)		
10.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-20: Non-digits in old with object id: 8332, did:1338 in dynamic app:1158 when updating p	erformance value (val:None)		
11.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-3: Non-digits in oid with object id: 8303, did:1325 in dynamic app:1148 when updating pe	rformance value (val:None)		
12.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-22: Non-digits in oid with object id: 8305, did:1330 in dynamic app:1148 when updating p	erformance value (val:None)		
13.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-22: Non-digits in old with object id: 8307, did:1330 in dynamic app:1148 when updating p	erformance value (val:None)		
14.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-22: Non-digits in oid with object id: 8307, did:1330 in dynamic app:1148 when updating p	erformance value (val:None)		
15.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-22: Non-digits in oid with object id: 8308, did:1330 in dynamic app:1148 when updating p	erformance value (val:None)		
16.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-22: Non-digits in oid with object id: 8310, did:1330 in dynamic app:1148 when updating p	erformance value (val:2.6666666666	66667E-5)	
17.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-1: Non-digits in oid with object id: 8331, did:1328 in dynamic app:1158 when updating pe	rformance value (val:None)		
18.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-3: Non-digits in old with object id: 8307, did:1325 in dynamic app:1148 when updating pe	rformance value (val:None)		
19.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-3: Non-digits in oid with object id: 8310, did:1325 in dynamic app:1148 when updating pe	rformance value (val:2.66666666666	6667E-5)	
20.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-1: Non-digits in oid with object id: 8332, did:1328 in dynamic app:1158 when updating pe	rformance value (val:None)		
21.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-17: Non-digits in old with object id: 8303, did:1337 in dynamic app:1148 when updating p	erformance value (val:None)		
22.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-17: Non-digits in oid with object id: 8307, did:1337 in dynamic app:1148 when updating p	erformance value (val:None)		
23.	2012-03-19 11:12:43 em7_ao Minor	11.PoolWorker-17: Non-digits in oid with object id: 8310, did:1337 in dynamic app:1148 when updating p	erformance value (val:2.6666666666	66667E-5)	
24.	2012-03-19 11:11:58 em7_ao Minor	11.PoolWorker-12: Non-digits in old with object id: 8348, did:1312 in dynamic app:1163 when updating p	erformance value (val:None)		
25.	2012-03-19 11:11:58 em7_ao Minor	11.PoolWorker-12: Non-digits in oid with object id: 8349, did:1312 in dynamic app:1163 when updating p	erformance value (val:None)		
	ewing Page: 3001 👻				

- 2. The search fields at the top of the **System Logs** page allows you to search for log entries by message, date, or module.
 - Search where. Specifies the parameter you want to search by. You can select from the following:
 - Search Message. Searches all log entries for those that match the text that you enter in the regular expression field.
 - Search Module ID. Searches all log entries for those that have the same module ID text as that entered in the regular expression field.

- Search Date = (Y-m-d H:i:s). Searches all log entries for those that have a date and time that is equal to the date entered in the regular expression field.
- Search Date > (Y-m-d H:i:s). Searches all log entries for those that have a date and time that is later than the date entered in the regular expression field.
- Search Date Like (Y-m-d H:i:s). Searches all log entries for those that have a date and time that is similar to the date entered in the regular expression field.
- Search Date Like != (Y-m-d H:i:s). Searches all log entries for those that have a date and time that is **not** similar to the date entered in the regular expression field.
- **regular expression**. In this field you manually enter the text to search for. You can use the following special characters in this field:
 - * Match zero or more characters preceding the asterisk. For example:

"dell*" would match "dell", "dell2650", "dell7250" and "dell1700N".

"*dell*" would match "mydell", "dell", "dell2650", "dell7250" and "dell1700N".

- % Match zero or more characters preceding the asterisk. This special character behaves in the same way as the asterisk.
- 3. When you click the **[Search]** button, the **System Logs** page will be refreshed and will display only the log entries that match the search parameters.

Deleting Entries from the System Logs

To save space, you might want to remove some or all log entries from the system log.

There are two ways to delete entries from the **System Logs** page:

- 1. Go to the **System Logs** page (System > Monitor > System Logs).
- 2. In the System Logs page, click the [Purge] button to delete all entries from the System Logs.

Or:

- 1. Go to the **System Logs** page (System > Monitor > System Logs).
- 2. In the **System Logs** page, highlight each entry you want to delete. To select multiple entries, right-click while holding down the [**<Ctrl>**] key.
- 3. Click the **[Delete]** button to delete all the selected entries from the System Logs.

Monitoring System Processes

The **System Processes** page (System > Monitor > Admin System Processes) allows you to view read-only information about the execution of SL1's system processes. System Processes gather, manipulate, and publish the data used in SL1. These system processes can be configured and debugged in the **Process Manager** page (System > Settings > Admin Processes).

NOTE: If you work frequently with ScienceLogic Support, ensure that you verify periodically which processes are running in debug mode, and disable debug mode as soon as is reasonable. This will reduce the noise generated to your log files and will reduce load on the /var/log/em7 partition on the central database.

Viewing the List of System Processes

To view the list of system processes for all appliances:

- 1. Go to the **System Processes** page (System > Monitor > Admin System Processes).
- 2. The System Processes page displays the following for each process:
 - **Appliance**. The appliance where the process ran or is currently running. This field will contain the device name of the appliance.
 - Process. Name of the process.
 - ID. Unique numeric ID automatically assigned to the process by SL1.
 - Start Time. Date and time at which the process started running.
 - End Time. Date and time at which the process stopped running.
 - **Duration**. Amount of time, in hours, minutes, and seconds, for which the process ran.
 - Frequency. Frequency with which SL1 launches the process. Possible values are:
 - Asynchronous. The process is launched in response to a system event or user request. Asynchronous events display a value of "-1" (negative one) in this column.
 - Always. The process always runs while SL1 is running. Always running processes display a value of "0" (zero) in this column.
 - The process runs at intervals in minutes ranging from 1 Minute to 1440 Minutes (Daily).
 - **Percent**. Percent of **Run Length** (defined in the **Process Manager** page) currently in use by the process.
 - Instances. This field is not currently in use.
 - Max Instances. Maximum number of instances of the process that have run in parallel.
 - **Processed**. Number of records processed by this run of the process.
 - Errors. Number of errors encountered by this run of the process.

Searching and Filtering the List of System Processes

The **System Processes** page includes ten filters. You can filter the list of processes by one or multiple of the following parameters: appliance, process name, start time, end time, duration, frequency, percent, max instances, processed, and errors. Only processes that meet all the filter criteria will be displayed in the **System Processes** page.

You can filter by one or more of the following parameters. The list of system processes is dynamically updated as you select each filter.

- For eight of the filters, you must enter text to match against. The user interface will search for processes that match the text, including partial matches. Text matches are not case sensitive. You can use the following special characters in each filter:
 - , Specifies an "or" operation. For example:
 - "dell, micro" would match all values that contain the string "dell" OR the string "micro".
 - ! Specifies a "not" operation. For example:

"!dell" would match all values that do not contain the string "dell".

- Appliance. You can enter text to match, including special characters, and the System Processes page will display only processes that have a matching appliance name.
- **Process**. You can enter text to match, including special characters, and the **System Processes** page will display only processes that have a matching process name.
- *ID*. You can enter text to match, and the **System Processes** page will display only processes that have a matching ID.
- **Start Time**. Only those processes that match all the previously selected fields and have the specified start date and time will be displayed. The choices are:
 - All. Display processes with all start dates and times.
 - Last Minute. Display only processes that started within the last minute.
 - Last Hour. Display only processes that started within the last hour.
 - Last Day. Display only processes that started within the last day.
 - Last Week. Display only processes that started within the last week.
 - Last Month. Display only processes that started within the last month.
 - Last Year. Display only processes that started within the last year.
- **End Time**. Only those processes that match all the previously selected fields and have the specified end date and time will be displayed. The choices are:
 - All. Display processes with all end dates and times.
 - Last Minute. Display only processes that ended within the last minute.
 - Last Hour. Display only processes that ended within the last hour.
 - Last Day. Display only processes that ended within the last day.
 - Last Week. Display only processes that ended within the last week.
 - Last Month. Display only processes that ended within the last month.
 - Last Year. Display only processes that ended within the last year.
- **Duration**. You can enter text to match, including special characters, and the **System Processes** page will display only processes that have a matching duration.

- **Frequency**. You can enter text to match, including special characters, and the **System Processes** page will display only processes that have a matching frequency.
- **Percent**. You can enter text to match, including special characters, and the **System Processes** page will display only processes that have a matching percent.
- Instances. This field is not currently in use. It is not recommended to filter the System Processes by this field.
- Max Instances. You can enter text to match, including special characters, and the System Processes page will display only processes that have a matching number of Max Instances.
- **Processed**. You can enter text to match, including special characters, and the **System Processes** page will display only processes that have a matching number of records processed.
- *Errors*. You can enter text to match, including special characters, and the **System Processes** page will display only processes that have a matching number of errors.


Monitoring the Status of Each Appliance

The **Appliance Manager** page allows you to view information, including license status, about each appliance in your system.

From the **Appliance Manager** page, you can also access the Web Configuration Utility for each appliance and the database administration tool for the Database Server.

To view the **Appliance Manager** page:

1. Go to the Appliance Manager page (System > Settings > Appliances).



2. The **Appliance Manager** page displays the following about each appliance:

- Name. Name of the appliance.
- IP Address. Primary IP address for the appliance.
- Module Type. Type of appliance. Choices are:
 - All-In-One Appliance
 - Database Server
 - Administration Portal
 - Data Collector
 - Message Collector
 - Integration Server
- **Collector Group**. For Data Collectors and All-In-One Appliances, specifies the Collector Group associated with the appliance.
- Description. Description of the appliance.
- Build. Specifies the latest build installed on the appliance.
- MariaDB. Specifies the version of MariaDB running on the All-In-One Appliance, Database Server, Data Collector, or Message Collector.
- Capacity. For Database Servers, specifies the licensed capacity of the appliance.
- Allocation. For Data Collectors, specifies the number of devices aligned with the appliance.
- *ID*. Unique numeric ID, automatically assigned by the platform to each appliance in the **Appliance Manager** page.
- Validated. Specifies whether the license is valid.
- Endpoint. SL1 Agent endpoint for the Gen 1 Agent.
- **Needs Reboot?**. Specifies whether the appliance requires reboot to add latest kernel or security updates. This column is updated every 30 minutes. Hover your mouse to determine why the reboot is required and information about kernel version, packages, and last reboot.
- Task Manager Paused? . Specifies whether the task manager service (em7) is paused. This value is updated every two minutes.
- Edit Date. Date the appliance's information was discovered or last edited.
- Edit User. User who last edited the appliance's information.
- https://sciencelogic.atlassian.net/wiki/spaces/ENG/pages/12347898729/Historical+RPM +Pkg+Upd+Ticket+Information
- Create Date. Date and time the appliance was registered and licensed.
- 3. If an SL1 appliance is running a different version of SL1 than the Database Server, that appliance is highlighted in the **Appliance Manager** page.
- 4. For all SL1 appliances, SL1 runs the system status script every 15 minutes. You can click on the logs icon (

- 5. For Database Servers, you can click the gear icon (*) to access the phpMyAdmin interface for the Database Server. In this interface, you can view all the database tables on the Database Server.
- 6. For Data Collectors and Message Collectors, you can click the lightning bolt icon (🖉) to manually force the Database Server to send the latest configuration information.

Monitoring User Actions and Events

The **Audit Logs** page provides an audit trail for SL1. The **Audit Logs** page displays a record of actions in SL1 that are generated by **users** or by **managed elements**. These actions are organized by organization.

Some of the actions that are logged in the Audit Logs page include:

- User logins to SL1
- Organization name changes
- The addition, editing, or deletion of elements in SL1

NOTE: Entries for the addition, editing, and deletion of elements includes the affected device ID, when applicable.

- The installation, editing, or uninstallation of PowerPacks, including when a PowerPack is imported or installed from Global Manager to a Stack
- Manually triggered discovery sessions
- Events and cleared events
- Devices being set to maintenance mode or devices no longer being in maintenance mode
- The unalignment of Dynamic Applications from devices and the deletion of that data
- The creation, editing, or deletion of Run Book Automation policies
- The addition or deletion of Reports
- Asset Record changes
- User-defined changes to settings on the **Data Retention Settings** page (System > Settings > Data Retention)
- Changes to settings on the System Threshold Defaults page (System > Settings > Thresholds > System)
- API requests that use a PUT, POST, or DELETE method

NOTE: By default, the Audit Logs page displays a list of actions associated with all organizations.

Viewing the List of Audit Logs

To view the list of log entries in the **Audit Logs** page:

1. Go to the **Audit Logs** page (System > Monitor > Audit Logs).

Date/Time •	Source	Organization	Message
(All	T		
1. 2017-05-18 15:48:20	API Server	System	User 'em7admin' Performed a POST request to resource /api/organization [result:CREATED: "organization /api/or
2. 2017-05-18 15:48:20	API Server	System	User 'em7admin' Performed a POST request to resource /api/account [result:CREATED: "account /api/account/2
3. 2017-05-18 15:48:20	API Server	System	User 'em7admin' Performed a POST request to resource /api/credential/idap [result:CREATED: "credential /api/cr
4. 2017-05-18 15:48:20	API Server	System	User 'em7admin' Performed a POST request to resource /api/account_policy [result:CREATED: "User Policy /api/
5. 2017-05-18 16:21:20	Login	System	User 'em7admin' Successfully Logged-In from IP address: 10.64.34.43/54021.
6. 2017-05-18 16:22:32	API Server	System	User 'em7admin' Performed a PUT request to resource /api/filestore/system_patch/EM7_v8.4.1.jenkins_EM7_G3
7. 2017-05-18 16:22:32	API Server	System	User 'em7admin' Performed a PUT request to resource /api/filestore/system_patch/EM7_v8.4.1.jenkins_EM7_G3
8. 2017-05-18 16:22:33	API Server	System	User 'em7admin' Performed a PUT request to resource /api/filestore/system_patch/EM7_v8.4.1.jenkins_EM7_G3
9. 2017-05-18 16:22:33	API Server	System	User 'em7admin' Performed a PUT request to resource /api/filestore/system_patch/EM7_v8.4.1.jenkins_EM7_G3
0. 2017-05-18 16:22:33	API Server	System	User 'em7admin' Performed a PUT request to resource /api/filestore/system_patch/EM7_v8.4.1.jenkins_EM7_G3
1. 2017-05-18 16:22:33	API Server	System	User 'em7admin' Performed a PUT request to resource /api/filestore/system_patch/EM7_v8.4.1.jenkins_EM7_G3
2. 2017-05-18 16:22:33	API Server	System	User 'em7admin' Performed a PUT request to resource /api/filestore/system_patch/EM7_v8.4.1.jenkins_EM7_G3
3. 2017-05-18 16:22:33	API Server	System	User 'em7admin' Performed a PUT request to resource /api/filestore/system_patch/EM7_v8.4.1.jenkins_EM7_G3
4. 2017-05-18 16:22:33	API Server	System	User 'em7admin' Performed a PUT request to resource /apl/filestore/system_patch/EM7_v8.4.1.jenkins_EM7_G3
5. 2017-05-18 16:22:33	API Server	System	User 'em7admin' Performed a PUT request to resource /apl/filestore/system_patch/EM7_v8.4.1.jenkins_EM7_G0
6. 2017-05-18 16:22:34	API Server	System	User 'em7admin' Performed a PUT request to resource /apl/filestore/system_patch/EM7_v8.4.1.jenkins_EM7_G3
7. 2017-05-18 16:22:34	API Server	System	User 'em7admin' Performed a PUT request to resource /apl/filestore/system_patch/EM7_v8.4.1.jenkins_EM7_G0
8. 2017-05-18 16:22:34	API Server	System	User 'em7admin' Performed a PUT request to resource /apl/filestore/system_patch/EM7_v8.4.1.jenkins_EM7_G3
9. 2017-05-18 16:22:34	API Server	System	User 'em7admin' Performed a PUT request to resource /apl/filestore/system_patch/EM7_v8.4.1.jenkins_EM7_G0
0. 2017-05-18 16:22:34	API Server	System	User 'em7admin' Performed a PUT request to resource /apl/filestore/system_patch/EM7_v8.4.1.jenkins_EM7_G3
1. 2017-05-18 16:22:34	API Server	System	User 'em7admin' Performed a PUT request to resource /apl/filestore/system_patch/EM7_v8.4.1.jenkins_EM7_G3
2. 2017-05-18 16:22:34	API Server	System	User 'em7admin' Performed a PUT request to resource /apl/filestore/system_patch/EM7_v8.4.1.jenkins_EM7_G3
3. 2017-05-18 16:22:35	API Server	System	User 'em7admin' Performed a PUT request to resource /apl/filestore/system_patch/EM7_v8.4.1.jenkins_EM7_G3
4. 2017-05-18 16:22:36	API Server	System	User 'em7admin' Performed a PUT request to resource /apl/filestore/system_patch/EM7_v8.4.1.jenkins_EM7_G3
5. 2017-05-18 16:22:36	API Server	System	User 'em7admin' Performed a PUT request to resource /apl/filestore/system_patch/EM7_v8.4.1.jenkins_EM7_G6
6. 2017-05-18 16:22:36	API Server	System	User 'em7admin' Performed a PUT request to resource /apl/filestore/system_patch/EM7_v8.4.1.jenkins_EM7_G6
7. 2017-05-18 16:22:36	API Server	System	User 'em7admin' Performed a PUT request to resource /apl/filestore/system_patch/EM7_v8.4.1.jenkins_EM7_G
8. 2017-05-18 16:22:36	API Server	System	User 'em7admin' Performed a PUT request to resource /apl/filestore/system_patch/EM7_v8.4.1.jenkins_EM7_G8
9. 2017-05-18 16:22:36	API Server	System	User 'em7admin' Performed a PUT request to resource /api/filestore/system_patch/EM7_v8.4.1.jenkins_EM7_G
0. 2017-05-18 16:22:36	API Server	System	User 'em7admin' Performed a PUT request to resource /api/filestore/system_patch/EM7_v8.4.1.jenkins_EM7_G

- 2. The **Audit Logs** page displays all actions that are performed by users or managed elements in SL1. For each action, the **Audit Logs** page displays:
 - Date/Time. Date and time the action occurred and the log entry was created.
 - **Source**. Source of the log entry. This usually describes where the action took place. For example, if you change the contact information for your account, an entry will be made in the audit log, and the source will be "Contact Information."
 - Organization. Organization associated with the action.
 - Message. Text of the log entry.

Searching and Filtering the List of Audit Logs

The Filter-While-You-Type fields appear as a row of blank fields at the top of the list. These fields allow you to filter the items that appear in the list.

The list is dynamically updated as you select each filter. For each filter, you must make a selection from a dropdown menu or type text to match against. SL1 will search for entries that match the text, including partial matches. Text matches are not case-sensitive, and you can use special characters in each text field.

By default, the cursor is placed in the first Filter-While-You-Type field. You can use the <Tab> key or your mouse to move your cursor through the fields.

You can filter by one or more of the following parameters. Only items that meet all of the filter criteria are displayed on the page.

The following describes each filter on the **Audit Logs** page:

- Date/Time. Only those audit logs that have the specified creation date will be displayed. The choices are:
 - All. Display all audit logs that match the other filters.
 - Last Minute. Display only audit logs that have been created within the last minute.
 - Last Hour. Display only audit logs that have been created within the last hour.
 - Last Day. Display only audit logs that have been created within the last day.
 - Last Week. Display only audit logs that have been created within the last week.
 - Last Month. Display only audit logs that have been created within the last month.
 - Last Year. Display only audit logs that have been created within the last year.
- **Source**. You can enter text to match, including special characters, and the Audit Logs page will display only audit logs that have a matching source.
- **Organization**. You can enter text to match, including special characters, and the Audit Logs page will display only audit logs that have a matching organization.
- **Message**. You can enter text to match, including special characters, and the Audit Logs page will display only audit logs that have a matching message.

Special Characters

You can include the following special characters to filter by each column except those that display date and time:

NOTE: When searching for a string, SL1 will match substrings by default, even if you do not include any special characters. For example, searching for "hel" will match both "hello" and "helicopter". When searching for a numeric value, SL1 will not match a substring unless you use a special character.

String and Numeric

• , (comma). Specifies an "OR" operation. Works for string and numeric values. For example:

"dell, micro" matches all values that contain the string "dell" OR the string "micro".

• & (ampersand). Specifies an "AND " operation. Works for string and numeric values. For example:

"dell & micro" matches all values that contain both the string "dell" AND the string "micro", in any order.

• ! (exclamation point). Specifies a "not" operation. Works for string and numeric values. For example:

"!dell" matches all values that do not contain the string "dell".

"! ^ micro" would match all values that do not start with "micro".

"!fer\$" would match all values that do not end with "fer".

"! ^ \$" would match all values that are not null.

"! ^ " would match null values.

"!\$" would match null values.

"!*" would match null values.

"happy, !dell" would match values that contain "happy" OR values that do not contain "dell".

NOTE: You can also use the "!" character in combination with the arithmetic special characters (min-max, >, <, >=, <=, =) described below.

• * (asterisk). Specifies a "match zero or more" operation. Works for string and numeric values. For a string, matches any string that matches the text before and after the asterisk. For a number, matches any number that contains the text. For example:

"hel*er" would match "helpers" and "helicopter" but not "hello".

"325*" would match "325", "32561", and "325000".

"*000" would match "1000", "25000", and "10500000".

• ? (question mark). Specifies "match any one character". Works for string and numeric values. For example:

"l?ver" would match the strings "oliver", "levers", and "lover", but not "believer".

"135?" would match the numbers "1350", "1354", and "1359", but not "135" or "13502"

String

- ^ (caret). For strings only. Specifies "match the beginning". Matches any string that begins with the specified string. For example:
 - "^sci" would match "scientific" and "sciencelogic", but not "conscious".
 - "^happy\$" would match only the string "happy", with no characters before or after.
 - "! ^ micro" would match all values that do not start with "micro".
 - "! ^ \$" would match all values that are not null.
 - "! ^ " would match null values.

• \$ (dollar sign). For strings only. Specifies "match the ending". Matches any string that ends with the specified string. For example:

"ter\$" would match the string "renter" but not the string "terrific".

"^happy\$" would match only the string "happy", with no characters before or after.

"!fer\$" would match all values that do not end with "fer".

"! ^ \$" would match all values that are not null.

"!\$" would match null values.

NOTE: You can use both ^ and \$ if you want to match an entire string and only that string. For example, "^ tern\$" would match the strings "tern" or "Tern" or "TERN"; it would not match the strings "terne" or "cistern".

Numeric

• min-max. Matches numeric values only. Specifies any value between the minimum value and the maximum value, including the minimum and the maximum. For example:

"1-5 "would match 1, 2, 3, 4, and 5.

• - (dash). Matches numeric values only. A "half open" range. Specifies values including the minimum and greater or including the maximum and lesser. For example:

"1-" matches 1 and greater. So would match 1, 2, 6, 345, etc.

"-5" matches 5 and less. So would match 5, 3, 1, 0, etc.

• > (greater than). Matches numeric values only. Specifies any value "greater than". For example:

">7" would match all values greater than 7.

• < (less than). Matches numeric values only. Specifies any value "less than". For example:

"<12" would match all values less than 12.

• >= (greater than or equal to). Matches numeric values only. Specifies any value "greater than or equal to". For example:

"=>7" would match all values 7 and greater.

• <= (less than or equal to). Matches numeric values only. Specifies any value "less than or equal to". For example:

"= <12" would match all values 12 and less.

• = (equal). Matches numeric values only. For numeric values, allows you to match a negative value. For example:

"=-5 " would match "-5" instead of being evaluated as the "half open range" as described above.

Additional Examples

- "aio\$". Matches only text that ends with "aio".
- "^ shu". Matches only text that begins with "shu".
- "^ silo\$". Matches only the text "silo", with no characters before or after.
- "!silo". Matches only text that does not contains the characters "silo".
- "! ^ silo". Matches only text that does not start with "silo".
- "!0\$". Matches only text that does not end with "0".
- "! ^ silo\$". Matches only text that is not the exact text "silo", with no characters before or after.
- "! ^ ". Matches null values, typically represented as "--" in most pages.
- "!\$". Matches null values, typically represented as "--" in most pages.
- "! ^ \$". Matches all text that is not null.
- silo, laggr". Matches text that contains the characters "silo" and also text that does not contain "aggr".
- "silo, 02, laggr". Matches text that contains "silo" and also text that contains "02" and also text that does not contain "aggr".
- "silo, 02, laggr, !01". Matches text that contains "silo" and also text that contains "02" and also text that does not contain "aggr" and also text that does not contain "01".
- "^s*i*l*o\$". Matches text that contains the letter "s", "i", "l", "o", in that order. Other letters might lie between these letters. For example "sXiXIXo" would match.
- "!^ s*i*l*o\$". Matches all text that does not that contains the letter "s", "i", "l", "o", in that order. Other letters might lie between these letters. For example "sXiXIXo" would not match.
- "!vol&!silo". Matches text that does not contain "vol" AND also does not contain "silo". For example, "volume" would match, because it contains "vol" but not "silo".
- "!vol&02". Matches text that does not contain "vol" AND also contains "02". For example, "happy02" would match, because it does not contain "vol' and it does contain "02".
- "aggr,!vol&02". Matches text that contains "aggr" OR text that does not contain "vol" AND also contains "02".
- "aggr,!vol&!infra". Matches text that contains "aggr" OR text that does not contain "vol" AND does not contain "infra".
- "*". Matches all text.
- "!*". Matches null values, typically represented as "--" in most pages.
- "silo". Matches text that contains "silo".
- " !silo ". Matches text that does not contain "silo".
- "!^silo\$". Matches all text except the text "silo", with no characters before or after.
- "-3,7-8,11,24,50-". Matches numbers 1, 2, 3, 7, 8, 11, 24, 50, and all numbers greater than 50.

- "-3,7-8,11,24,50-,a". Matches numbers 1, 2, 3, 7, 8, 11, 24, 50, and all numbers greater than 50, and text that includes "a".
- "?n". Matches text that contains any single character and the character "n". For example, this string would match "an", "bn", "cn", "1n", and "2n".
- "n*SAN". Matches text the contains "n", zero or any number of any characters and then "SAN". For example, the string would match "nSAN", and "nhamburgerSAN".
- "^?n*SAN\$". Matches text that begins with any single character, is following by "n", and then zero or any number of any characters, and ends in "SAN".

Generating Reports on Audit Logs

You can export the entries on the Audit Logs page as one of the following report types:

- Acrobat document (.pdf)
- Web page (.html)
- Excel spreadsheet (.xlsx)
- OpenDocument Spreadsheet (.ods)
- Comma-separated values (.csv)

When you create a report in the **Audit Logs** page, SL1 includes only those logs that appear in the current view of the page. If you filter the entries on the **Audit Logs** page, only those logs that meet the filter criteria and currently appear on the page will appear in the report.

To generate an audit logs report:

- 1. From the Audit Logs page, click the [Report] button. The Export current view as a report window appears.
- 2. In the **Output Format** field, select the report format type.
- 3. Click [Generate].

Monitoring the Status of Data Collectors

The Collector Status page displays the status of each Data Collector and Message Collector in your system.

NOTE: This page does not appear in All-In-One Appliances.

Data Collectors retrieve data from managed devices and applications. This collection occurs during initial discovery, during nightly updates, and in response to policies defined for each managed device. The collected data is used to trigger events, display data in the user interface, and generate graphs and reports.

Message Collectors receive and process inbound, asynchronous syslog and trap messages from monitored devices. In most distributed systems, dedicated **Message Collector** appliances perform message collection. A single **Message Collector** can handle syslog and trap messages from devices that are monitored by multiple **Data Collectors**.

To perform collection, you must define a Collector Group and align it with at least one Data Collector. If your Collector Group includes multiple Data Collectors, you can configure the Collector Group for high-availability. For details, see the section on Collector Groups.

To ensure the health of your system, you should periodically check on the status of the Data Collectors and Message Collectors. To access the **Collector Status** page:

1. Go to the **Collector Status** page (System > Monitor > Collector Status).

Collector Status				🔦 Activity	Em7admin 🗸 🥄	ScienceLogic
Collector Status					Refres	h Guide
Collector Name 1. 10-64-171-180-MC 2. 10-64-171-173-CU-MOSS1 3. 10-64-171-173-CU-MOSS1 4. 10-64-171-175-CU-UsualSuspects1 5. 10-84-171-175-CU-UsualSuspects2 6. 10-84-171-175-CU-SarumAndCoke 7. 10-64-171-172-CU-SarumAndCoke 8. 10-64-171-172-CU-Sared 9. 10-64-171-172-CU-RNG 9. 10-64-171-173-CU-RaceCondition1 11. 10-64-171-182-CU-RaceCondition2 2. 10-64-171-183-CU-RaceCondition2	Collector ID 13 6 7 8 9 10 5 11 12 14 15 16	Collector Address 10.64.171.180 10.64.171.173 10.64.171.173 10.64.171.175 10.64.171.175 10.64.171.175 10.64.171.172 10.64.171.172 10.64.171.182 10.64.171.182	Group ID 	Group name 	Last State Change 2021-03-29 16:34:04 2021-03-29 16:34:05 2021-03-29 16:34:05 2021-03-29 16:34:05	Available [0] Available [0] Available [0] Available [0] Available [0] Available [0] Available [0] Available [0] Available [0]

- 2. For each Data Collector in your system, the **Collector Status** page displays the following:
 - Collector Name. Name of the Data Collector or Message Collector.
 - **Collector ID**. Unique numeric ID automatically assigned to the Data Collector or Message Collector by SL1.
 - Collector Address. IP address of the Data Collector or Message Collector.
 - **Group ID**. Unique numeric ID of the Collector Group associated with the Data Collector or Message Collector.
 - Group Name. Name of the Collector Group associated with the Data Collector or Message Collector.
 - Last State Change. Date and time the platform last polled the status of the Data Collector or Message Collector.
 - Collector State. Operating state of the Data Collector or Message Collector.

Chapter

5

Upgrading SL1

Overview

This chapter provides an overview of the **System Updates** page, detailed steps for performing an SL1 upgrade, and detailed steps on upgrading MariaDB, upgrading PowerPacks, and performing reboots.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon (=).
- To view a page containing all the menu options, click the Advanced menu icon (…).

For more information about reasons to upgrade, watch the video at https://www.youtube.com/watch?v=QVmldOenro4.

This chapter includes the following topics:

Reference: The System Updates Page	
Reference: Viewing the List of Updates	
Reference: Viewing the Log Files for Updates	
Workflow	
Planning	
Scheduling Maintenance Windows	
Updating SL1 Appliances to Oracle Linux	
Pre-Upgrade Best Practices	
Backing Up Settings in the NextUI	
Backing Up SSL Certificates	
Setting the Timeout for PhoneHome Watchdog	

Adjusting the Timeout for Staging and Deploying	
Running the System Status Script Before Upgrading	
Upgrading the SL1 Distributed Architecture on SL1 Versions 8.5.0 and Earlier	
Upgrading the SL1 Distributed Architecture on SL1 versions 8.6.0 and Later	
Upgrading SL1 Extended Architecture	
Manual Steps for Updates to 8.4.x and Earlier Systems	
Automatically Upgrading MariaDB with a Script	
Manually Upgrading MariaDB	
Rebooting Appliances in the SL1 Distributed Stack	
Restoring Settings for NextUI	
Restoring the SSL Certificate	
Resetting the Timeout for PhoneHome Watchdog	
Updating Default PowerPacks	
Configuring Subscription Billing	

Reference: The System Updates Page

The **System Updates** page (System > Tools > Updates) allows you to update the software on your SL1 appliances.

You must first download the update file to the local computer.

You can then import the software update through the user interface.

After you import a software update to your SL1 system, the SL1 system can automatically *stage* the software update. Staging is when the software is copied to each ScienceLogic appliance. Staging allows SL1 to simultaneously apply the software changes to each ScienceLogic appliance, regardless of the speed of the connection to each ScienceLogic appliance.

You can allow the SL1 system to automatically stage the software or you can manually stage the software.

After the software update is staged, you can deploy the software.

WARNING: To apply updates to an existing Data Collector, that Data Collector must be a member of a Collector Group. In some SL1 systems, users might have to create a Collector Group for a single Data Collector before applying updates.

NOTE: To conserve disk space on Data Collectors and Message Collectors, after an update, SL1 removes previous Docker images.

Reference: Viewing the List of Updates

The **System Updates** page (System > Tools > Updates) displays the following about each update:

System Updates								Appliance List Im	iport Reset Guide
EM7 Releases Versions Found [1] EM7 Version • 1. EM7 10.1.0	OS Version Platform 2020-05-01	Update Signature Base Installation	Imported On 2020-06-25 15:46:01	Imported By em7admin	Complete	Staging Status	Preupgrade Status	Deployment Status	Deployment Status Date 2020-06-25 22:59:53
						_			

TIP: To sort the list of update files, click on a column heading. The list will be sorted by the column value, in ascending order. To sort by descending order, click the column heading again. The *Deployed Status Date* column sorts by descending order on the first click; to sort by ascending order, click the column heading again.

- EM7 Version. Name and version number for the software update.
- OS Version. Name and number of the platform OS update.
- **Update Signature**. Name of the entity that released the update and type of update. Usually "ScienceLogic Official Release".
- Imported On. Date and time the software update was loaded onto the SL1 system.
- Imported By. Name of the ScienceLogic user who loaded the software update onto the SL1 system.
- *Import Status*. Status of the import process. Clicking on the log icon displays the log file associated with importing the selected software. Possible values are:
 - In Progress. Software is currently being imported by the SL1 system.
 - Complete. Software has been imported successfully.
 - Failed. Software import has failed due to an unexpected condition. Contact ScienceLogic Support for assistance.
 - *Missing Base*. The SL1 system cannot import this software until another software package has been imported. The dependency is for compression purposes. Check the log for a message stating which software package needs to be imported.
- **Staging Status**. Status of the staging process. Clicking on the log icon displays the log file associated with staging the selected software. Possible values are:
 - --. No staging request is active and software has not been staged on any SL1 appliances.
 - Scheduled. The SL1 system is aware of the staging request and is preparing for staging.
 - In Progress. Staging is in progress but has not completed.

- Complete. Staging has completed, and all appliances are ready to deploy the software.
- Incomplete. Staging has completed, and one or more appliances are ready to deploy the software.
- Canceled. User manually canceled the staging process.
- Outdated. The current update is not the latest or has already been installed.
- Failed. An unexpected error occurred in the staging process. Contact ScienceLogic Support.

NOTE: If you did not select **Auto Stage** during import, the **Staging Status** column will include an asterisk (*) until you manually stage the update.

- **Preupgrade Status**. You can run the pre-upgrade check after importing and staging an update but before deploying the update. The pre-upgrade check will ensure that all criteria are met before deploying.
 - If you want to run the pre-upgrade check, select the purple checkmark for the selected row.
 - The possible values in this field are *In Progress* or *Complete*.
 - Clicking on the magnifying-glass icon () in this column displays the output of the pre-upgrade check.
 - If a pre-upgrade criterion fails, the **[Deploy]** button will be disabled for the selected row.
 - If an appliance fails the pre-upgrade criteria, you can view the output from the system status script for each failed appliance. Go to the Appliance Manager page (System > Settings > Appliances), find the appliance that failed, and click on the magnifying-glass icon (a).
 - For details see the section on the Pre-Upgrade Check .
- Deployment Status. Specifies the current deployment state. Possible values are:
 - --. No deployment request is active, and software has not been deployed on any SL1 appliances.
 - Scheduled. The SL1 system is aware of the deployment request and is preparing for deployment.
 - In Progress. Deployment is in progress but has not completed.
 - Complete. Deployment has completed, and all appliances are updated.
 - Incomplete. Deployment has completed, and one or more appliances are updated.
 - Canceled. User manually canceled the deployment.
 - Outdated. The current update is not the latest or has already been installed.
 - Failed. An unexpected error occurred in the deployment process. Contact ScienceLogic Support.
- Deployment Status Date. Specifies the date and time the software update was last deployed.

Reference: Viewing the Log Files for Updates

From the **System Updates** page, you can view a log file that displays the history of the software update. To view this log file:

- 1. Go to the **System Updates** page (System > Tools > Updates).
- 2. In the **System Updates** page, find the software update for which you want to view the log files. Go to its *Import Status* column, **Staging Status** column, or **Deployment Status** column and click the log icon (a).
- 3. The appropriate log page appears. In this modal page, each log entry displays:
 - Information about the status of the software update and its related actions.
 - For each action, the name and IP address of the appliance where the action occurred
 - The date and time each action occurred.

Workflow

The following sections describe the steps to plan and deploy an SL1 update.

If would like assistance planning an upgrade path that minimizes downtime, please contact your Customer Success Manager.

The workflow for upgrading SL1 is:

- 1. Planning
- 2. Scheduling maintenance windows
- 3. (If necessary) updating SL1 Appliances to a versions of SL1 that uses RedHat Linux (SL1 8.1.1 and later).
- 4. Pre-upgrade best practices for SL1
- 5. Backing Up Custom Settings in the NextUI
- 6. Backing Up SSL Certificates
- 7. Setting the Timeout for PhoneHome Watchdog
- 8. Adjusting Timeout for slow connections
- 9. Running the system status script on the Database Server or All-In-One before upgrading.
- (If necessary) Upgrading the SL1 Distributed Architecture on SL1 Versions 8.5.0 and Earlier using the System Update tool (System > Tools > Updates).
- Upgrading the SL1 Distributed Architecture on SL1 Versions 8.6.0 and Later using the System Update tool (System > Tools > Updates).
- 12. Removing SL1 Appliances from Maintenance Mode

- 13. (As needed) Manual updates for systems upgrading from 8.4.x and earlier
- 14. (As needed) Upgrading MariaDB

CAUTION: Refer to the release notes for your current release to determine if you must upgrade MariaDB.

15. (As needed) Rebooting SL1 Appliances

CAUTION: Refer to the release notes for your current release to determine if you must reboot all SL1 appliances after upgrading.

- 16. Restoring Custom Settings in the NextUI
- 17. Restoring SSL Certificates
- 18. Resetting the Timeout for PhoneHome Watchdog
- 19. Updating PowerPacks
- 20. (One-time) Configure Subscription Billing. For details, see the Subscription Billing manual.

Planning

Before upgrading SL1, perform the following steps that are specific to your organization:

- 1. Read the release notes to determine:
 - What is fixed?
 - What is new?
 - What has changed?
 - What has been deprecated?
- 2. Read the Known Issues for the release at https://support.sciencelogic.com/s/topic/0TO0z00000E6w7GAC
- Identify all integrations and third-party applications that access the SL1 database or manipulate data on SL1. Determine how to disable these integrations during the deployment and re-enable after deployment.
- 4. Identify activities and customers that will be affected by maintenance windows and schedule and inform appropriately.
- 5. Identify custom work (PowerPacks, Run Book Automations, Event policies, Dashboard widgets) and ensure that it is backed up so you can restore it if necessary.

NOTE: Ensure that the each SL1 appliance has 3GB of free space in the /var partition to allow you stage the upgrade. Ensure that each SL1 appliance has 1GB of free space in / (the root partition) to allow you to deploy the upgrade.

Scheduling Maintenance Windows

Upgrading SL1 includes a minimum of two and possibly four maintenance windows:

- Import and stage update and run the pre-upgrade script. These steps can take place prior to the day of upgrade and do not affect SL1 functionality. ScienceLogic suggest you perform these steps at least three days before the planned upgrade and ideally a week before the planned upgrade.
- **Deploy update**. On the day of the upgrade, put all SL1 appliances in maintenance mode. The SL1 system will not be available during this procedure. Update he SL1 Distributed systems.

CAUTION: If you are upgrading from a version of SL1 prior to 8.6.0, you will have to perform the first two bullets twice, once to upgrade to 8.6.0 and then again to upgrade to the latest update. You will need an additional maintenance window for the extra deploy step.

• Update MariaDB (if required). The SL1 system will not be available during this procedure.

CAUTION: Refer to the release notes for your current release to determine if you must upgrade MariaDB.

• Reboot Appliances (if required). Individual SL1 appliances will not be available during these procedures.

CAUTION: Refer to the release notes for your current release to determine if you must reboot all SL1 appliances after upgrading.

• Identify activities and customers that will be affected by maintenance windows and schedule and inform appropriately.

Updating SL1 Appliances to Oracle Linux

SL1 Release Prior to 8.1.1

SL1 8.1.1 included a complete update of the operating system for each SL1 appliance, from CentOS 5.11 to Oracle Linux. Major operating system components, including the database, web server, and High Availability/Disaster Recovery packages have been updated or replaced by new industry-standard packages.

When upgrading from a version prior to 8.1.1, each appliance must be migrated to 8.9.0 and the Oracle Linux 7.5 operating system.

ScienceLogic strongly suggests that you contact Customer Support or your Customer Success Manager to plan your migration from CentOS (versions of SL1 prior to 8.1.1) to the latest release.

SL1 Releases Prior to 8.10.0

Please note that SL1 8.10.0 and later versions do not support "mixed-mode", where the Database Servers and Administration Portals are running Oracle Linux (SL1 versions 8.1.1 and later) and the Data Collectors and Message Collectors are running CentOS (SL1 version prior to 8.1.1). If your system uses "mixed-mode", you must reinstall the Data Collectors and Message Collectors with an SL1 ISO that matches the SL1 version running on the Database Servers or Administration Portals before upgrading to the current versions of SL1.

ScienceLogic strongly suggests that you contact Customer Support or your Customer Success Manager to plan your migration from mixed mode to SL1 versions 8.10.0 and later

Pre-Upgrade Best Practices

Before you upgrade, check the following:

- Before you install an SL1 upgrade, ScienceLogic recommends reviewing the hardware specifications of all the appliances in your system to ensure they meet the requirements for the current usage of your system. For more details about sizing and capacity for your specific environment, contact your Customer Success Manager and see https://support.sciencelogic.com/s/system-requirements.
- Before installing an SL1 upgrade, ScienceLogic recommends that you verify that recent backups are available for your system.
- Ensure that each SL1 appliance has a valid license.
- To apply updates to an existing Data Collector, that Data Collector must be a member of a Collector Group. In some SL1 systems, users might have to create a Collector Group for a single Data Collector.
- Ensure that each Data Collector is "available" to the Database Server. To check, see the **Collector Status** page (System > Monitor > Collector Status).

Backing Up Settings in the NextUI

To save any custom settings in the NextUI:

- 1. Login to the console of the Database Server or SSH to the Database Server.
- 2. Open a shell session.
- 3. Enter the following at the shell prompt:

cp /opt/em7/nextui/nextui.env /opt/em7/nextui/nextui.env.backup

Backing Up SSL Certificates

To backup your SSL Certificates:

- 1. Log in to the console of the Database Server or SSH to the Database Server.
- 2. Open a shell session.
- 3. Enter the following at the shell prompt:

```
cp /etc/nginx/silossl.key /etc/nginx/silossl.key.bak
```

- cp /etc/nginx/silossl.pem /etc/nginx/silossl.pem.bak
- 4. Repeat these steps on each Database Server in your SL1 system.

Setting the Timeout for PhoneHome Watchdog

You can manually adjust the settings for the PhoneHome Watchdog server, to reduce CPU consumption during the upgrade process. To do this:

- 1. Log in to the console of the Data Collector as the root user or open an SSH session on the Data Collector.
- 2. At the command line, type the following:

```
phonehome watchdog view
```

3. You should see something like the following:

```
Current settings:
autosync: yes
interval: 20
state: enabled
autoreconnect: yes
timeoutcount: 2
check: default
```

- 4. Note the settings for interval and timeoutcount, so you can restore them after the upgrade.
- 5. To change the settings for SL1 upgrade, type the following at the command line:

```
sudo phonehome watchdog set interval=120;
```

sudo phonehome watchdog set timeoutcount=2;

```
systemctl stop em7_ph_watchdog;
```

- systemctl start em7_ph_watchdog;
- 6. Repeat the steps in this section on each Data Collector.
- 7. Repeat the steps in this section on each Message Collector.
- 8. Repeat the steps in this section on each Database Server.

Adjusting the Timeout for Staging and Deploying

If you have slow connections between SL1 appliances, you can adjust the timeout values for staging and deploying upgrades.

SL1 8.14 and Later Releases

To do this on an SL1 system running 8.14.0 or later:

- 1. Log in to the console of the Database Server or SSH to the Database Server.
- 2. Open a shell session.
- 3. Enter the following at the shell prompt:

sudo pcli set-patcher-param staging_wait_time <timeout_in_seconds>

- where <timeout_in_seconds> is the timeout value, in seconds, for staging for each SL1 appliance. The default value is 1800 seconds (30 minutes). You can increase this value for slow connections.
- 4. Enter the following at the shell prompt:

sudo pcli set-patcher-param deploy_wait_time <timeout_in_seconds>

• where <timeout_in_seconds> is the timeout value, in seconds, for deploying to each SL1 appliance. The default value is 3600 seconds (1 hour). You can increase this value for slow connections.

SL1 8.12 and Prior Releases

To do this on SL1 systems running versions prior to 8.14.0:

- 1. Log in to the console of the Database Server or SSH to the Database Server.
- 2. Open a shell session.
- 3. Enter the following at the shell prompt:

```
silo_mysql -e "UPDATE master.system_settings_patcher SET value=<timeout_in_
seconds> WHERE param='staging_wait_time'"
```

- where <timeout_in_seconds> is the timeout value, in seconds, for staging for each SL1 appliance. The default value is 1800 seconds (30 minutes). You can increase this value for slow connections.
- 4. Enter the following at the shell prompt:

```
silo_mysql -e "UPDATE master.system_settings_patcher SET value=<timeout_in_
seconds> WHERE param='deploy_wait_time'"
```

• <timeout_in_seconds > is the timeout value, in seconds, for deploying to each SL1 appliance. The default value is 3600 seconds (1 hour). You can increase this value for slow connections.

Running the System Status Script Before Upgrading

SL1 includes a script, system_status.sh, that provides diagnostic data for each appliance in your SL1 system.

NOTE: On SL1 Systems prior to 10.2.0, after running the system status script, you must ensure that the file /var/lob/em7/silo.log has the owner and group "s-em7-core".

Running the System Status Script on SL1 8.14.0 and Later Releases

If you are running SL1 version SL 8.14.0 or later, SL1 automatically runs the system status script every 15 minutes on each appliance in your SL1 system.

For SL1 systems running 8.140 or later, ScienceLogic recommends that you view the output from the system status script before upgrading:

- 1. In SL1, go to the **Appliance Manager** page (System > Settings > Appliances).
- 2. Locate the SL1 appliance that you want to view diagnostic information about.
- 3. Click on its magnifying-glass icon () to view the output of the system status script for that appliance.
- 4. If the output includes errors and you need help fixing them, contact ScienceLogic Customer Support to fix the errors before upgrading.
- 5. Repeat for each appliance in your SL1 system.
- 6. To get the very latest status before upgrading, *manually run the system status script* on each Database Server or All-In-One Appliance.

Running the System Status Script on SL1 8.12.x Releases

If you are running an SL1 version in the 8.12.x line of releases, SL1 includes the system status script already installed in the /opt/em7/bin directory. However, there is no user interface option in the **Appliance Manager** page (System > Settings > Appliances) until SL1 version 8.14.0.

Before upgrading from any 8.12.x or later version, ScienceLogic recommends that you manually run the system status script on each Database Server or All-In-One Appliance, to get the latest results.

To run the system status script on each SL1 appliance:

- 1. Either go to the console of the SL1 appliance or use SSH to access the SL1 appliance.
- 2. Open a shell session on the server.
- 3. Navigate to /opt/em7/bin:

cd /opt/em7/bin

4. At the shell prompt, enter the following:

sudo system_status.sh > /tmp/status

- 5. Enter the root password.
- 6. Navigate to /tmp/status to view the results.

cd /tmp cat status

- 7. If the output includes errors and you need help fixing them, contact ScienceLogic Customer Support to fix the errors before upgrading.
- 8. After fixing any errors and running the system_status.sh script again, check the ownership of /var/log/em7/silo.log:

```
ls -l /var/log/em7/silo.log
```

9. Ensure that the file has owner "s-em7-core" and "group s-em7-core":

```
chown s-em7-core:s-em7-core /var/log/em7/silo.log
```

NOTE: : SL1 Systems 10.2.0 and later will automatically reset the ownership of /var/log/em7/silo.log if necessary before upgrade.

10. Repeat these steps on each SL1 appliance in your SL1 system.

Running the System Status Script on SL1 8.10 and Prior Releases

If you are running an SL1 release prior to 8.12.0, you can download and run the system status script before upgrading. You should run this script on each SL1 appliance.

To download and run the system_status.sh script:

- Go to <u>https://docs.sciencelogic.com/system_status/system_status.sh</u> to download the system status script. Save the file to a local computer.
- Using WinSCP or another file-transfer utility, copy the file system_status.sh to a directory on the SL1 appliance.
- 3. Go to the console of the SL1 appliance or use SSH to access the SL1 appliance.
- 4. Navigate to the directory that includes the system status.sh file.
- 5. Enter the following to make the script executable:

chmod +x system status.sh.

6. To execute the script with the default options:

```
sudo ./system_status.sh
```

7. You can use the help option to view all the options:

./system_status.sh --help You should see something like this:

- -l [--logcollect] = gather logs into a single file
- -c [--crmreport] = create CRM report for HA/DR issues
- -f [--fix] = fix mode (fix anything marked [fixable])

```
-m [--mysql-tuning] = a MySQL configuration tuning script (formerly known as
"Gold Changes")
-n [--no-upgrade] = Do not upgrade or prompt to upgrade, even if an upgrade is
available
-o [--outage] = outage investigator
-p [--ptstalk] = run pt-stalk
-h [--help] = help message (what you're reading now)
-u [--autoupdate] = if an update is available, upgrade without prompting
-v [--version] = show version number
Here is a sample output of the script run without options:
```

```
System Status v3.11
Tue Jul 17 15:39:43 UTC 2019
Using latest revision
Results marked with [KB ####] refer to a KB article number you can reference at
https://support.sciencelogic.com/s/article/####
Database Specs:
SL1 Architecture: AIO
SL1 Specs:
SL1 Release: EM7 8.10.0 [build 1023]
ISO Release: 8.1.1
Managed Devices: 2 (2 active)
Managed Components: 0 (0 active)
Managed Interfaces: 14 (3 active)
OS Specs:
OS Release: Oracle Linux Server release 7.5
Hostname: ha2
Active IPs:
- 192.168.##.##/22
Licensed IP: 192.168.##.##
Appliance Model: AIO
Appliance Type: Virtual - VMware Virtual Platform
MySQL Version: 10.1.36
Number of Cores: 2
Total RAM: 6GB
Disk Size: 60GB
- Disk size below minimum for 2 active devices, should be a minimum of 80GB
/data.local/db size: 27G
5 Minute Load Avg: 2.74
Memory Utilization: 65%
```

```
Other Information:
```

Disabled Processes [KB 1277]:

- Enterprise Database: Asset Record Maintenance
- Enterprise Database: Subscription Usage Crunch

Checking for errors...

- Devlogging ON [KB 1049]
- More than three kernels installed. [KB 1294]

```
- DRBD active, but DRBD SNMP extensions for monitoring not found [KB 1278] [fixable]
```

All Done!

- 8. If the output includes errors and you need help fixing them, contact ScienceLogic Customer Support to fix the errors before upgrading.
- 9. After fixing any errors and running the system_status.sh script again, check the ownership of /var/log/em7/silo.log:

```
ls -l /var/log/em7/silo.log
```

10. Ensure that the file has owner "s-em7-core" and "group s-em7-core":

```
chown s-em7-core:s-em7-core /var/log/em7/silo.log
```

NOTE: : SL1 Systems 10.2.0 and later will automatically reset the ownership of /var/log/em7/silo.log if necessary before upgrade.

11. Repeat these steps on each SL1 appliance in your SL1 system.

For more information about System Status Script, watch the video at https://www.youtube.com/watch?v=n32v8hYIIZ4.

Upgrading the SL1 Distributed Architecture on SL1 Versions 8.5.0 and Earlier

To use the steps in this section, you must be running SL1 version 8.1.1 or later. If you are running a previous version, ScienceLogic strongly suggests that you contact Customer Support or your Customer Success Manager to plan your migration from CentOS (versions of SL1 prior to 8.1.1) to the latest release.

NOTE: The upgrade process might include importing multiple upgrade files. You must wait until an update file has imported successfully (i.e. the Import Status column displays Complete) before importing the next update file.

Any distributed system running 8.6.0 or later can be upgraded by importing, staging, and deploying a single update file. After you upgrade to 8.6.0, you can use the delta-less upgrade feature.

NOTE: The 8.4.2 release changed the firewall on all appliances from iptables to firewalld. If you have added a custom firewall rule, such as a non-standard port for Phone Home Collectors, these rules must be migrated before upgrading to an 8.4.2 or later release. Please contact ScienceLogic Support for more information.

Upgrading the Distributed Stack for SL1 includes the following steps:

- Disabling automatic staging
- Downloading the Updates
- Importing the Updates
- Staging the Updates
- Running the Pre-Upgrade Check
- Putting All SL1 Appliances in Maintenance Mode
- Deploying the Update
- Putting All SL1 Appliances Out of Maintenance Mode

CAUTION: SL1 versions 8.10.0 and later do not support Data Collectors and Message Collectors running the CentOS operating system. If your system includes Data Collectors and Message Collectors running the CentOS operating system, contact your Customer Success Manager for details on upgrading Data Collectors and Message Collectors to Oracle Linux before upgrading.

Disabling Automatic Staging

For systems running an SL1 version prior to 8.12.0, go to the System Updates page and disable automatic staging (System > Tools > Updates > Actions > Disable automatic staging).

If you have previously used manual staging, perform these additional steps:

- 1. Select all updates in the EM7 Releases pane and select all updates in the ScienceLogic OS pane.
- 2. In the Select Action menu, select Unstage Update (remove staging policy override). Click Go.
- 3. For software that was previously staged with automatic staging, Unstage Update (remove staging policy override) does not affect staging.

Downloading the Updates

NOTE: These steps do not affect the performance of SL1. ScienceLogic recommends that you perform these steps at least 3 days before upgrading.

To download updates for previous SL1 software versions that have reached their End of Life date and are no longer supported by ScienceLogic, contact ScienceLogic Support or a designated Customer Success Manager to get the update files.

Store the update files in a location that you can use to upload files to the SL1 system

Importing the Updates

NOTE: These steps do not affect the performance of SL1. ScienceLogic recommends that you perform these steps at least 3 days before upgrading.

If your system is not currently running a recent release, the upgrade process includes importing multiple update files. You must wait until an update file has imported successfully (i.e. the *Import Status* column displays *Complete* in both the **EM7 Releases** pane and the **ScienceLogic OS** pane) before importing the next update file.

Although you must import all the update files between your current release and SL1 8.6.0, you must stage only the final update.

To import an update:

1. Go to the System Updates page (System > Tools > Updates

System Updates				In	stallation mode: [Upgra	de only]	 Actions Imp 	ort Reset	Guide
EM7 Releases Versions Found [2] Release Version - 1. EM7 8.2.0 jenkins_EM7_G3_8.2.0 r4269	Update Sknature ScienceLogic Internal QA Build	Imported On 2016-12-04 16:39:35	Imported By em7admin	Import Status	Staging Status N/A	Deployment	Deployment Status New/Unscheduled	Deployment Status Date	
2. EM7 8.2.0	Base installation	2016-11-14 16:43:54	em7admin	Complete	N/A	Full (1/1)	New/Unscheduled	-	100
ScienceLogic OS Updates Found [2] Belease Version -	Update Signature	Imported On	Imported By	Import Status	Staging Status	Deployment	Deployment Status	Deployment Status Date	
1. Platform 2016-12-01	ScienceLogic Internal QA Build	2016-12-04 16:39:35		🛃 Missing Key	N/A	-	New/Unscheduled	-	
2. Platform 2016-11-11	Base installation	2016-11-14 16:43:54	em7admin	Complete	N/A	Outdated	New/Unscheduled		
		2010/11/14 10:40:34		Compare	104	Condito	Henron June dured		

- 2. Select the [Import]button.
- 3. In the **Import a new update** modal page, navigate to the software file for the update and select it. Select the **[Import]** button.
- 4. The *Import Status* column displays the status of the import. Possible values are:

- Processing. Software update is currently being imported by the SL1 system.
- Complete. Software update has been imported successfully.
- Failed. Import has failed due to an unexpected condition. Contact ScienceLogic Support for assistance.
- *Missing Base*. The SL1 system cannot import this software update until another software package has been imported. Check the log for a message stating which software package needs to be imported.
- 5. The update file will load an update in both the **EM7 Releases** pane and the **ScienceLogic OS** pane. You must wait until the update file has imported successfully (i.e. the *Import Status* column displays *Complete*) before importing the next update file.
- 6. For more detailed information about importing, in the *Import Status* column, select the log icon (🗟).
- 7. Repeat these steps for each update file between your current version and 8.6.0

Staging the Update

NOTE: These steps do not affect the performance of SL1. ScienceLogic recommends that you perform these steps at least 3 days before upgrading.

When you manually stage a software update, SL1 checks the status of the software on each SL1 appliance. The platform then stages the software update only to those SL1 appliances that have not yet been staged for this software update.

You must stage only the latest update. For example, if you downloaded updates for 8.4.0, 8.5.0, and 8.6.0, you must stage only the update for 8.6.0.

To manually stage a software update:

1. Go to the **System Updates** page (System > Tools > Updates

System Updates					tallation mode: [Upgra	ide only]	 Actions Imp 	sort Reset	Guide
M7 Releases Versions Found [2]									
Release Version -	Update Signature	Imported On	Imported By	Import Status	Staging Status	Deployment	Deployment Status	Deployment Status Date	te
1. EM7 8.2.0.jenkins_EM7_G3_8.2.0 r4269	ScienceLogic Internal QA Build	2016-12-04 16:39:35		🔄 Missing Key	N/A	-	New/Unscheduled	-	1
2. EM7 8.2.0	Base installation	2016-11-14 16:43:54	em7admin	Complete	N/A	Full (1/1)	New/Unscheduled		
cienceLogic OS Updates Found [2]	Hodate Simahrae	Imported On	Innovelari Br	Invest Status	Staning Status	Derloyment	Dankyment Statue	Dankymant Status Date	
cienceLogic OS Updates Found [2] Release Version • 1. Platform 2016-12-01	Uotate Signature ScienceLogic Internal CA Build	Imported On 2016-12-04 16:39:35	Imported By em7admin	Import Status	Staging Status N/A	Deployment	Deployment Status New/Unscheduled	Deployment Status Date	le / ==
Release Version			em7admin	🔄 Missing Key					le /
Release Version • Platform 2016-12-01	ScienceLogic Internal QA Build	2016-12-04 16:39:35	em7admin		N/A	-	New/Unscheduled	-	le / 1
Release Version • Platform 2016-12-01	ScienceLogic Internal QA Build	2016-12-04 16:39:35	em7admin	🔄 Missing Key	N/A	-	New/Unscheduled	-	r 7
Release Version - Platform 2016-12-01	ScienceLogic Internal QA Build	2016-12-04 16:39:35	em7admin	🔄 Missing Key	N/A	-	New/Unscheduled	-	1
Release Version - Platform 2016-12-01	ScienceLogic Internal QA Build	2016-12-04 16:39:35	em7admin	🔄 Missing Key	N/A	-	New/Unscheduled	-	<u>le</u> 7 1
Release Version - Platform 2016-12-01	ScienceLogic Internal QA Build	2016-12-04 16:39:35	em7admin	🔄 Missing Key	N/A	-	New/Unscheduled	-	
Release Version - Platform 2016-12-01	ScienceLogic Internal QA Build	2016-12-04 16:39:35	em7admin	🔄 Missing Key	N/A	-	New/Unscheduled	-	le //
Release Version - Platform 2016-12-01	ScienceLogic Internal QA Build	2016-12-04 16:39:35	em7admin	🔄 Missing Key	N/A	-	New/Unscheduled	-	1
Release Version • Platform 2016-12-01	ScienceLogic Internal QA Build	2016-12-04 16:39:35	em7admin	🔄 Missing Key	N/A	-	New/Unscheduled	-	
Release Version • Platform 2016-12-01	ScienceLogic Internal QA Build	2016-12-04 16:39:35	em7admin	🔄 Missing Key	N/A	-	New/Unscheduled	-	
Release Version • Platform 2016-12-01	ScienceLogic Internal QA Build	2016-12-04 16:39:35	em7admin	🔄 Missing Key	N/A	-	New/Unscheduled	-	
Release Version - 1. Platform 2016-12-01	ScienceLogic Internal QA Build	2016-12-04 16:39:35	em7admin	🔄 Missing Key	N/A	-	New/Unscheduled	-	
Release Version • Platform 2016-12-01	ScienceLogic Internal QA Build	2016-12-04 16:39:35	em7admin	🔄 Missing Key	N/A	-	New/Unscheduled	-	

- 2. In the EM7 Releases pane, find the software update for EM7 8.6.0. Select its checkbox.
- 3. In the ScienceLogic OS pane, find the latest OS update. Select its checkbox.
- 4. In the **Select Actions** field in the lower right, select Stage Update (prepare for installation). Click the **[Go]** button.
- 5. The Staging Status column displays the status of the staging process. Possible values are:
 - -- Software is not currently being staged, but one or more SL1 appliances can install it.
 - N/A. This update cannot be installed in the current Installation mode.
 - Obsolete. The current update is not the latest or has already been installed. If the Installation Mode is set to Upgrade Only, you cannot install an obsolete update.
 - Failed. An unexpected error occurred in the staging process. Contact ScienceLogic Support.
 - In progress. Staging is in progress but has not completed.
 - Complete. Staging has completed and all appliances are ready to deploy the software.
- 6. For more detailed information about staging, in the **Staging Status** column, select the log icon (
- 7. SL1 will copy the software update to each SL1 appliance that has not yet been staged.

Running the Pre-Upgrade Check

NOTE: These steps do not affect the performance of SL1. ScienceLogic recommends that you perform these steps at least 3 days before upgrading.

The pre-upgrade check examines the following:

All SL1 Appliances:

The pre-upgrade-checkv2.sh script checks the following on all SL1 appliances:

- Hostname and hosts file
- Uptime and average CPU load
- SL1 version
- OS versions
- MariaDB version
- Current disk utilization
- Is post update running?
- Checks yum config for configured proxy
- Check for packages installed outside of official SL1 update
- Filters out unsupported appliance types
- Gathers system status

Active Database Server:

The pre-upgrade-checkv2.sh script checks the following on all active Database Servers:

- Identifies Data Collectors that are not members of a Collector Group
- Lists all active SL1 appliances
- Lists all SL1 appliances that are disabled or ineligible for upgrade
- Checks for active staging schedules
- Check for active deployment schedules
- Are backups configured and successful?
- Checks pruner status
- Checks SIGTERMs for past 24 hours
- Compares number of tables on disk to the table definition cache
- Lists the largest 10 databases by size
- Searches for long running queries
- Shows status of used mysql connections and variables
- Lists mysql config files
- Gathers pt-diststats at 15 second interval three times
- Checks for system status wrapper bug
- Ensure that silo.log ownership is correct

All Database Servers:

The pre-upgrade-checkv2.sh script checks the following on all Database Servers:

- Checks for a minimum of 300 MB disk space on /var partition
- Checks HA/DR status
- Checks for CRM bans
- Checks for old CRM templates in HA/DR setups
- Fixes the missing SysVInit script for the MariaDB service
- Are custom SSL certs named silo default?
- Gathers output of top
- Is this SL1 Appliance memory swapping?

Administration Portal:

The pre-upgrade-checkv2.sh script checks the following on all Administration Portals:

- Checks web processes
- Are custom SSL certs named silo default?

Data Collectors and Message Collectors:

The pre-upgrade-checkv2.sh script checks the following on all active Data Collectors and Message Collectors

• Checks running Python processes

Downloading and Running the Pre-Upgrade Check

To download and run the pre-upgrade check:

- 1. Contact ScienceLogic Customer Support to get the file. Save the file to a local computer.
- 2. Use WinSCP or another file-transfer utility to copy the file pre-upgrade-check-v2.sh to the directory /home/em7admin of each SL1 appliance.
- 3. Go to the console of each SL1 appliance or open a SSH session to each SL1 appliance.
- 4. Navigate to the directory /home/em7admin.
- 5. At the shell prompt, enter the following to make the script executable:

chmod +x pre-upgrade-check-v2.sh

6. To execute the script with the default options:

```
sudo ./pre-upgrade-check-v2.sh -<appliance_type> > /tmp/preupgrade-check-v2-
`hostname -s`.`date "+%Y%m%d"` 2>&1
where:
```

appliance_type is one of the following:

- -d = Database Appliance
- -o = All-In-One
- -c = Data Collector
- -m = Message Collector
- -a = Admin Portal
- 7. To view the output from the script, view the file /tmp/pre-upgrade-check-v2-<current hostname>.<today's date>
- 8. If the output includes errors and you need help fixing them, contact ScienceLogic Customer Support to fix the errors before upgrading.
- 9. Perform these steps on each SL1 appliance.

Putting All SL1 Appliances in Maintenance Mode

NOTE: ScienceLogic recommends that you perform these steps during a maintenance window.

Immediately before deploying a software update, ScienceLogic recommends that you put all SL1 appliances in maintenance mode. This will prevent spurious error messages and events during the deployment.

To enable user maintenance mode for all the SL1 appliances in your SL1 system:

- 1. Go to the Appliance Manager page (System > Settings > Appliances). Note the list of SL1 appliances in your system.
- 2. Go to the **Device Manager** page (Registry > Devices > Device Manager):

Data Data <th< th=""><th>Manager Devices Found [176]</th><th></th><th></th><th></th><th></th><th></th><th></th><th></th><th></th><th>Actions</th><th>Report</th><th>Reset</th><th>Guide</th></th<>	Manager Devices Found [176]									Actions	Report	Reset	Guide
All Montania No. Control	Device Name *	IP Address		Device Class Sub-class	DID	0	canization	Current State				SNMP Version	
Pin 102 00 1040 Pin 102 00 103 Network Roder Cos O System (250) Pin 102 00 103 Active Cos O SIMPLA - Esa V2 Pin 102 00 103 Pin 102 00 103 Pin 200 003 Microson (2004) Pin 102 00 103 Active Cos O SIMPLA - Esa V2 Pin 102 00 103 Pin 102 00 103 Pin 200 003 Microson (2004) Pin 102 00 103 Active Cos O SIMPLA - Esa V2 Pin 102 00 103 Pin 102 00 103 Pin 200 003 Microson (2004) Pin 102 00 103 Active Cos O SIMPLA - Esa V2 Pin 102 00 103 Pin 102 00 103 Pin 200 003 Microson (2004) Pin 102 001 003 Active Cos O SIMPLA - Esa V2 Pin 102 001 003 Active Cos O SIMPLA - Esa V2 Pin 102 001 003 Active Cos O SIMPLA - Esa V2 Pin 102 001 003 Active Cos O SIMPLA - Esa V2 Pin 102 001 003 Active Cos O SIMPLA - Esa V2 Pin 102 001 003 Active Cos O SIMPLA - Esa V2 Pin 102 001 003 Active Cos O SIMPLA - Esa V2 Pin 102 001 003 Active Cos O SIMPLA - Esa V2 Pin 102 003 Active Cos O SIMPLA - Esa V2 Pin 102 003 003 Pin 102 003 003 003 P								_]
Print 2001 Print 2001 Active Dec 30 HMAP, Ess V2 Print 2001 Print 2001 System Attestry UD14 Active Dec 30 HMAP, Ess V2 Print 2001 Print 2001 System Attestry UD14 Active Dec 30 HMAP, Ess V2 Print 2001 Print 2001 System Attestry UD14 Active Dec 30 HMAP, Ess V2 Print 2001 2000 H14 102.00 H14 Network Switche 2005 System (Edaty HS-COOC-CarD) HS System Teashy UD14 Active Dec 30 HMAP, Ess V2 Print 2001 Active Dec 30 HMAP, Ess V2 <td>10-Forward</td> <td>910.20.0.195</td> <td>Servers</td> <td>NET-SNMP FreeBSD</td> <td>54</td> <td>System</td> <td>A</td> <td>lealthy</td> <td>CUG1</td> <td>Active</td> <td>Cisco SNMPv2 - E</td> <td>xa V2</td> <td></td>	10-Forward	9 10.20.0.195	Servers	NET-SNMP FreeBSD	54	System	A	lealthy	CUG1	Active	Cisco SNMPv2 - E	xa V2	
Pin 12 00 13 Unacoun Generic [SNIP 107 System Allestry Cuo1 Active Cace 0SNIP2-15:a V Pin 200 010 00 141 102.00.114 Network Switche Cace System (Cataly VIS-C600-CatOS 118 System Meatry Cu01 Active Cace 0SNIP2-15:a V Pin 200 02.00.1141 102.00.114 Network Switche Cace System (Cataly VIS-C600-CatOS 118 System Meatry Cu01 Active Cace 0SNIP2-15:a V	P 10.20.0.108	10.20.0.108	Network.Router	Cisco Systems 2501	72	System	A1	lealthy	CUG1	Active	Cisco SNMPv2 - E	xa V2	m13 %
Part 10:20 Part 20:20:135 Pertons System (Latary 13:500-30.) System Part 10:01 Active Cos SIMP.2: Eas V2 20:01:41 10:20:01:41 Network Switcher Cos System (Latary 13:500-20.01) 18 System Peak Peak <td>A 10.20.0.123</td> <td>10.20.0.123</td> <td>Network.Router</td> <td>Cisco Systems 7206VXR</td> <td>112</td> <td>System</td> <td>11</td> <td>Minor</td> <td>CUG1</td> <td>Active</td> <td>Cisco SNMPv2 - E</td> <td>xa V2</td> <td>(m) 12 (b)</td>	A 10.20.0.123	10.20.0.123	Network.Router	Cisco Systems 7206VXR	112	System	11	Minor	CUG1	Active	Cisco SNMPv2 - E	xa V2	(m) 12 (b)
22.0.141 12.0.20.141 Network.Switcher Goo System (Latayu VS-C000 CullOS 110 2001 Active Cico SIMP/2 - Ea V2 20.0.144 12.0.0.147 Network.Switcher Gaos System (Latayu VS-C000 CullOS 110 5 System Nethy CU01 Active Cico SIMP/2 - Ea V2 20.0.147 12.0.0.147 Network.Evocdba Interpole Network.Switcher Gaos SIMP/2 - Ea V2 Cico SIMP/2 - Ea V2 Cico SIMP/2 - Ea V2 20.0.147 12.0.0.0.147 Network.Evocdba Interpole Network.Switcher Gaos SIMP/2 - Ea V2 Cico SIMP/2 - Ea V2 20.0.146 12.0.0.0.146 Network.Evocdba Interpole Network.Switcher Gaos SIMP/2 - Ea V2 Cico SIMP/2 - Ea V2 20.0.146 12.0.0.0.140 Network.Evocdba Interpole Network.Switcher Gaos SIMP/2 - Ea V2 Cico SIMP/2 - Ea V2 20.0.147 10.0.0.0.140 Network.Evocdba Interpole Network.Switcher Gaos SIMP/2 - Ea V2 Cico SIMP/2 - Ea V2 20.0.150 10.0.0.0.170 Unknown Generic SIMP/2 System Network. Cico SIMP/2 - Ea V2 20.0.151 10.0.0.0.170 Unknown Generic SIMP/2 System Network. Cico SIMP/2 - Ea V2 20.0.151 10.0.0.0.170 Unknown Generic SIMP/2 System Network. Cico SIMP/2 - Ea V2	A 10.20.0.13	10.20.0.13	Unknown	Generic SNMP	107	System	At	lealthy	CUG1	Active	Cisco SNMPv2 - E	xa V2	(m) 10 (b)
2500 141 12.0.0.141 Network.Switcher Goo System (Lataby WS-C000 CullOS 110 2 System Nethy CU01 Active Cico SIMPA/2 - Da V2 2500 144 152.0.0.147 152.0.0.147 152.0.0.147 152.0.0.147 Cico SIMPA/2 - Da V2 Network. Evadoration (Simpa/2 Simpa/2 Si	And 10 20.0.135	10.20.0.135	Network Switche	Cisco Systems Catalyst 3508G-XL	131	System	A	lealthy	CUG1	Active	Cisco SNMPv2 - E	xa V2	m108
200 147 10 20 147 Network Broadbal Helpagi Network Broadbal		10.20.0.141			118	System	Hea	ithy	CUG1	Active	Cisco SNMPv2 - E	xa V2	
2020 144 1220 044 Network Erosaba Hepsip (1200, R40x, R7x0, R8 (8) System Hampy CU01 Ache Dice 03 MHP2-12: bit V2 2020 149 1220.014 Network Erosaba Hepsip (1202-7) 122 System Heshy CU01 Ache Dice 03 MHP2-12: bit V2 2020 151 1220.0150 Unincown Generic (SMP 144 System Heshy CU01 Ache Dice 03 MHP2-12: bit V2 2020 151 1220.0150 Unincown Generic (SMP 144 System Healty CU01 Ache Dice 03 MHP2-12: bit V2 2020 157 1220.0170 Unincown Generic (SMP 44 System Healty CU01 Ache Dice 05 MHP2-12: bit V2 2020 157 1220.0170 Unincown Generic (SMP 44 System Liber Dice 05 MHP2-12: bit V2 20 2020 157 Unincown Generic (SMP 58 System Liber Dice 05 MHP2-12: bit V2 20 2020 157 Unincown Generic (SMP 58 System Liber Dice 05 MHP2-12: bit V2 20 2020 150 Unincown Generic (SM	0.20.0.146	10.20.0.146	Network Broadba	n Netopia Netopia 3346 v8.2r1	2	System	Hea	ithy	CUG1	Active	Cisco SNMPv2 - E	xa V2	
200144 1220.144 Network Endada Helpa (R300,R46x, R2x0,R2 80 System Helpy CU01 Ache Cao SHM2-2-bit V2 200149 1220.149 Network Endada Helpa (R300,R46x, R2x0,R2 122 System Helpy CU01 Ache Cao SHM2-2-bit V2 200151 1220.0150 Unincown Rentro (SMP System Helpy CU01 Ache Cao SHM2-2-bit V2 200153 1220.0157 Unincown Generic (SMP H55 System Helpy CU01 Ache Cao SHM2-2-bit V2 200153 1220.0175 Unincown Generic (SMP 44 System Helpy CU01 Ache Cao SHM2-2-bit V2 200154 1220.0175 Unincown Generic (SMP 44 System Helpy CU01 Ache Cao SHM2-2-bit V2 200154 122.0175 Unincown Generic (SMP 44 System Helpy CU01 Ache Cao SHM2-2-bit V2 200154 122.0176 Unincown Generic (SMP 45 System Lineo CU01 Ache Cao SHM2-2-bit V2 200154	0.20.0.147	10.20.0.147	Network Broadba	r Netopia Netopia 3381 v8.0.10	175	System	Hea	thy	CUG1	Active	Cisco SNMPv2 - E	xa V2	
220 151 122 00 151 Unknown Operand SMP 141 System Healthy CU01 Active Disco SMM2-2: bit V2 200 150 122 0.010 Unknown Generic SMMP 165 System Healthy CU01 Active Disco SMM2-2: bit V2 200 150 122 0.0175 102 0.0175 Unknown Generic SMMP 44 System Healthy CU01 Active Disco SMM2-2: bit V2 200 157 102 0.0175 Unknown Generic SMMP 44 System Meanty CU01 Active Disco SMM2-2: bit V2 200 157 102 0.0175 Unknown Generic SMMP 56 System Lifter CU01 Active Disco SMM2-2: bit V2 200 151 02 0.0201 Unknown Generic SMMP 54 System Lifter CU01 Active Disco SMM2-2: bit V2 200 151 02 0.0201 Unknown Generic SMMP 54 System Healthy CU01 Active Disco SMM2-2: bit V2 20 0.52 12 0.0203 Unknown <	.20.0.148	10.20.0.148	Network Broadba	Netopia Netopia (R3100, R45xx, R7xx0, R9	163	System			CUG1	Active	Cisco SNMPv2 - E	xa V2	
220151 122.0151 Unincern Generic (SMP 141 System Heathy Cu31 Ache Cool SMPA 2- bia V2 200163 122.0151 Unincern Generic (SMP 165 System Heathy Cu31 Ache Cool SMPA 2- bia V2 200163 122.0157 122.0157 Unincern Generic (SMP 44 System Heathy Cu31 Ache Cool SMPA 2- bia V2 200175 122.0177 Unincern Generic (SMP 44 System Lifter Cu31 Ache Cool SMPA 2- bia V2 200176 122.0176 Unincern Generic (SMP 54 System Lifter Cu31 Ache Cool SMPA 2- bia V2 200176 122.0101 Unincern Generic (SMP 56 System Lifter Cu31 Ache Cool SMPA 2- bia V2 200171 122.020170 Unincern Generic (SMP 58 System Lifter Cu31 Ache Cool SMPA 2- bia V2 200173 122.02017 Unincern <t< td=""><td>0.20.0.149</td><td>10.20.0.149</td><td>Network Broadba</td><td>r Netopia I R7200-T</td><td>162</td><td>System</td><td>Hea</td><td></td><td>CUG1</td><td>Active</td><td>Cisco SNMPv2 - E</td><td>xa V2</td><td></td></t<>	0.20.0.149	10.20.0.149	Network Broadba	r Netopia I R7200-T	162	System	Hea		CUG1	Active	Cisco SNMPv2 - E	xa V2	
220.163 122.0.163 Unknown Generic [SMP 164 System Healty CU01 Active Caco SMPA 2- Lix V2 220.163 102.00.163 Unknown Generic [SMP 164 System Healty CU01 Active Caco SMPA 2- Lix V2 220.175 102.00.175 Unknown Generic [SMP 44 System Healty CU01 Active Caco SMPA 2- Lix V2 220.176 102.00.176 Unknown Generic [SMPA 54 System Lifter Cu03 Active Caco SMPA 2- Lix V2 220.176 102.00.176 Unknown Generic [SMPA 53 System Lifter Cu03 Active Caco SMPA 2- Lix V2 220.176 102.00.176 Unknown Generic [SMPA 53 System Lifter Cu03 Active Caco SMPA 2- Lix V2 220.570 102.00.270 Tapbony Outcom Theor 53 System Healty CU01 Active Caco SMPA 2- Lix V2 220.572 102.00.282 Unknown Generic [SMPA 53 System Healty CU01 Active													
220 163 10 20 0163 Unknown Generic (SMP 164 System Healty CU01 Active Disc SMMP2-Dis V2 220 175 12 20 0.75 Unknown Generic (SMP 44 System Healty CU01 Active Disc SMMP2-Dis V2 220 176 12 20 0.75 Unknown Generic (SMP 54 System LMmer CU01 Active Disc SMMP2-Dis V2 230 176 10 20 0.76 Unknown Generic (SMP 55 System LMmer CU01 Active Disc SMMP2-Dis V2 230 178 10 20 0.71 Unknown Generic (SMP 54 System LMmer CU01 Active Disc SMMP2-Dis V2 230 178 10 20 0.21 Unknown Generic (SMP 53 System Hadity CU01 Active Disc SMMP2-Dis V2 230 0.50 10 20 0.20 Binnown Generic (SMP 53 System Hadity DU01 Active Disc SMMP2-Dis V2 20 0.50 12 20 0.51 Teophyne 53													
220.0175 Unknown Generg (SMP 44 System Methy CUG1 Active Caco SMPA/2-Exa V2 220.0176 Unknown Kenic Cognotation (GEU 41 System Methy CUG1 Active Caco SMPA/2-Exa V2 220.0176 Unknown Generg (SMPA 57 System Unknown Caco SMPA/2-Exa V2 220.0191 Ulknown Generg (SMPA 57 System Methy CUG1 Active Caco SMPA/2-Exa V2 220.0191 Ulknown Generg (SMPA 58 System Methy CUG1 Active Caco SMPA/2-Exa V2 200.0201 Ulknown Generg (SMPA 58 System Methy CUG1 Active Caco SMPA/2-Exa V2 200.0202 Ulknown Generg (SMPA 138 System Methy CUG1 Active Caco SMPA/2-Exa V2 200.0202 Ulknown Generg (SMPA 178 System Methy CUG1 Active Caco SMPA/2-Exa V2 200.020 Ulknown Generg (SMPA 178 System Methy CUG1 Active Caco SMPA/2-Exa V2													
220.0176 102.00.9176 Unknown Konica Corporation (DEU 41 System UMer Clo31 Active Clo30 SUM2 - Exist V2 200.0150 102.00.910 Unknown Generic (SIMP 56 System LMiner Cl031 Active Clo30 SIMP 2- Exist V2 200.0191 102.00.910 Uffice/Printer Knick Minds (Fery X3222XM) 57 System Heathy Cl031 Active Clo30 SIMP 2- Exist V2 200.0101 01.00.02010 Unknown Generic (SIMP 2- Exist V2													
230.0190 10.20.0197 Unnown Generic (SMP 59 System Umer CU01 Active Cos SMPA/2- Cas V2 230.0191 10.20.0191 Unnown Generic (SMP 53 System TMinor Cos SMPA/2- Cas V2 230.0191 10.20.0191 Unnown Generic (SMP 53 System Heathy CU01 Active Cos SMPA/2- Cas V2 230.0201 10.20.0202 Unnown Generic (SMP 52 System Heathy CU01 Active Cos SMPA/2- Cas V2 230.0201 10.20.0202 Telephony Quintum Teor 53 System Heathy CU01 Active Cos SMPA/2- Cas V2 200.022 10.20.020 Telephony Quintum Teor 53 System Heathy CU01 Active Cos SMPA/2- Cas V2 200.023 10.20.020 Unnown Generic (SMP 13 System Heathy CU01 Active Cos SMPA/2- Cas V2 200.02 Unnown Generic (SMP 3 System Heathy CU01 Active Cas SMPA/2- Cas V2 20.02 10.20.051													
320.0191 10.20.0219 Office Printer Knock Minds (Minds													_
220 201 10 20.021 Unnown Generic (SMP 48 System Healty CU01 Active Clac SMPA 2- bia V2 220 2030 10 20.020 Telephony Outhin (Teorier SSMPA 2- bia V2 Easter SSMPA 2- bia V2 Easter SSMPA 2- bia V2 220 2030 10 20.020 Telephony Outhin (Teorier SSMPA 2- bia V2 Easter SSMPA 2- bia V2 220 2030 10 20.020 Telephony Outhin (Teorier SSMPA 2- bia V2 Easter SSMPA 2- bia V2 220 2030 10 20.022 Unnown Generic (SMPA 10 38 System Healty CU01 Active Clac SSMPA 2- bia V2 220 0.23 10 20.023 Unnown Generic (SMPA 10 17 System Healty CU01 Active Clac SSMPA 2- bia V2 220 0.34 10 20.029 Unnown Generic (SMPA 10 3 System Healty CU01 Active Clac SSMPA 2- bia V2 20 0.51 10 20.041 Unnown Generic (SMPA 10 3 System Healty CU01 Active Clac SSMPA 2- bia V2 20 0.51 10 20.041 Unnown Generic (SMPA 10 3 System Healty CU01 Active Clac SSMPA 2- bia V2 20 0.51 10 20.041 Unnown Generic (SMPA 10 <td></td> <td>_</td>													_
220 2030 102 20 2030 Unknown Oenercj SMMP 52 System Hathy CU01 Active Caso SMMP2-Esk V2 20 20 200 102 00 200 Telephony Quit Handown Rearcy SMMP System Heathy CU01 Active Caso SMMP2-Esk V2 20 0 200 102 00 202 Unknown Rearcy SMMP 174 System Heathy CU01 Active Caso SMMP2-Esk V2 20 0 20 00 20 202 Unknown Rearcy SIMP2 174 System Heathy CU01 Active Caso SMMP2-Esk V2 20 0 25 Unknown Generic SIMP 174 System Heathy CU01 Active Caso SIMP2-Esk V2 20 0 5.5 Unknown Generic SIMP System Heathy CU01 Active Caso SIMP2-Esk V2 20 0 5.5 Unknown Generic SIMP System Heathy CU01 Active Caso SIMP2-Esk V2 20 0 5.5 Unknown Generic SIMP System Heathy CU01 Active Caso													
220.039 102.0.039 Tephony Outhum Tenor 5.3 System Teshy CUG1 Active Caco SMPA 2- Exa V2 20.030 102.00.22 Uninown Generic SMPA 138 System Teshy CUG1 Active Caco SMPA 2- Exa V2 20.036 102.00.22 Uninown Generic SMPA 171 System Teshy CUG1 Active Caco SMPA 2- Exa V2 20.036 Uninown Generic SMPA 13 System Teshy CUG1 Active Caco SMPA 2- Exa V2 20.037 102.03.23 Uninown Generic SMPA 3 System Yeatm Teshy CUG1 Active Caco SMPA 2- Exa V2 20.039 Uninown Generic SMPA 3 System Yeatm Teshy CUG1 Active Caco SMPA 2- Exa V2 20.041 Victoria Generic SMPA 3 System Yeatm Teshy CUG1 Active Caco SMPA 2- Exa V2 20.041 Victoria Generic SMPA 84 System Yeatm Teshy CUG1 Active Caco SMPA 2- Exa V2 <tr< td=""><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td>_</td></tr<>													_
220 222 102 00 922 Uninovum Generic (SMP 138 System really CU01 Active ClasS SMPA/2-Exit V2 200 36 102 00 58 Uninovum Generic (SMP 171 System really CU01 Active ClasS SMPA/2-Exit V2 200 37 102 00 58 Uninovum AERXY Completer Core (JCPH 5 System really CU01 Active ClasS SMPA/2-Exit V2 200 55 102 00 59 Uninovum AERXY Completer Core (JCPH 3 System really CU01 Active ClasS SMPA/2-Exit V2 200 59 Uninovum Generic (SMP 3 System really CU01 Active ClasS SMPA/2-Exit V2 200 51 Uninovum Generic (SMP 3 System really CU01 Active ClasS SMPA/2-Exit V2 200 51 Uninovum Generic (SMP 84 System really CU01 Active ClasS SMPA/2-Exit V2 200 53 Uninovum Generic (SMP 84 System really CU01 Active ClasS SMPA/2-Exit V2 200 54 Uninovum Generic (SMP 84 System really CU01 Active ClasS SMPA/2-Exit V2 200 55 <td></td>													
220.08 102.00.32 Uninovin Opencie (SMMP 171 System Teamly CU01 Active Caco SMMPA-2 bay 2 200.05 Uninovin ASRC* Comparise Complex Coll 5 System Healby CU01 Active Caco SMMPA-2 bay 2 200.05 102.00.59 Uninovin Generic (SMMP 3 System Healby CU01 Active Caco SMMPA-2 bay 2 200.05 102.00.59 Uninovin Generic (SMMP 84 System Healby CU01 Active Caco SMMPA-2 bay 2 200.061 102.00.59 Uninovin Generic (SMMP 84 System Healby CU01 Active Caco SMMPA-2 bay 2 200.061 Holdowin Generic (SMMP 84 System Healby CU01 Active Caco SMMPA-2 bay 2 200.061 Healby CU03 Healby CU03 Healby CU03 Healby CU04 Caco SMMPA-2 bay 2 200.061 Healby CU03 Healby CU03 Healby CU03 Healby CU04 Caco SMMPA-2 bay 2 200.061 Healby CU03 Healby CU03 Healby CU03 Healby CU04 Caco SMMPA-2 bay 2 2													_
220 553 102.20.9 Unincown ASKPY Computer Corp. (DEM) 5 System Framy CUG1 Active Caco SMIPA-2-Exit V2 220 53 102.00.91 Unincown Generic (SMMP 3 System Framy CUG1 Active Caco SMIPA-2-Exit V2 220 053 102.00.91 Unincown Generic (SMMP 84 System Framy CUG1 Active Caco SMIPA-2-Exit V2 220 053 102.00.91 Unincown Generic (SMMP 84 System Framy CUG1 Active Caco SMIPA-2-Exit V2 220 053 102.00.91 Unincown Generic (SMMP 84 System Framy CUG1 Active Caco SMIPA-2-Exit V2 220 053 102.00.91 Unincown Generic (SMMP 84 System Frame CuG1 Active Caco SMIPA-2-Exit V2 220 054 Unincown Generic (SMMP 84 System Frame CuG1 Active Caco SMIPA-2-Exit V2 220 054 Unincown Generic (SMMP 84 System Frame CuG1 Active Caco SMIPA-2-Exit V2 220 054 Unincown Generic (SMMP 84 System Frame CuG1 CuG2 220 055 Exit Frame CuG1 <td< td=""><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td></td<>													
220 59 10 20 0.99 Unknown Generic (SMP 3 System Healby CU01 Active Claco SMPA 2-2 to V2 220 63 10 20 0.81 Unknown Generic (SMP 84 System Healby CU01 Active Claco SMPA 2-2 to V2 220 63 10 20 0.81 Unknown Generic (SMP 84 System Healby CU01 Active Claco SMPA 2-2 to V2 Claco SMP 2-2 to V2 Claco SMPA 2-2 to V2 Claco SMP 2-2 to V2 Claco SMPA 2-2 to V2 Claco SMPA 2-2 to V2 Claco SMPA 2-2 to V2 Claco SMP 2-2 to V2 Claco SMPA 2-2 to V2 Claco SMPA 2-2 to V2 Claco SMPA 2-2 to V2 Claco SMP 2-2 to V2 Claco SMPA 2-2 to V2 Claco SMPA 2-2 to V2 Claco SMPA 2-2 to V2 Claco SMP 2-2 to V2 Claco SMPA 2-2 to V2 Claco SMPA 2-2 to V2 Claco SMPA 2-2 to V2 Claco SMP 2-2 to V2 Claco SMPA 2-2 to V2 Claco SMPA 2-2 to V2 Claco SMPA 2-2 to V2 Claco SMP 2-2 to V2 Claco SMPA 2-2 to V2 Claco SMPA 2-2 to V2 Claco SMPA 2-2 to V2 Claco SMP 2-2 to V2 Claco SMPA 2-2 to V2 Claco SMPA 2-2 to V2 Claco SMPA 2-2 to V2 Claco SMP 2-2 to V2 Claco SMPA 2-2 to V2 Claco SMPA 2-2 to V2													_
220.0.61 U.20.0.61 Unknown Generic (SMMP 64 System Feathy CUG1 Active Feathy Administration Administration CUG1 CUG1 CUG1 CUG1 CUG1													
Advisor - LDELETE Selected Davides - LUDUETE Selected Davides - LUDUETE Selected Davides - LOLEAR Davide Instance - LOLEAR Davide Instance - LOLEAR Davide Instance - Compact Calceton State - LADite - Compact Instance - Ladite - Ladite - Ladite - Ladite - Ladite - Compact Instance - Ladite - Ladite - Compact Instance - Ladite - Compact Instance - Ladite -													_
											Ininistration: DELETE Selected Di MODIFY By Templat CLEAR Device Logi CREATE Asset Rec SCHEDULE Mainten FIND Collection Lab- bange Collection : Active Disabled bange User Maint Enabled with Collec Enabled without Co Disabled awarge Collector G	e ord ance el Duplicate State: anance M tion llection iroup:	

- 3. In the **Device Manager** page, select the checkbox for each SL1 appliance in your SL1 system. This includes both primary and secondary Database Servers.
- 4. In the Select Action drop-down list, select the following:
 - Change User Maintenance Mode: Enabled without Collection. This option puts the selected devices into user maintenance mode with collection disabled. The devices will remain in this state until you or another user disables user maintenance mode.
- 5. Click the **[Go]** button.

Deploying the Update

NOTE: ScienceLogic recommends that you perform these steps during a maintenance window.

When you deploy a software update, SL1 checks the status of the software on each SL1 appliance. SL1 can deploy the software update to those SL1 appliances that have been successfully staged.

If SL1 is still staging the software update when you select the lightning bolt icon (\checkmark), SL1 will wait until staging has completed before deploying the updates to each SL1 appliance.

You must deploy only the latest update. For example, if you downloaded updates for 8.4.0, 8.5.0, and 8.6.0, you must deploy only the update for 8.6.0.

To deploy a software update:

1. Go to the **System Updates** page (System > Tools > Updates

System Updates					tallation mode: [Upgra	de only]	 Actions Imp 	ort Reset	Guide
EM7 Releases Versions Found [2] Release Version •	Update Signature	Imported On	Imported By	Import Status	Staging Status	Deployment	Deployment Status	Deployment Status Date	
1. EM7 8.2.0.jenkins_EM7_G3_8.2.0 r4269	ScienceLogic Internal QA Build	2016-12-04 16:39:35		Missing Key	N/A	-	New/Unscheduled	-	9 -
2. EM7 8.2.0	Base installation	2016-11-14 16:43:54	em7admin	Complete	N/A	Full (1/1)	New/Unscheduled	-	
ScienceLogic OS Updates Found [2]									
ScienceLogic OS Updates Found [2] Release Version -	Update Signature	Imported On	Imported By	Import Status	Staging Status	Deployment	Deployment Status	Deployment Status Date	
	Update Stockers BickenceLogic Internal QA Build	Imported On 2016-12-04 16:39:35		Import Status	Staging Status N/A	Deployment 	Deployment Status New/Unscheduled	Deployment Status Date	1 1
Release Version			em7admin						
Release Version • 1. Platform 2016-12-01	ScienceLogic Internal QA Build	2016-12-04 16:39:35	em7admin	🔄 Missing Key	N/A	-	New/Unscheduled	-	1
Release Version • 1. Platform 2016-12-01	ScienceLogic Internal QA Build	2016-12-04 16:39:35	em7admin	🔄 Missing Key	N/A	-	New/Unscheduled	-	1
Release Version	ScienceLogic Internal QA Build	2016-12-04 16:39:35	em7admin	🔄 Missing Key	N/A	-	New/Unscheduled	-	1
Release Version	ScienceLogic Internal QA Build	2016-12-04 16:39:35	em7admin	🔄 Missing Key	N/A	-	New/Unscheduled	-	1
Release Version	ScienceLogic Internal QA Build	2016-12-04 16:39:35	em7admin	🔄 Missing Key	N/A	-	New/Unscheduled	-	1
Release Version Platform 2016-12-01	ScienceLogic Internal QA Build	2016-12-04 16:39:35	em7admin	🔄 Missing Key	N/A	-	New/Unscheduled	-	9
Release Version • 1. Platform 2016-12-01	ScienceLogic Internal QA Build	2016-12-04 16:39:35	em7admin	🔄 Missing Key	N/A	-	New/Unscheduled	-	1
Release Version • 1. Platform 2016-12-01	ScienceLogic Internal QA Build	2016-12-04 16:39:35	em7admin	🔄 Missing Key	N/A	-	New/Unscheduled	-	1
Release Version • 1. Platform 2016-12-01	ScienceLogic Internal QA Build	2016-12-04 16:39:35	em7admin	🔄 Missing Key	N/A	-	New/Unscheduled	-	1
Release Version • 1. Platform 2016-12-01	ScienceLogic Internal QA Build	2016-12-04 16:39:35	em7admin	🔄 Missing Key	N/A	-	New/Unscheduled	-	1
Release Version • 1. Platform 2016-12-01	ScienceLogic Internal QA Build	2016-12-04 16:39:35	em7admin	🔄 Missing Key	N/A	-	New/Unscheduled	-	1
Release Version • 1. Platform 2016-12-01	ScienceLogic Internal QA Build	2016-12-04 16:39:35	em7admin	🔄 Missing Key	N/A	-	New/Unscheduled	-	1

- 2. Ensure that the software update for EM7 8.6.0 has a Staging Status of Complete.
- 3. In the EM7 Releases pane, find the software update for EM7 8.6.0. Select its lightning bolt icon (🖉).
- 4. In the **ScienceLogic OS** pane, find the latest OS update. Select its lightning bolt icon (**/**).
- 5. The software update will be deployed to those SL1 appliances in your system that have been successfully staged.
- 6. The **Deployment Status** column displays the status of the deployment. Possible values are:
 - Full. Software was fully deployed to all SL1 appliances.
 - Partial. Software was deployed to some but not all SL1 appliances.
 - Outdated. Software is not the latest version. A later version has been deployed.
 - --. Software has not been deployed on any SL1 appliances.
- 7. For more detailed information about deployment, in the **Deployment Status** column, select the log icon (
- 8. SL1 will install the software update on each SL1 appliance .

Putting All SL1 Appliances Out of Maintenance Mode

To disable user maintenance mode for all the SL1 appliances in your SL1 system:

- 1. Go to the Appliance Manager page. Note the list of SL1 appliances in your system.
- 2. Go to the **Device Manager** page (Registry > Devices > Device Manager):

Data Data <th< th=""><th>e Manager Devices Found [176]</th><th></th><th></th><th></th><th></th><th></th><th></th><th></th><th></th><th>Actions</th><th>Report</th><th>Reset</th><th>Guide</th></th<>	e Manager Devices Found [176]									Actions	Report	Reset	Guide
All Monutation Process	Davina Nama •	IP Address	Device	Devine Class I Sub-class	DID		Ornanization	Current State			SNMP Credential		
Constrain Constrain <thcons< th=""> Cons Constrain</thcons<>	22110210010						0.000000						1
Public 20 133 Public 20 133 Public 20 133 Public 20 133 Public 20 134 Active Cace SIMPLY 2- Exit V PUC 20 13 Pul 10 20 10 15 PU 20 20 135 PU 20 20 141 PU 20 20 20 20 20 20 20 20 20 20 20 20 20	10-Forward	10.20.0.195	Servers	NET-SNMP FreeBSD	54	System		Healthy	CUG1	Active	Cisco SNMPv2 - E	xa V2	(m)) (s)
Philo Philo <th< td=""><td>A 10.20.0.108</td><td>910.20.0.108</td><td>Network.Router</td><td>Cisco Systems 2501</td><td>72</td><td>System</td><td></td><td>Healthy</td><td>CUG1</td><td>Active</td><td>Cisco SNMPv2 - E</td><td>xa V2</td><td>H</td></th<>	A 10.20.0.108	910.20.0.108	Network.Router	Cisco Systems 2501	72	System		Healthy	CUG1	Active	Cisco SNMPv2 - E	xa V2	H
Juli B200 1155 UD101 Active Disco SIMPA 2- Exis V2 PC 200 200.0 141 10.20.0 141 Network. Switcher Gao Systems (Cataly V3-Sold V2.0 31 System Heathy CU01 Active Disco SIMPA 2- Exis V2 PC 200 200.0 141 10.20.0 141 Network. Switcher Gao Systems (Cataly V3-Sold V2.0 31 System Heathy CU01 Active Disco SIMPA 2- Exis V2 PC 200 Active Disco SIMPA 2- Exis V2 Disco SIMPA	A 10.20.0.123	10.20.0.123	Network.Router	Cisco Systems 7206VXR	112	System		Minor	CUG1	Active	Cisco SNMPv2 - E	ixa V2	
2500 141 120.0141 Network.Switcher Gao Systems (Latalysi VS-C000-Ca005 16 System Nethy CU01 Achive Caoo SIMPA 2- Eas V2 200 144 120.00147 120.00147 Network.Broadsheithage Methoga 334:0-01 2 System Nethy CU01 Achive Caoo SIMPA 2- Eas V2 200 147 120.00147 Network.Broadsheithage Methoga 1870,RSK,RXX,RV 18 System Nethy CU01 Achive Caoo SIMPA 2- Eas V2 200 144 120.00147 Network.Broadsheithage Methoga 1870,RSK,RXX,RV 18 System Nethy CU01 Achive Caoo SIMPA 2- Eas V2 200 143 120.00140 Uninnoun Generic [SMP 141 System Nethy CU01 Achive Caoo SIMPA 2- Eas V2 200 143 120.00163 Uninnoun Generic [SMP 141 System Nethy CU01 Achive Caoo SIMPA 2- Eas V2 200 143 100.0016 Uninnoun Generic [SMP 141 System Nethy CU01 Achive Caoo SIMPA 2- Eas V2 200 143 100.0016 Uninnoun Generic [SMP 145 System 1410		10.20.0.13	Unknown	Generic SNMP	107	System		Allealthy	CUG1	Active	Cisco SNMPv2 - E	xa V2	(m) 13 (k)
2020 144 102.00.144 102.00.147 102.00.147 102.00.147 102.00.147 Network Encade Helping Helping 334' of 21 2 System Helping Cloid 1 Active Caso SMMP-2-Exit V2 2020 147 102.00.147 Network Encade Helping Helping 334' of 21 17 System Helping Cloid 1 Active Caso SMMP-2-Exit V2 2020 143 102.00.147 Network Encade Helping 1720-7 162 System Helping Cloid 1 Active Caso SMMP-2-Exit V2 2020 143 102.00.147 Network Encade Helping 1720-7 162 System Helping Cloid 1 Active Caso SMMP-2-Exit V2 2020 143 102.00.161 Uninnown Generic 10MP 165 System Helping Cloid 1 Active Caso SMMP-2-Exit V2 2020 143 102.00.161 Uninnown Generic 10MP 165 System Helping Cloid 1 Active Caso SMMP-2-Exit V2 2020 143 102.00.161 Uninnown Generic 10MP 145 System Helping Cloid 1 Active Caso SMMP-2-Exit V2 2020 149 Uninnown Generic 10MP <td>10.20.0.135</td> <td>10.20.0.135</td> <td>Network.Switche</td> <td>Cisco Systems Catalyst 3508G-XL</td> <td>131</td> <td>System</td> <td></td> <td>Allealthy</td> <td>CUG1</td> <td>Active</td> <td>Cisco SNMPv2 - E</td> <td>xa V2</td> <td>m 10 %</td>	10.20.0.135	10.20.0.135	Network.Switche	Cisco Systems Catalyst 3508G-XL	131	System		Allealthy	CUG1	Active	Cisco SNMPv2 - E	xa V2	m 10 %
220 147 12.20 147 12.20 147 12.20 147 12.20 147 12.20 147 12.20 147 12.20 147 12.20 148 Network Encade Helpigh (Hock, RTAD, RTA) 13.3 System 1481by CUG1 Achive Caso SIMPA - Exis V2 220 149 12.20 0.149 Network Encades Helpigh (HCR), RTAD, RTA 13.3 System 1481by CUG1 Achive Caso SIMPA - Exis V2 220 149 10.20 0.151 Unnown Generic (SIMPA 141 System 1481by CUG1 Achive Caso SIMPA - Exis V2 200 150 10.20 0.151 Unnown Generic (SIMPA 145 System 1481by CUG1 Achive Caso SIMPA - Exis V2 200 155 Unnown Generic (SIMPA 145 System 1481by CUG1 Achive Caso SIMPA - Exis V2 200 155 Unnown Generic (SIMPA 145 System 1481by CUG1 Achive Caso SIMPA - Exis V2 200 156 Unnown Generic (SIMPA 145 System 1481by CUG1 Achive Caso SIMPA - Exis V2 200 157 Unnown Generic (SIMPA 13 </td <td>.20.0.141</td> <td>10.20.0.141</td> <td>Network.Switche</td> <td>s Cisco Systems Catalyst WS-C6009-CatOS</td> <td>118</td> <td>System</td> <td></td> <td>Healthy</td> <td>CUG1</td> <td>Active</td> <td>Cisco SNMPv2 - E</td> <td>xa V2</td> <td></td>	.20.0.141	10.20.0.141	Network.Switche	s Cisco Systems Catalyst WS-C6009-CatOS	118	System		Healthy	CUG1	Active	Cisco SNMPv2 - E	xa V2	
200 144 1220 143 1220 144 1220 144 1220 144 1220 144 1220 144 1220 144 1220 144 1220 144 1220 144 1220 144 1220 144 1220 144 1220 144 1220 144 1220 144 1220 144 1220 144 1220 144 1220 145	.20.0.146	10.20.0.146	Network.Broadba	r Netopia Netopia 3346 v8.2r1	2	System		Healthy	CUG1	Active	Cisco SNMPv2 - E	xa V2	
2020 149 12.20.149 Hervork Breades (SHAP 141 System Heady Cu01 Active Caso SHMP-2-tax V2 2020 151 102.20.151 Uninovin Generic (SHAP 141 System Heady Cu01 Active Caso SHMP-2-tax V2 2020 151 102.20.151 Uninovin Generic (SHAP 141 System Heady Cu01 Active Caso SHMP-2-tax V2 2020 153 102.20.157 Uninovin Generic (SHAP 144 System Heady Cu01 Active Caso SHMP-2-tax V2 2020 157 102.20.175 Uninovin Generic (SHAP 144 System Heady Cu01 Active Caso SHMP-2-tax V2 2020 157 102.20.176 Uninovin Generic (SHAP 44 System Tilleer Cu01 Active Caso SHMP-2-tax V2 2020 158 102.20.159 Uninovin Generic (SHAP 45 System Tilleer Cu01 Active Caso SHMP-2-tax V2 2020 158 102.20.201 Uninovin Generic (SHAP 57 System Tilleer Cu01 Active Ca	0.20.0.147	10.20.0.147	Network.Broadba	r Netopia Netopia 3381 v8.0.10	175	System		Healthy	CUG1	Active	Cisco SNMPv2 - E	xa V2	
220.0151 Ubinovin Operand (MP) (41) System Pathy CU01 Active Cao SMM2-2-bit V2 200.150 102.00.163 Ubinovin Generic (SMP) 165 System Pathy CU01 Active Cao SMM2-2-bit V2 200.153 102.00.175 Ubinovin Generic (SMP) 44 System Pathy CU01 Active Cao SMM2-2-bit V2 200.157 102.00.175 Ubinovin Generic (SMP 44 System Pathy CU01 Active Cao SMM2-2-bit V2 200.156 102.00.175 Ubinovin Generic (SMP 54 System Pathy CU01 Active Cao SMM2-2-bit V2 200.151 102.00.210 Ubinovin Generic (SMP 54 System Lifter CU01 Active Cao SMM2-2-bit V2 200.151 Ubinovin Generic (SMP 45 System Lifter CU01 Active Cao SMM2-2-bit V2 200.202 Ubinovin Generic (SMP 53 System Pathy	.20.0.148	10.20.0.148	Network.Broadba	r Netopia Netopia (R3100, R45xx, R7xx0, R9	163	System		Healthy	CUG1	Active	Cisco SNMPv2 - E	xa V2	
220.163 10.20.163 Unknown Generic (SMP 164 System Featry CUO1 Active Caco SMPA/2-Exa V2 220.163 10.20.0153 Unknown Generic (SMP 164 System Featry CUO1 Active Caco SMPA/2-Exa V2 220.175 10.20.0175 Unknown Generic (SMP 44 System Featry CUO1 Active Caco SMPA/2-Exa V2 220.176 10.20.0176 Unknown Generic (SMP 44 System Featry CUO1 Active Caco SMPA/2-Exa V2 220.176 10.20.0191 Unknown Generic (SMP 56 System Featry CUO1 Active Caco SMPA/2-Exa V2 220.011 10.20.0191 Unknown Generic (SMP 58 System Featry CUO1 Active Caco SMPA/2-Exa V2 20.011 10.20.0121 Unknown Generic (SMP 58 System Featry CUO1 Active Caco SMPA/2-Exa V2 20.023 Unknown Generic (SMP 58 System Featry CUO1 Active Caco SMPA/2-Exa V2 <	.20.0.149	10.20.0.149	Network.Broadba	r Netopia R7200-T	162	System		Healthy	CUG1	Active	Cisco SNMPv2 - E	xa V2	
200 1630 102.00.163 Uninovin Generic (SMPP 164 System Heatry CUG1 Active Caco SMPA 2- Exa V2 200 1630 102.00.163 Uninovin Generic (SMPP 164 System Heatry CUG1 Active Caco SMPA 2- Exa V2 200 175 102.00.175 Uninovin Generic (SMPP 44 System Heatry CUG1 Active Caco SMPA 2- Exa V2 200 175 Uninovin Generic (SMPP 45 System Lifeer CUG1 Active Caco SMPA 2- Exa V2 200 176 Uninovin Generic (SMP 56 System Lifeer CUG1 Active Caco SMPA 2- Exa V2 200 176 Uninovin Generic (SMP 58 System Fuller CUG1 Active Caco SMPA 2- Exa V2 200 520 Uninovin Generic (SMP 58 System Fuller CUG1 Active Caco SMPA 2- Exa V2 200 520 Tagaboris Generic (SMP 51 System Fuller CUG1 Active Caco SMPA 2- Exa V2 200 520 Tagaboris Generic (SMP <td></td> <td>10.20.0.151</td> <td>Unknown</td> <td>Generic SNMP</td> <td>141</td> <td>System</td> <td></td> <td>Healthy</td> <td>CUG1</td> <td>Active</td> <td>Cisco SNMPv2 - E</td> <td>xa V2</td> <td></td>		10.20.0.151	Unknown	Generic SNMP	141	System		Healthy	CUG1	Active	Cisco SNMPv2 - E	xa V2	
200083 10200183 Unknown Genetic (SMP 144 System Testhy Cloit Active Caso SMPA-2-bix V2 200175 10200175 Unknown Genetic (SMP 44 System Testhy Cloit Active Caso SMPA-2-bix V2 200175 10200176 Unknown Genetic (SMP 55 System Cloit Active Caso SMPA-2-bix V2 200176 10200176 Unknown Genetic (SMP 55 System Take Cloit Active Caso SMPA-2-bix V2 200171 10200191 Office Printer Knick Mincka Innoka Innoka (Fery 3222-KM System Taket Cuso SMPA-2-bix V2 200131 10200201 Unknown Genetic (SMP 48 System Tabit Cloit Active Caso SMPA-2-bix V2 200203 10200201 Unknown Genetic (SMP 53 System Tabit Cloit Active Caso SMPA-2-bix V2 200202 Testhym Cuso SMP System Testhy Cloit Active		10.20.0.160	Unknown	Generic SNMP	165	System			CUG1	Active	Cisco SNMPv2 - E	xa V2	
200.176 102.09.176 Unknown Konick Corporation (DEM) 41 System Unknown Active Closicit Active Closicit </td <td>20.0.163</td> <td>10.20.0.163</td> <td>Unknown</td> <td>Generic SNMP</td> <td>164</td> <td>System</td> <td></td> <td>Healthy</td> <td>CUG1</td> <td>Active</td> <td>Cisco SNMPv2 - E</td> <td>xa V2</td> <td></td>	20.0.163	10.20.0.163	Unknown	Generic SNMP	164	System		Healthy	CUG1	Active	Cisco SNMPv2 - E	xa V2	
220.175 102.00.176 Unknown Keinic Corporation (DEU) 41 System Unknown Clos (SMLPA-2-bix V2 200.196 102.00.191 Unknown Generic (SMLPA 55 System Unknow Clos (SMLPA-2-bix V2 200.191 102.00.091 Office Printer Kinick Minota (Minota (Minota (Minota) Fary/32.22xML 57 System Unknow Clos (SMLPA-2-bix V2 200.011 102.00.201 Unknown Generic (SMLPA 58 System Heathy Clos (SMLPA-2-bix V2 200.0203 102.00.201 Unknown Generic (SMLPA 58 System Heathy Clos (SMLPA-2-bix V2 200.0203 102.00.201 Unknown Generic (SMLPA 53 System Heathy Clos (SMLPA-2-bix V2 200.0203 102.00.201 Guthone (Mereic (SMLPA 53 System Heathy Clos (SMLPA-2-bix V2 200.0203 102.00.201 Guthone (Mereic (SMLPA 53 System Heathy Clos (SMLPA-2-bix V2 200.023 102.00.201 Guthone (Mereic (SMLPA 53 System Heathy Clos (SMLPA-2-bix V2 200.023 102.00.201 Guthone (Mereic (SMLPA 53 System Heathy Clos (SMLPA-2-bix V2 200.023 102.00.20	.20.0.175	10.20.0.175	Unknown	Generic SNMP	44	System		Heathy	CUG1	Active	Cisco SNMPv2 - E	xa V2	
200.0191 1020.03191 Office Printer Knick Merda (Fery/36.22C-ML 97 System User Out01 Active Caso SMM2-2-Exit V2 20.0301 10.20.0210 Unknown Generic SMMP 43 System Heathy Cu01 Active Caso SMM2-2-Exit V2 20.0301 10.20.0210 Unknown Generic SMMP System Heathy Cu01 Active Caso SMM2-2-Exit V2 20.0301 10.20.020 Thelphony Out1 Rote Caso SMM2-2-Exit V2 20.0302 Hanown Generic SMMP System Heathy Cu01 Active Caso SMM2-2-Exit V2 20.0303 10.20.0402 Unknown Generic SMMP 171 System Heathy Cu01 Active Caso SMM2-2-Exit V2 20.053 10.20.054 Unknown Generic SMMP System Heathy Cu01 Active Caso SMM2-2-Exit V2 20.053 10.20.054 Unknown Generic SMMP System Heathy Cu01 Active Caso SMM2-2-Exit V2 20.05	20.0.176	10.20.0.176	Unknown	Konica Corporation OEM	41	System			CUG1	Active	Cisco SNMPv2 - E	xa V2	
200.0191 010ce Printer Konce Minda Mercel System Testing Clo31 Active Caso SMM2-2-bit V2 200.021 10.20.020 Unknown Genetic SMMP 43 System Testing Cl031 Active Caso SMM2-2-bit V2 200.020 10.20.020 Unknown Genetic SMMP 52 System Testing Cl031 Active Caso SMM2-2-bit V2 200.020 10.20.020 Unknown Genetic SMMP 53 System Testing Cl031 Active Caso SMM2-2-bit V2 200.020 10.20.020 Unknown Genetic SMMP 138 System Testing Cl031 Active Caso SMM2-2-bit V2 200.023 Unknown Genetic SMMP 171 System Testing Cl031 Active Caso SMM2-2-bit V2 200.023 Unknown Genetic SMMP 13 System Testing Cl031 Active Caso SMM2-2-bit V2 200.03 Unknown Genetic SMMP 3 System Testing Cl041	20.0.190	10.20.0.190	Unknown	Generic I SNMP	56	System		(1) Minor	CUG1	Active	Cisco SNMPv2 - E	xa V2	
20031 102.00.01 Unknown Generic (SMP 48 System Feastry CU01 Active Caso SMPA/2-Exis V2 200308 102.00.020 Telephony Guntum, Teor 53 System Heathy CU01 Active Caso SMPA/2-Exis V2 200308 102.00.020 Telephony Guntum, Teor 53 System Heathy CU01 Active Caso SMPA/2-Exis V2 200308 102.00.020 Telephony Guntum, Teor 53 System Heathy CU01 Active Caso SMPA/2-Exis V2 200308 102.00.020 Unknown Generic (SMP 171 System Heathy CU01 Active Caso SMPA/2-Exis V2 200308 102.00.020 Unknown Generic (SMP 171 System Heathy CU01 Active Caso SMPA/2-Exis V2 200308 102.00.021 Unknown Generic (SMP 171 System Heathy CU01 Active Caso SMPA/2-Exis V2 200309 102.00.021 Unknown Generic (SMP 141 System Heathy CU01 Active Caso SMPA/2-Exis V2 20131 102.00.021 Unknown Generic (SMP 145 System Heathy CU01	20.0.191	10 20 0 191	Office Printers	Konica Minota I Fiery X3e 22C-KM	57			() Minor	CUG1	Active	Cisco SNMPv2 - E	xaV2	1
202030 10200308 Unknown Opencie (SMMP 52 System Healty CUG1 Active Caso SMM2-2: bix V2 200209 10200302 Unknown Generic (SMMP 53 System Healty CUG1 Active Caso SMM2-2: bix V2 200209 10200302 Unknown Generic (SMMP 138 System Healty CUG1 Active Caso SMM2-2: bix V2 20023 10200302 Unknown Generic (SMP 171 System Healty CUG1 Active Caso SMM2-2: bix V2 20053 1020059 Unknown Generic (SMP 171 System Healty CUG1 Active Caso SMM2-2: bix V2 20059 Unknown Generic (SMP 3 System Healty CUG1 Active Caso SMP2-2: bix V2 20059 Unknown Generic (SMP 3 System Healty CUG1 Active Caso SMP2-2: bix V2 20061 Unknown Generic (SMP 3 System Healty CUG1 </td <td></td> <td></td> <td>Unknown</td> <td></td> <td></td> <td></td> <td></td> <td></td> <td></td> <td></td> <td></td> <td></td> <td>-</td>			Unknown										-
20.029 10.20.039 Tephony Outhum Teor 5.3 System tealhy CUG1 Actve Caoo SMM-2-Exa V2 20.020 20.022 Unknown Generic SMMP 138 System tealhy CUG1 Actve Caoo SMM-2-Exa V2 20.052 10.20.023 Unknown Generic SMMP 171 System tealhy CUG1 Actve Caoo SMM-2-Exa V2 20.053 10.20.052 Unknown Generic SMMP 13 System tealhy CUG1 Actve Caoo SMM-2-Exa V2 20.053 Unknown Generic SMMP 3 System tealhy CUG1 Actve Caoo SMM-2-Exa V2 20.054 Unknown Generic SMMP 3 System tealhy CUG1 Actve Caoo SMM-2-Exa V2 20.051 Unknown Generic SMMP 84 System tealhy CUG1 Actve Caoo SMM-2-Exa V2 20.051 Unknown Generic SMMP 84 System tealhy CUG1 Actve Caoo SMM-2-Exa V2 20.051 Unknown Generic SMMP 84 System tealhy CUG1 Actve Caoo SMM-2-Exa V2 20.051 Unknown Generic SMMP 84 Sys													1
20 222 Uninown Generic (SMP 174 System Testly Cu31 Active Casa SMPA-2-Ex V2 20 56 Uninown Generic (SMP 174 System Testly Cu31 Active Casa SMPA-2-Ex V2 20 55 122 0.53 Uninown ASKY Compart Con (DEM 7 System Testly Cu31 Active Casa SMPA-2-Ex V2 20 59 0 Uninown Generic (SMP 3 System Testly Cu31 Active Casa SMPA-2-Ex V2 20 61 0.20 59 Uninown Generic (SMP 8 System Testly Cu31 Active Casa SMPA-2-Ex V2 20 61 0.20 59 Uninown Generic (SMP 8 System Testly Cu31 Active Casa SMPA-2-Ex V2 20 61 0.20 59 Uninown Generic (SMP 8 System Testly Cu31 Active Casa SMPA-2-Ex V2 20 61 0.20 59 Uninown Generic (SMP 8 System Testly Cu31 Active Casa SMPA-2-Ex V2 20 61 0.20 59 Uninown Generic (SMP 8 System Testly Cu31 Active Casa SMPA-2-Ex V2 20 61 0.20 59 Uninown Generic (SMP 6 System Testly Cu31 Active Casa SMPA-2-Ex V2 20 61 0.20 59 Uninown Generic (SMP 6 System Testly Cu31 Active Casa SMPA-2-Ex V2 20 61 0.20 59 Cu31 Uninown Generic (SMP 6 System Testly Cu31 Active Casa SMPA-2-Ex V2 20 61 0.20 59 Cu31 Uninown Generic (SMP 6 System Testly Cu31 Active Cu31 Active Casa SMPA-2-Ex V2 20 61 0.20 59 Cu31 Uninown Generic (SMP 6 System Testly Cu31 Active Cu31 Activ													-
2005 102005 Ukinovin Generic SMP 171 System 1891by CuG1 Actve Caso SMPA-2-bav2 2055 102005 Ukinovin ASKY: Comparison Comparison SMPA Comparison SMPA Comparison SMPA Comparison Comparison SMPA Comparison Compar													
20059 1020059 Unknown ASKY Compare Cop. (DEM 5 System Testhy CU01 Active Caso SMR/A-2-Ex V2 20059 1020059 Udo of the Coso SMR/A-2-Ex V2 System Testhy CU01 Active Caso SMR/A-2-Ex V2 20051 1020059 Udo of the Coso SMR/A-2-Ex V2 System Testhy CU01 Active Caso SMR/A-2-Ex V2 20053 1020059 Unknown Generic (SMR/A System Testhy CU01 Active Caso SMR/A-2-Ex V2 20051 1020059 Unknown Generic (SMR/A System Testhy CU01 Active Caso SMR/A-2-Ex V2 20053 1020059 Unknown Generic (SMR/A System Testhy CU01 Active Caso SMR/A-2-Ex V2 20054 1020059 Finance Generic (SMR/A Execol Min/A-2-Ex V2 Execol Min/A-2-Ex V2 Execol Min/A-2-Ex V2 20055 Concol Min/A-2-Ex V2 Execol Min/A-2-Ex V2 Execol Min/A-2-Ex V2 Execol Min/A-2-Ex V2 20057 Strandard Andre Execol Min/A-2-Ex V2 Execol Min/A-2-Ex V2 Execol Min/A-2-Ex V2 20057 Strandard Andre Execol Min/A-2-Ex V2 Execol Min/A-2-Ex V2 Execol Min/A-2-Ex V2 20057 Strandard													
20059 10.20059 Unanown Generic (SMMP 3 System Healby CuG1 Active Caso SMMP-2-Ex V2 20063 10.20081 Unknown Generic (SMMP 84 System Healby CuG1 Active Caso SMMP-2-Ex V2 Unknown Generic (SMMP 84 System Healby CuG1 Active Caso SMMP-2-Ex V2 Unknown Generic (SMMP 84 System Healby CuG1 Active Caso SMMP-2-Ex V2 UCLRA Device Logs Caso SMMP-2-Ex V2 UCLRA Device													
200.081 Unknown Generic (SMMP 84 System Hostbry CUG1 kictive Cource) And the Article A													1
LEETE Seried Gevices LUCETE Seried Gevices LUCEAR Device Logs CREATE Asset Record ESDEDUE Mentenance Compo Centrol State: Lactive Logabed Compo Centrol State: Lactive Logabed Compo Centrol State: Lactive Logabed Compo Centrol State: Logabed Compo Centrol State: Logabed Centrol State: Logabed Centrol State													
Nove To Organization;										a	Inimistration: DELETE Selected D LOELETE Selected D LOEDET Selected D CREATE Asset Rec SCHEDULE Mainten FIND Colection Labiange Collection : Active Disabled Inange User Maintu Enabled with Colec Enabled with Colec Enabled with Cole Disabled Inange Collector G CUG1	e ord ance el Duplicate State: anance M tion llection iroup:	

- 3. In the **Device Manager** page, select the checkbox for each SL1 appliance in your SL1 system.
- 4. In the Select Action drop-down list, select the following:
 - Change User Maintenance Mode: Disabled. This option disables user maintenance mode for the selected devices.
- 5. Click the **[Go]** button.

Performing Deltaless Upgrades

After performing the steps to upgrade to SL1 8.6.0, continue to the **Upgrading the SL1 Distributed** Architecture on SL1 versions 8.6.0 and Later to upgrade to the latest SL1 release.

Upgrading the SL1 Distributed Architecture on SL1 versions 8.6.0 and Later

As of 8.12.0, SL1 uses an improved System Updates tool (System > Tools > Updates).

Version 8.12.1.3 introduced delta-less upgrades, meaning that you can import a single file and upgrade to the latest version. Delta-less upgrades can upgrade the SL1 system from any SL1 release 8.6.0 or later to the current release, using only a single update.

NOTE: : You must be running SL1 8.6.0 or later to use delta-less updates.

NOTE: Ensure that the each SL1 appliance has 3GB of free space in the /var partition to allow you stage the upgrade. Ensure that each SL1 appliance has 1GB of free space in / (the root partition) to allow you to deploy the upgrade.

Any distributed system running 8.6.0 or later can be upgraded by importing, staging, and deploying a single update file.

Upgrading the Distributed Stack for SL1 includes the following steps:

- For systems prior to 8.12.0, disabling automatic staging
- Downloading the Update
- Importing the Update
- Staging the Update
- Monitoring Staging
- Running the Pre-Upgrade Check
- Putting All SL1 Appliances in Maintenance Mode
- Deploying the Update
- Monitoring Deployment
- Putting All SL1 Appliances Out of Maintenance Mode

Special Steps for SL1 8.12.0 and Earlier

For systems running an SL1 version prior to 8.12.0, go to the System Updates page and disable automatic staging (System > Tools > Updates > Actions > Disable automatic staging).

If you have previously used manual staging, perform these additional steps:

- 1. Select all updates in the EM7 Releases pane and select all updates in the ScienceLogic OS pane.
- 2. In the **Select Action** menu, select Unstage Update (remove staging policy override). Click Go.
- 3. For software that was previously staged with automatic staging, Unstage Update (remove staging policy override) does not affect staging.

Downloading the Update

NOTE: To download updates for previous the SL1 system software versions that have reached their End of Life date and are no longer supported by ScienceLogic, contact ScienceLogic Support or a designated Customer Success Manager to get the update files.

Before you can load a patch or update onto your instance of the SL1 system, you must first download the patch or update to your local computer. To do this:

NOTE: These steps do not affect the performance of the SL1 system. ScienceLogic recommends that you perform these steps at least 3 days before upgrading.

- 1. Log in to https://support.sciencelogic.com. Use your ScienceLogic customer account and password to access this site.
- 2. Select the [Product Downloads] button, select the Product Downloads menu, and choose Platform.
- 3. Find the release you are interested in and click its name.

Release Version SL1 Big Ben 8.12.0				Edit Del
Release Version Name		Version		
GL1 Big Ben 8.12.0		8.12.0		
ind of Maintenance 10/31/2020		End of Life 4/30/2021		
Online Documentation		Allow Customers to View on Community		
lumber of Files				
Release Files (2)				Ν
LE NAME	COMMENTS	RECORD TYPE	RELEASE DATE	
12.0	System running 8.10.0+ or System has 8.10.0 siloupdat	Product Update	4/24/2019	
12.0		Image	4/24/2019	

- 4. In the **Release Version** article, click on the link for the release image or release patch you want to download. Scroll to the bottom of the page.
- 5. Under **Files**, select the link for the file you want to download. The file is then downloaded to your local computer.

Importing the Update

To import a product update on to your SL1 system:

NOTE: These steps do not affect the performance of the SL1 system. ScienceLogic recommends that you perform these steps at least 3 days before upgrading.

- 1. Make sure that you can navigate to the patch file.
- 2. In the SL1 system, go to the **System Updates** page (System > Tools > Updates).
- 3. In the System Updates page, click the [Import] button.

Import a new update		×
Browse for file	Browse	
Auto Stage		
	Import	

- 4. In the Import a new update modal page, browse to the product update file and select it.
 - If you select the **Auto Stage** button, the SL1 system will begin staging as soon as the import is completed.
 - If you do not select the **Auto Stage** button, you must click the staging button(20) after import is completed. You can do so at any time after import has completed.
 - For more information on automatic staging and manual staging, see the section on "Staging" in the *System Administration* manual.
- 5. Click the [Import] button.
- 6. In the System Updates page, the Import Status column can have one of the following statuses:
 - In Progress. Software is currently being imported by the SL1 system.
 - Complete. Software has been imported successfully.
 - Failed. Software import has failed due to an unexpected condition. Contact ScienceLogic Support for assistance.
 - *Missing Base*. The SL1 system cannot import this software until another software package has been imported. The dependency is for compression purposes. Check the log for a message stating which software package needs to be imported.
- 7. The update file or patch file is imported to SL1 system and appears in the System Updates page.

NOTE: For details on the import process, go to the **System Updates** page, find the entry for the software you are interested in, go to its **Import Status** column, and click the log icon (a).

Staging the Update

After you import a software update to your SL1 system, you must **stage** the software update. During staging, the SL1 system copies the software update to each SL1 appliance. Staging allows SL1 to simultaneously apply the software changes to each SL1 appliance, regardless of the speed of the connection to each SL1 appliance. The SL1 system stages updates per import. You can choose to automatically stage imports or manually stage import.

For easiest troubleshooting, ScienceLogic recommends that you manually stage imports.

NOTE: These steps do not affect the performance of the SL1 system. ScienceLogic recommends that you perform these steps at least 3 days before upgrading.

After the software update is imported and staged, you can deploy the software.

Automatic Staging

To enable automatic staging:

- 1. In SL1, go to the **System Updates** page (System > Tools > Updates).
- 2. In the System Updates page, click the [Import] button.

Import a new update			×
Browse for file		Browse	
Auto Stage			
	Import		

- 3. In the Import a new update modal page, browse to the product update file and select it.
 - If you select the **Auto Stage** button, the SL1 system will begin staging as soon as the import is completed.
- After import, in the System Updates page, the Staging Status column will display the number of ScienceLogic appliances that have been successfully stage compared to the total number of ScienceLogic appliances.

NOTE: For details on the staging process, go to the **System Updates** page, find the entry for the software you are interested in, go to its **Staging Status** column, and click the log icon (a).

- 5. The Staging Status column can have one of the following statuses:
 - --. No staging request is active and software has not been staged on any SL1 appliances.
 - Scheduled. The SL1 system is aware of the staging request and is preparing for staging.
 - In Progress. Staging is in progress but has not completed. The page displays the percentage complete as staging progresses.
 - Complete. Staging has completed, and all appliances are ready to deploy the software.
 - Incomplete. Staging has completed, and one or more appliances are ready to deploy the software.
 - Canceled. User manually canceled the staging process.
 - Outdated. The current update is not the latest or has already been installed.
 - Failed. An unexpected error occurred in the staging process. Contact ScienceLogic Support.

To disable automatic staging:

- 1. In SL1, go to the **System Updates** page (System > Tools > Updates).
- 2. In the System Updates page, click the [Import] button.

Import a new update	×
Browse for file	Browse
Auto Stage	
	Import

- 3. In the Import a new update modal page, browse to the product update file and select it.
 - If you **do not select** the **Auto Stage** button, you must click the staging button(⁽²⁾) after import is completed. You can do so at any time after import has completed.

NOTE: For details on the staging process, go to the **System Updates** page, find the entry for the software you are interested in, go to its **Staging Status** column, and click the log icon (a).

Manually Staging an Update

You can manually stage a software update to one or more SL1 appliances.

For example, you can manually stage a software update:

- If you imported an update but do not want to stage it immediately.
- If you add another ScienceLogic appliance to your SL1 system and need to apply software updates.
- If staging failed on one or more ScienceLogic appliances.
- If you want to ensure that a previous staging process was successful.

When you manually stage a software update, SL1 checks the status of the software updated on each ScienceLogic appliance. SL1 then stages the software update **only to those SL1 appliances that have not yet been staged** for this software update.

To manually stage a software update:

1. In SL1, go to the **System Updates** page (System > Tools > Updates).

ystem Updates					•	Import Reset Guide
M7 Releases Versions Found [2] EM7 Version •	OS Version	Update Signature	Imported On Imported By	Import Status Stage	ng Status Deployment Statu	s Deployment Status Date
1. EM7 8.12.0	Platform 2019-04-09	ScienceLogic Official Release	2019-04-19 05:13:55 em7admin	Complete Complete	te (4/4) Complete (4/4)	2019-04-19 09:44:10
2. EM7 8.10.0	Platform 2018-11-27	Base installation	2018-12-17 23:42:02 em7admin	🗟 Complete 🔄 Outdate	d Qutdated	2019-04-19 09:15:45 🛛 🕥 🖉 📰

- 2. In the **System Updates** page, find the software update you want to stage. Select its staging icon **(**).
- 3. The software update will be copied to each ScienceLogic appliance that has not yet been staged.
- 4. The Staging Status column will display the number of ScienceLogic appliances that have been successfully stage compared to the total number of ScienceLogic appliances.

NOTE: For details on the staging process, go to the **System Updates** page, find the entry for the software you are interested in, go to its **Staging Status** column, and click the log icon (a).

- 5. The Staging Status column can have one of the following statuses:
 - --. No staging request is active and software has not been staged on any SL1 appliances.
 - Scheduled. The SL1 system is aware of the staging request and is preparing for staging.

- In Progress. Staging is in progress but has not completed.
- Complete. Staging has completed, and all appliances are ready to deploy the software.
- Incomplete. Staging has completed, and one or more appliances are ready to deploy the software.
- Canceled. User manually canceled the staging process.
- Outdated. The current update is not the latest or has already been installed.
- Failed. An unexpected error occurred in the staging process. Contact ScienceLogic Support.


Monitoring Staging

For SL1 versions 8.12.0 and later, you can monitor staging. To do so:

- 1. Either go to the console of the Database Server or use SSH to access the Database Server.
- 2. Enter the following at the shell prompt:

monitor stage

3. You should see something like this:



- System Update Vitals. Displays the current status of the services that are required for System Update.
- Staging Process Stats. Displays status of staging on all SL1 appliances.

Running the Pre-Upgrade Check for SL1 10.1 and Later

After importing and staging an update, you can run a pre-upgrade check before deploying. The pre-upgrade check will ensure that all criteria are met before deploying.

NOTE: These steps do not affect the performance of SL1. ScienceLogic recommends that you perform these steps at least 3 days before upgrading.

The pre-upgrade check examines the following:

- Is each SL1 Appliance eligible to be updates?
- Are updates enable on each SL1 Appliance?
- Are any of the SL1 Appliances running CentOS 5?
- Is this hostfile on each SL1 Appliance correctly configured
- Is each Data Collector and Message Collector in a Collector Group?
- Is there enough free space on the disk to perform the upgrade?
- Is the RPM database corrupted?
- Are the RPM packages corrupted?
- Does the patch hook directory have the correct owner assigned?
- Detect out-of-date CRM templates on High Availability and Disaster Recovery systems
- If /etc/init.d/mysql does not exist, creates the file
- Skips SL1 appliances that have been deleted since the last upgrade

Running the Pre-Upgrade Check

To run a pre-upgrade check:

1. Go to the **System Updates** page (System > Tools > Updates.

System Updates								Appliance List In	port Reset Guide
EM7 Releases Versions Found [1] EM7 Version • 1. EM7 10.1.0	OS Version Platform 2020-05-01	Update Signature Base Installation	Imported On 2020-06-25 15:46:01	Imported By em7admin	Import Status	Staging Status	Preupgrade Status	Deployment Status	Deployment Status Date 2020-06-25 22:59:53

- 2. Find the upgrade that you want to deploy.
- 3. Click the purple checkmark at the end of the row. The pre-upgrade check will run.
- 4. If a pre-upgrade criterion fails, the [Deploy] button will be disabled for the selected row.
- 5. To view the output from the pre-upgrade check, click on the on the magnifying-glass icon () in the selected row.
- 6. If the pre-upgrade check finds a failure, see the list below for possible causes.
- 7. Fix all failures before deploying the update.

CentOS 5 Failure

CentOS 5 is no longer supported by System Update. If one or more Data Collectors are running CentOS5, the pre-upgrade check will fail. Contact your Customer Success Manager to determine how to upgrade your Data Collectors.

Collector Group Membership

This test checks that each Data Collector and Message Collector is a member of a Collector Group.

If a Data Collector or Message Collector is not a member of a Collector Group, the pre-upgrade test will define the appliance as "not eligible for patching.

To fix this error, add the Data Collector or Message Collector to a Collector Group.

Eligibility Failure

The most common reasons for eligibility failure are:

- The SL1 appliance is not licensed or the license has expired
- The SL1 appliance cannot be reached over the network
- The Data Collector has failed over
- The SL1 appliance is not configured
- The Data Collector is waiting to be returned to service
- The Data Collector is not assigned to a Collector Group

Enabled Failure

By default, all SL1 appliances are enabled for patching.

However, if you have used a command-line tool to exclude an SL1 appliance from updates, the pre-upgrade check will fail. To fix this error, include the SL1 appliance for updates.

Free Disk-Space Failure

This test checks the root partition and requires 1GB of free disk space. If the root partition does not have 1GB of free disk space, the pre-upgrade check will fail.

If the root partition does not have 1GB of free disk space, you must archive or delete files that are no longer required or add a new empty disk and resize the filesystem.

Host File Failure

This test validates the /etc/hosts file for the presence of an IPv6 entry for localhost, which is required by System Update.

If /etc/hosts does not include an IPv6 entry for localhost, the pre-upgrade test automatically adds the required entry.

Check for following in case of failure:

- The /etc/hosts file exists
- The /etc/hosts can be edited by root

Patch-Hook Ownership Failure

If the owner of the patch hook directory ((/var/lib/em7/patch_hook) is incorrect, the pre-upgrade test automatically fixes the ownership. However, if this error occurs, check for the following:

- The patch hook directory (/var/lib/em7/patch hook) does not exist
- The s-em7-core user or the s-em7-core group does not exist

RPM Database Failure

If the RPM database fails the pre-upgrade test, the RPM database is corrupted.

Follow these steps on this page to recover the RPM database:

- 1. Either go to the console of the Database Server or use SSH to access the Database Server. Log in with the credentials you defined when you installed the Database Server.
- 2. At the shell prompt, enter the following:

```
mkdir -p /tmp/rpm.bak
cp /var/lib/rpm/* /tmp/rpm.bak
rm -f /var/lib/rpm/__db*
rpm --rebuilddb -vv
rpm -q kernel
```

3. If the last command returns a value, you can delete the backup directory.

rm -Rf /tmp/rpm.bak

RPM Package Failure

If one or more RPM packages failed the pre-upgrade test, possible causes are:

- Packages are not staged, and hence some files are missing. This can be caused due to a failed staging or a timeout during staging. You can try to stage again. You can also **adjust the timeout for staging**.
- Duplicate packages

- Conflicting packages
- Unmet dependencies

Duplicate Packages:

- 1. Either go to the console of the Database Server or use SSH to access the Database Server. Log in with the credentials you defined when you installed the Database Server.
- 2. At the shell prompt, enter the following:

sudo package-cleanup --dupes

3. If there are duplicate packages:

sudo package-cleanup --cleandupes --removenewestdupes

Conflicting Packages

- 1. Look for conflicting packages in the staging log
- 2. Verify that the package is a part of SL1 ISO or patch bundle
- 3. If the package is not part of the SL1 ISO or patch bundle, uninstall the package.

Unmet dependencies

You'll have to reset the staging status of the appliance and stage it again. Contact ScienceLogic Customer Success for help in resetting the staging status.

Running the Pre-Upgrade Check for SL1 8.14 and Earlier

NOTE: These steps do not affect the performance of SL1. ScienceLogic recommends that you perform these steps at least 3 days before upgrading.

The pre-upgrade check examines the following:

All SL1 Appliances:

The pre-upgrade-checkv2.sh script checks the following on all SL1 appliances:

- Hostname and hosts file
- Uptime and average CPU load
- SL1 version
- OS versions
- MariaDB version
- Current disk utilization
- Is post update running?
- Checks yum config for configured proxy
- Check for packages installed outside of official SL1 update

- Filters out unsupported appliance types
- Gathers system status

Active Database Server:

The pre-upgrade-checkv2.sh script checks the following on all active Database Servers:

- Identifies Data Collectors that are not members of a Collector Group
- Lists all active SL1 appliances
- Lists all SL1 appliances that are disabled or ineligible for upgrade
- Checks for active staging schedules
- Check for active deployment schedules
- Are backups configured and successful?
- Checks pruner status
- Checks SIGTERMs for past 24 hours
- Compares number of tables on disk to the table definition cache
- Lists the largest 10 databases by size
- Searches for long running queries
- Shows status of used mysql connections and variables
- Lists mysql config files
- Gathers pt-diststats at 15 second interval three times
- Checks for system status wrapper bug
- Ensure that silo.log ownership is correct

All Database Servers:

The pre-upgrade-checkv2.sh script checks the following on all Database Servers:

- Checks for a minimum of 300 MB disk space on /var partition
- Checks HA/DR status
- Checks for CRM bans
- Checks for old CRM templates in HA/DR setups
- Fixes the missing SysVInit script for the MariaDB service
- Are custom SSL certs named silo default?
- Gathers output of top
- Is this SL1 Appliance memory swapping?

Administration Portal:

The pre-upgrade-checkv2.sh script checks the following on all Administration Portals:

- Checks web processes
- Are custom SSL certs named silo default?

Data Collectors and Message Collectors:

The pre-upgrade-checkv2.sh script checks the following on all active Data Collectors and Message Collectors

• Checks running Python processes

Downloading and Running the Pre-Upgrade Check

To download and run the pre-upgrade check:

- 1. Contact ScienceLogic Customer Support to get the file. Save the file to a local computer.
- 2. Use WinSCP or another file-transfer utility to copy the file pre-upgrade-check-v2.sh to the directory /home/em7admin of each SL1 appliance.
- 3. Go to the console of each SL1 appliance or open a SSH session to each SL1 appliance.
- 4. Navigate to the directory /home/em7admin.
- 5. At the shell prompt, enter the following to make the script executable:

chmod +x pre-upgrade-check-v2.sh

6. To execute the script with the default options:

```
sudo ./pre-upgrade-check-v2.sh -<appliance_type> > /tmp/preupgrade-check-v2-
`hostname -s`.`date "+%Y%m%d"` 2>&1
where:
```

appliance_type is one of the following:

- -d = Database Appliance
- -o = All-In-One
- -c = Data Collector
- -m = Message Collector
- -a = Admin Portal
- 7. To view the output from the script, view the file /tmp/pre-upgrade-check-v2-<current hostname>.<today's date>
- 8. If the output includes errors and you need help fixing them, contact ScienceLogic Customer Support to fix the errors before upgrading.
- 9. Perform these steps on each SL1 appliance.

Putting All SL1 Appliances in Maintenance Mode

NOTE: ScienceLogic recommends that you perform these steps during a maintenance window.

Immediately before deploying a software update, ScienceLogic recommends that you put all SL1 appliances in maintenance mode. This will prevent spurious error messages and events during the deployment.

To enable user maintenance mode for all the SL1 appliances in your SL1 system:

- 1. Go to the Appliance Manager page (System > Settings > Appliances). Note the list of SL1 appliances in your system.
- 2. Go to the **Device Manager** page (Registry > Devices > Device Manager):

Jul Monumer Description Product Description Description Description Description Description Description Description Descripti	Image: Control Image: Contro Image: Control Image:	ice Manager Devices Found [176]		Device				Current	Collection	Actions	SNMP	SNMP
July D-Fund Witch Struct Sectors Market Struct Active Struct Construct Active Struct Construct Witch Struct	Julio De Name Process Name Rectars MILE 20 0100 Process Name/Less VI Process VI Process Name/Less VI Process Nam/Less VI <	Device Name •	IP Address	Category	Device Class Sub-class	DID	Organization		Group	State	Credential	Version
Pin 12:00 1010 Petrovik Rovar Coso System (250) Pin 25 System Pin 12:00 103 Achive Coso SHMP 2- Star V Pin 25 Pin 12:00 103 VI 02:00 103 Ulanovm Generic (SMIP System Alvestry Clo31 Achive Coso SHMP 2- Star V Pin 25:00 Pin 12:00 103 VI 02:00 103 Ulanovm Generic (SMIP System Alvestry Clo31 Achive Coso SHMP 2- Star V Pin 25:00 0:20.0 114 10:20.0 141 Network Swetcher Coso System (Clahry 345:002.11 System Heathy Cl011 Achive Coso SHMP 2- Star V Pin 25:00 0:20.0 141 10:20.0 147 Network Swetcher Closo System (Clahry 345:002.11 System Heathy Cl011 Achive Closo SHMP 2- Star V Pin 25:00 0:20.0 141 10:20.0 147 Network Swetcher Closo SHMP 2- Star V Pin 25:00 P	Pin 1220 1040 Pin 1220 1040 Pin 1220 1050 Pin 1220							>=Health 👻				
Open 1000 Open 1000 Metwork Roader Case Systems 2501 Z System Metwork Roader Case Systems 2502 Open 2015 PH 102 00 13 V 002.00.033 Metwork Roader SMP 2 Easily 2 PH 200 P	Pin 102 00 100 Pin 102 00 100 Network Reader Caso Systems 2001 A the e Caso Systems 2001 A the e Caso Systems 2001 A the e Caso Systems 2000 A the e Caso	10-Forward	10.20.0.195	Servers	NET-SNMP FreeBSD	54	System	A Healthy	CUG1	Active	Cisco SNMPv2 - Exa	V2 mm 10 %
April 120 133 Unice Dial of System (1200/DR) U.S. System Athene (140) Achie Case SHMP2-Ess V2 PE 200 Case SHMP2-Ess V	April 12:02:01:33 Method: Routine Disc System (72:60/XR) 112 System Lifters Clob 1 Active Disc SIMP/2 - Ex VI Piol mil 10:20:01:55 Miloxon (20:01:55) Miloxon (20:01:55) Miloxon (20:01:55) Active Clas SIMP/2 - Ex VI Piol 20:01:11 10:20:01:15 Miloxon (20:01:15) Miloxon (20:01:15) Active Clas SIMP/2 - Ex VI Piol 20:01:11 10:20:01:14 Miloxon (20:01:15) Miloxon (20:01:15) Active Clas SIMP/2 - Ex VI Piol 20:01:14 Miloxon (20:01:15) Miloxon (20:01:15) System Miloxon (20:01:16) Active Clas SIMP/2 - Ex VI 20:01:14 Miloxon (20:01:15) Miloxon (20:01:15) Miloxon (20:01:15) Active Clas SIMP/2 - Ex VI 20:01:15 Miloxon (20:01:15) Miloxon (20:01:15) Miloxon (20:01:15) Active Clas SIMP/2 - Ex VI 20:01:15 Miloxon (20:01:15) Miloxon (20:01:15) Miloxon (20:01:15) Active Clas SIMP/2 - Ex VI 20:01:15 Miloxon (20:01:15) Miloxon (20:01:15) Miloxon (20:01:15) Milo		10,20,0,108	Network Router	Cisco Systems 2501	72	System	Allealthy	CUG1	Active	Cisco SNMPv2 - Exa	
Interver Optimization Optimization <td>Initial (1) Uninova Centrel (1) Statem Unitability Un</td> <td></td>	Initial (1) Uninova Centrel (1) Statem Unitability Un											
jiii 02 00 135 bit Network. Switche Caso System (Cataly M3 5060-Xu) 13 System Test (All States) Cold (All States) Achie Caso SMM 2-Ex V2 Dist (All States) 20 0 141 10 20.0114 Network. Switche Caso System (Cataly M3 5-Color Cas) 118 System Test (All States) Achie Caso SMM 2-Ex V2 Dist (All States) Dist (All States) Achie Caso SMM 2-Ex V2 Dist (All States) Dist (All St	Juli Dao 11:5 Wp1/2020.155 Merkork-System (Cablyst S306/-XL) 11 System Alteshy Data Cli01 Adve Case SMM/2-Ex V2 Vertical Case SMM/2-Ex V2 20.0 144 102.00.114 Network-Swotchic Cao System (Cablyst VS-ColveCa) 13 System Heating Cli01 Adve Case SMM/2-Ex V2 System		10.20.0.13	Unknown	Generic I SNMP	107	System	A Healthy	CUG1	Active	Cisco SNMPv2 - Exa	
200 141 120.0.141 Network.Switchet.Goo System (Latalysi VS-C000-Cu00) 18 System Featby Cl01 Achie Caoo SMM2-Esa V2 200 146 102.0.0.147 Network.Smoothen Helphale (Network.Smoothen Helph	20111 102.0111 Network.Switche:Coco.Systems (Cabyl WrS-C600-CatOS) 18 System Heating CuG1 Active Caco.SMM-2: Ex.0V (2) 20.0146 502.0146 Network.Smith Helping Network.SMI (2) System Heating CuG1 Active Caco.SMM-2: Ex.0V (2) 20.0147 102.00147 Network.Smith Helping Network.SMI (2) Network.Smith Helping Network.Smith Helping Network.Smith Helping Network			Network Switche	Cisco Systems Catalyst 3508G-XL	131	System	Allealthy	CUG1	Active	Cisco SNMPv2 - Exa	
200 148 102 00.146 Hetwork Endation Headpoin (Hetwice) 334 v 62.11 2 System Headby CliG1 Achive Case SIMPA-2-Ex V2 200 147 102 00.17 Network Endation Headpoin (Hetwice) 334 v 62.10 175 System Headby CliG1 Achive Case SIMPA-2-Ex V2 200 148 102 00.146 Hetwork Endation Headpoin (Hetwice) (SIMPA-1Ex V2 CliG1 Achive Case SIMPA-2-Ex V2 200 149 102 00.146 Hetwork Endation Headpoin (Hetwice) (SIMPA 141 System Headby CliG1 Achive Case SIMPA-2-Ex V2 200 149 102 00.146 Hetwork Endation Hedpain (Hetpain (SIMPA 141 System Headby CliG1 Achive Case SIMPA-2-Ex V2 200 147 12 20 0.175 Uninnown Generic (SIMP 141 System Headby CliG1 Achive Case SIMPA-2-Ex V2 200 147 Uninnown Generic (SIMP 141 System Headby CliG1 Achive Case SIMPA-2-Ex V2 200 147 Uninnown Generic (SIMP 41 System <td< td=""><td>200 148 19 20 149 Hervior, Branche Herbing, Honga 3349 vb 2n System Heating Cli01 Adve Exis SMIM2 - Exis V2 200 147 10 20 147 Hervior, Branche Herbing, Honga (R3108, R250, R260, R9 Figure 1001 Adve Clinis SMIM2 - Exis V2 200 148 10 20 0149 Hervior, Branche Herbing, R120, R250, R250, R2 Figure 1001 Adve Clinis SMIM2 - Exis V2 200 149 10 20 0149 Hervior, Branche Herbing, R120, R250, R250, R2 Figure 1001 Adve Clinis SMIM2 - Exis V2 200 143 10 20 0150 Unknown General (SMIP - Exis V2 System Herbing Clinis Adve Clinis SMIPA - Exis V2 200 140 10 20 0150 Unknown General (SMIP - Exis V2 Signem Herbing Clinis Adve Clinis SMIPA - Exis V2 200 140 10 20 0150 Unknown General (SMIP - Exis V2 Signem Herbing Clinis Adve Clinis SMIPA - Exis V2 200 141 10 20 0201 Unknown General (SMIP - Exis V2 Signem Herbing Clinis Adve Clinis SMIPA - Exis V2 200 030 10 20 0201</td><td></td><td>10.20.0.141</td><td>Network.Switche</td><td>clisco Systems I Catalyst WS-C6009-CatOS</td><td>118</td><td>System</td><td>Healthy</td><td>CUG1</td><td>Active</td><td>Cisco SNMPv2 - Exa</td><td></td></td<>	200 148 19 20 149 Hervior, Branche Herbing, Honga 3349 vb 2n System Heating Cli01 Adve Exis SMIM2 - Exis V2 200 147 10 20 147 Hervior, Branche Herbing, Honga (R3108, R250, R260, R9 Figure 1001 Adve Clinis SMIM2 - Exis V2 200 148 10 20 0149 Hervior, Branche Herbing, R120, R250, R250, R2 Figure 1001 Adve Clinis SMIM2 - Exis V2 200 149 10 20 0149 Hervior, Branche Herbing, R120, R250, R250, R2 Figure 1001 Adve Clinis SMIM2 - Exis V2 200 143 10 20 0150 Unknown General (SMIP - Exis V2 System Herbing Clinis Adve Clinis SMIPA - Exis V2 200 140 10 20 0150 Unknown General (SMIP - Exis V2 Signem Herbing Clinis Adve Clinis SMIPA - Exis V2 200 140 10 20 0150 Unknown General (SMIP - Exis V2 Signem Herbing Clinis Adve Clinis SMIPA - Exis V2 200 141 10 20 0201 Unknown General (SMIP - Exis V2 Signem Herbing Clinis Adve Clinis SMIPA - Exis V2 200 030 10 20 0201		10.20.0.141	Network.Switche	clisco Systems I Catalyst WS-C6009-CatOS	118	System	Healthy	CUG1	Active	Cisco SNMPv2 - Exa	
200147 12.0.0.147 Network Broadbal Helping Hotopia 330 0.10 7.5 System Heathy Clio1 Achive Caso SMM2-2-Ex V2 200148 102.0.0.440 Network Broadbal Helping HARD, REX, REX, REX, REX, REX, REX, REX, REX	200147 10.00147 Hervork Broadshar Helping Handbag 13010, 405.00 10.3 System Heating Cu01 A.dre Caco SHM2-2: Exa V2 200148 192.00149 Hervork Broadshar Helping HANDBAG, RYXA, 19 10.3 System Heating Cu01 A.dre Caco SHM2-2: Exa V2 200149 192.00149 Hervork Broadshar Helping HANDBAG, RYXA, 19 10.0 A.dre Caco SHM2-2: Exa V2 200151 192.00151 Unknown Generic [SHWP Hell System Helping Cu01 A.dre Caco SHM2-2: Exa V2 200163 Unknown Generic [SHWP Held System Helping Cu01 A.dre Caco SHM2-2: Exa V2 200175 Unknown Generic [SHWP Held System Likee Cu01 A.dre Caco SHM2-2: Exa V2 200175 Unknown Generic [SHWP Held System Likee Cu01 A.dre Caco SHM2-2: Exa V2 200176 Unknown Generic [SHWP Held System Likee Cu01 A.dre Caco SHM2-2: Exa V2 200176 Heloon System Likee Sys	20.0.146	10.20.0.146				System		CUG1	Active	Cisco SNMPv2 - Exa	V2
220 149 12 20 149 Hetwork Breades Hopping 1720-T 10 System Heatry CuG1 Achee Caso SMM2-2-Ex V2 220 151 10 20 0151 Unknown Generic SMMP 141 System Heatry CuG1 Achee Caso SMM2-2-Ex V2 220 150 10 20 0151 Unknown Generic SMMP 168 System Heatry CuG1 Achee Caso SMM2-2-Ex V2 220 157 10 20 0173 Unknown Generic SMMP 164 System Heatry CuG1 Achee Caso SMM2-2-Ex V2 220 157 10 20 0173 Unknown Generic SMMP 144 System Heatry CuG1 Achee Caso SMM2-2-Ex V2 220 157 10 20 0174 Unknown Generic SMP 141 System Table CuG1 Achee Caso SMM2-2-Ex V2 220 157 10 20 0151 Unknown Generic SMP 158 System Table CuG1 Achee Caso SMM2-2-Ex V2 220 150 Unknown Generic SMP 158 System Table CuG1 Achee Caso SMM2-2-Ex V2 220 151 Unknown Generic SMP 53 System Hamy CuG1 Achee Caso SMM2-2-Ex V2 220 52 <	1200149 1200149 Hevords Broadse Hepping 1720-T 112 System Healing Clinit Active Cace SHM2-2: Eavy 2 200151 10200.151 Uknown Generic [SMP H4 System Healing Clinit Active Cace SHM2-2: Eavy 2 200163 10200.157 Uknown Generic [SMP H4 System Healing Clinit Active Cace SHM2-2: Eavy 2 200163 10200.175 Uknown Generic [SMP H4 System Healing Clinit Active Cace SHM2-2: Eavy 2 200175 Uknown Generic [SMP H4 System Harrow Clinit	.20.0.147	10.20.0.147			175	System		CUG1	Active	Cisco SNMPv2 - Exa	V2
200151 10200151 Unknown General SMMP 141 System 1930/0 Achre Caso SMM2-2-bit V2 200160 1220.016 Unknown General SMMP 165 System 1640/0 Cloit Achre Caso SMM2-2-bit V2 200163 1220.0176 Unknown General SMMP 44 System 1640/0 Cloit Achre Caso SMM2-2-bit V2 200175 1220.0176 Unknown General SMMP 44 System 1Mes Cloit Achre Caso SMM2-2-bit V2 200176 1220.0176 Unknown General SMMP 54 System 1Mes Cloit Achre Caso SMM2-2-bit V2 200176 Unknown General SMMP 54 System 1Mes Cloit Achre Caso SMM2-2-bit V2 200171 1020.0170 Unknown General SMMP 45 System 1Mes Cloit Achre Caso SMM2-2-bit V2 200203 Unknown General SMMP 45 System feathy Cloit <td>200151 1200151 Unknown Generic [SMIP 141 System Mathy C001 Active Disc SMIP/2 - Ex V2 200160 102.0.19 Unknown Generic [SMIP 164 System Heating C001 Active Clos SMIP/2 - Ex V2 200163 102.0.19 Unknown Generic [SMIP 144 System Heating Cl01 Active Clos SMIP/2 - Ex V2 200175 102.0.175 Unknown Generic [SMIP 44 System Jiker Cl01 Active Clos SMIP/2 - Ex V2 200176 Unknown Generic [SMIP 44 System Jiker Cl01 Active Clos SMIP/2 - Ex V2 200170 12.0.0.161 Otknown Generic [SMIP 55 System Jiker Cl01 Active Clos SMIP/2 - Ex V2 20.0.101 42.0.0.01 Motion Generic [SMIP 55 System Jiker Cl03 Active Clos SMIP/2 - Ex V2 20.0.20 12.0.0.2.0 Unknown Generic [SMIP Syst</td> <td>.20.0.148</td> <td>10.20.0.148</td> <td>Network Broadba</td> <td>Netopia Netopia (R3100, R45xx, R7xx0, R9</td> <td>163</td> <td>System</td> <td>Heathy</td> <td>CUG1</td> <td>Active</td> <td>Cisco SNMPv2 - Exa</td> <td>V2</td>	200151 1200151 Unknown Generic [SMIP 141 System Mathy C001 Active Disc SMIP/2 - Ex V2 200160 102.0.19 Unknown Generic [SMIP 164 System Heating C001 Active Clos SMIP/2 - Ex V2 200163 102.0.19 Unknown Generic [SMIP 144 System Heating Cl01 Active Clos SMIP/2 - Ex V2 200175 102.0.175 Unknown Generic [SMIP 44 System Jiker Cl01 Active Clos SMIP/2 - Ex V2 200176 Unknown Generic [SMIP 44 System Jiker Cl01 Active Clos SMIP/2 - Ex V2 200170 12.0.0.161 Otknown Generic [SMIP 55 System Jiker Cl01 Active Clos SMIP/2 - Ex V2 20.0.101 42.0.0.01 Motion Generic [SMIP 55 System Jiker Cl03 Active Clos SMIP/2 - Ex V2 20.0.20 12.0.0.2.0 Unknown Generic [SMIP Syst	.20.0.148	10.20.0.148	Network Broadba	Netopia Netopia (R3100, R45xx, R7xx0, R9	163	System	Heathy	CUG1	Active	Cisco SNMPv2 - Exa	V2
200151 1000000 Generg (SMUP 141 System Heatry CliG1 Achie Case SMU2-2es V2 200169 1220.016 Uninown Generg (SMUP 165 System Heatry CliG1 Achie Case SMU2-2es V2 200175 1220.0173 Uninown Generg (SMUP 44 System Heatry CliG1 Achie Case SMU2-2es V2 200175 1020.0173 Uninown Generg (SMUP 44 System Flastry CliG1 Achie Case SMU2-2es V2 200176 1020.0173 Uninown Generg (SMUP 55 System Lflastry CliG1 Achie Case SMU2-2es V2 200176 Uninown Generg (SMUP 55 System Lflastry CliG1 Achie Case SMU2-2es V2 200171 1020.021 Uninown Generg (SMUP 45 System Lflastry CliG1 Achie Case SMU2-2es V2 20020 CliG20.020 Uninown Generg (SMUP 53 System Feathy <td>20011 10.20.0151 Unknown Generic [SMUP 141 System Heating Cli01 Active Easing SMMP2-Easing 2 200160 102.0.150 Unknown Generic [SMUP 164 System Heating Cli01 Active Clics SMMP2-Easing 2 200175 102.0.175 Unknown Generic [SMUP 44 System Heating Cli01 Active Clics SMMP2-Easing 2 200175 102.0.175 Unknown Generic [SMUP 44 System Liner Cli01 Active Clics SMMP2-Easing 2 200176 102.0.175 Unknown Generic [SMUP 56 System Liner Cli01 Active Clics SMMP2-Easing 2 200176 102.0.176 Unknown Generic [SMUP 56 System Liner Cli01 Active Clics SMMP2-Easing 2 200170 102.0.015 Unknown Generic [SMUP 56 System Heating Cli01 Active Clics SMMP2-Easing 2 200.200 Texphony Unknown</td> <td>20.0.149</td> <td>10.20.0.149</td> <td>Network Broadba</td> <td>r Netopia I R7200-T</td> <td>162</td> <td>System</td> <td>Healthy</td> <td>CUG1</td> <td>Active</td> <td>Cisco SNMPv2 - Exa</td> <td>V2</td>	20011 10.20.0151 Unknown Generic [SMUP 141 System Heating Cli01 Active Easing SMMP2-Easing 2 200160 102.0.150 Unknown Generic [SMUP 164 System Heating Cli01 Active Clics SMMP2-Easing 2 200175 102.0.175 Unknown Generic [SMUP 44 System Heating Cli01 Active Clics SMMP2-Easing 2 200175 102.0.175 Unknown Generic [SMUP 44 System Liner Cli01 Active Clics SMMP2-Easing 2 200176 102.0.175 Unknown Generic [SMUP 56 System Liner Cli01 Active Clics SMMP2-Easing 2 200176 102.0.176 Unknown Generic [SMUP 56 System Liner Cli01 Active Clics SMMP2-Easing 2 200170 102.0.015 Unknown Generic [SMUP 56 System Heating Cli01 Active Clics SMMP2-Easing 2 200.200 Texphony Unknown	20.0.149	10.20.0.149	Network Broadba	r Netopia I R7200-T	162	System	Healthy	CUG1	Active	Cisco SNMPv2 - Exa	V2
20160 10.20.163 Uninovin Generic (SMP 165 System Featby CliG1 Active Case SMPA-2-Ex V2 20163 10.20.013 Uninovin Generic (SMP 164 System Featby CliG1 Active Case SMPA-2-Ex V2 20.0175 Uninovin Generic (SMP 44 System Featby CliG1 Active Case SMPA-2-Ex V2 20.0176 Uninovin Generic (SMP 44 System Life CliG1 Active Case SMPA-2-Ex V2 20.0176 Uninovin Generic (SMP 55 System Life CliG1 Active Case SMPA-2-Ex V2 20.011 10.20.019 Uninovin Generic (SMP 55 System Featby CliG1 Active Case SMPA-2-Ex V2 20.021 10.20.031 Uninovin Generic (SMP 53 System Featby CliG1 Active Case SMPA-2-Ex V2 20.023 Uninovin Generic (SMP 53 System Featby CliG1 Ac	20169 10.0.0.01 Outcom Generic (SMP 164 System Meany Clio1 A.dre Cace SMM/2-2: Eavy2 20163 10.20.01% Unknown Generic (SMP 164 System Meany Clio1 A.dre Cace SMM/2-2: Eavy2 20.01% 10.20.01% Unknown Generic (SMP 14 System Meany Clio1 A.dre Cace SMM/2-2: Eavy2 20.01% 10.20.01% Unknown Kenica Caperation (DM 41 System Meany Clio1 A.dre Cace SMM/2-2: Eavy2 20.01% 10.20.01% Unknown Kenica (SMW/2-Eavy2 System Meany Clio1 A.dre Cace SMM/2-2: Eavy2 20.011 10.20.01% Unknown Generic (SMW System Meany Clio1 A.dre Cace SMM/2-2: Eavy2 20.02030 10.20.02% Unknown Generic (SMW System Meany Clio1 A.dre Cace SMM/2-2: Eavy2 20.02030 10.20.02% Unknown Generic (SMW System Meany Clio1 A.dre Cace SMM/2-2: Eavy2 20.02% Unknow	.20.0.151	10.20.0.151			141	System		CUG1	Active	Cisco SNMPv2 - Exa	V2
220.163 192.00.163 Undnown Generic (SMIP H4 System Heatry Cloid Active Case SMIPA2-Ex V2 200.175 102.00.175 Undnown Generic (SMIP 44 System LMane Cloid Active Case SMIPA2-Ex V2 200.176 102.00.178 Undnown Generic (SMIP 55 System LMane Cloid Active Case SMIPA2-Ex V2 200.176 102.00.178 Undnown Generic (SMIPA 56 System LMane Cloid Active Case SMIPA2-Ex V2 200.171 102.00.201 Undnown Generic (SMIPA 54 System LMane Cloid Active Case SMIPA2-Ex V2 200.011 102.00.201 Undnown Generic (SMIPA 53 System Heatty Cloid Active Case SMIPA2-Ex V2 200.028 Undnown Generic (SMIPA 53 System Heatty Cloid Active Case SMIPA2-Ex V2 200.028 Undnown Generc (SMIPA 53 Syst	2020 163 1920 0163 Unknown Demici [SMIP 194 System Heating Clin3 Adve Design SMIP/2 - Exity /2 200 176 1020 0.175 Unknown Geneci [SMIP/2 - Exity /2] Clin3 Adve <			Unknown						Active		
2020 175 Unknown Generic (SMP 44 System Failbard Cubit Active Caso SMPA-2-Ex V2 2020 176 10200 176 Unknown Keinic Cognostion (DEU 41 System Fuller Cubit Active Caso SMPA-2-Ex V2 2020 176 10200 176 Unknown Generic (SMP 58 System Fuller Cubit Active Caso SMPA-2-Ex V2 2020 176 Unknown Generic (SMP 57 System Fuller Cubit Active Caso SMPA-2-Ex V2 2020 171 10200 201 Unknown Generic (SMP 52 System Failty Cubit Active Caso SMPA-2-Ex V2 2020 201 10200 203 Telephony Cubit Inframe Sa System Failty Cubit Active Caso SMPA-2-Ex V2 2020 201 10200 203 Telephony Cubit Inframe Sa System Faility Cubit Active Caso SMPA-2-Ex V2 2020 201 10200 203 Telephony Gune Cubit Active Caso	2020 175 Unknown Cancer (SMP 44 System Heinity CUG1 A.dre Cacc SMPA2-Exa V2 2020 176 1920 176 Unknown Gene (SMPA) Edit System J.Mase CuG3 A.dre Cacc SMPA2-Exa V2 2020 176 1920 0190 Unknown Gene (SMPA) Edit System J.Mase CuG3 A.dre Cacc SMPA2-Exa V2 2020 191 1920 0190 Unknown Generic (SMPA FS System Hastr CUG1 A.dre Cacc SMPA2-Exa V2 2020 191 1920 0201 Unknown Generic (SMPA FS System Hastr CUG1 A.dre Cacc SMPA2-Exa V2 2020 2020 1920 0203 Heatory CUG1 A.dre Cacc SMPA2-Exa V2 2020 2020 1920 0203 Teleptory Generic (SMPA FS System Heatory CUG1 A.dre Cacc SMPA2-Exa V2 2020 2021 1920 0203 Teleptory Generic (SMPA FS System Heatory CUG1 A.dre Cacc SMPA2-Exa V2 2020 2021 1920 0203 Teleptory Generic (SMPA FS System Heatory CUG1 A.dre Cacc SMPA2-Exa V2 2020 201 Teleptory	20.0.163	10.20.0.163	Unknown	Generic I SNMP	164	System	Healthy	CUG1	Active	Cisco SNMPv2 - Exa	V2
220.0176 Undown Konics Corporation (DEM) 41 System Undown Active Case SMM2-2-Ex V2 200.0160 102.00.019 Undown Generic SIMP 65 System Undown Cubic SimP2-Ex V2 200.011 102.00.019 Undown Generic SIMP2 57 System Undown Cubic SimP2-Ex V2 200.011 102.00.020 Undown Generic SIMP2 58 System Teatry Cubic Active Case SIMP2-2-Ex V2 200.020 102.00.020 Undown Generic SIMP2 System Teatry Cubic Active Case SIMP2-2-Ex V2 200.020 102.00.020 Undown Generic SIMP2 System Teatry Cubic SIMP2-2-Ex V2 200.020 102.00.020 Undown Generic SIMP2 System Teatry Cubic SIMP2-2-Ex V2 200.021 Undown Generic SIMP2 System Teatry Cubic SIMP2-2-Ex V2 200.023 102.00.021 Undown Generic SIMP2 System Teatry Cubic Active Case SIMP2-2-Ex V2 <	220.176 120.0176 Unknown Rome capparation (PDM 41 System Minor GUG1 Adve Casc SHMP2-Ex V2 200.196 102.0.190 Unknown Generic (SMP2 56 System J Minor CUG1 Adve Casc SHMP2-Ex V2 200.191 102.0.0.90 Unknown Generic (SMP2 57 System J Minor CUG1 Adve Casc SHMP2-Ex V2 200.191 102.0.0.20 Unknown Generic (SMP2 54 System Heathy CUG1 Adve Casc SHMP2-Ex V2 200.203 162.0.0.20 Unknown Generic (SMP4 54 System Heathy CUG1 Adve Casc SHMP2-Ex V2 200.203 162.0.0.25 Unknown Generic (SMP4 53 System Heathy CUG1 Adve Casc SHMP2-Ex V2 200.203 162.0.0.25 Unknown Generic (SMP4 53 System Heathy CUG1 Adve Casc SHMP2-Ex V2 200.51 102.0.59 Unknown Generic (SMP											
280.960 12.20.919 Unknown General (SMMP 56 System Tuber CuG1 Achie Case SMMP-2-Ex V2 20.0191 0120.0191 0160.0716 Ferry S22-XM 57 System Tuber CuG1 Achie Case SMMP-2-Ex V2 20.0191 1020.0191 Unknown Generic (SMMP 52 System Featry CUG1 Achie Case SMMP-2-Ex V2 20.0202 1020.0201 Unknown Generic (SMMP 52 System Featry CUG1 Achie Case SMMP-2-Ex V2 20.0202 1020.0201 Telephony Gutham Featry System Featry CUG1 Achie Case SMMP-2-Ex V2 20.0202 1020.0201 Telephony Gutham Featry System Featry CUG1 Achie Case SMMP-2-Ex V2 20.0202 Unknown Generic (SMMP 13 System Featry CUG1 Achie Case SMMP-2-Ex V2 20.021 Unknown Generic (SMP 14 System Featt	200.1960 112.00.1960 Unknown Generic JSMP 56 System 11Meer CUG1 Active Cace SMM2-2: Sav /2 200.011 102.00.191 Unknown Generic JSMP 54 System 14Meer Cace SMM2-2: Sav /2 200.020 110.020.011 Unknown Generic JSMP 52 System 14eby CUG1 Active Cace SMM2-2: Sav /2 200.020 110.020.011 Unknown Generic JSMP 52 System 14eby CUG1 Active Cace SMM2-2: Sav /2 200.020 Telephory Outhun Tenor 53 System 14eby CUG1 Active Cace SMM2-2: Sav /2 200.020 Telephory Outhun Tenor 53 System 14eby CuG1 Active Cace SMM2-2: Sav /2 200.022 Unknown Generic JSMP 118 System 14eby CuG1 Active Cace SMM2-2: Sav /2 200.023 112.00.023 Unknown Generic JSMP 15 System 14eby CuG1 Active Cace SMM2-2: Sav /2 200.024 Unknown Generic JSMP 15 System 14eby CuG1 Active Cace SMM2-2: Sav /2 200.025 Unknown Generic JSMP<			Unknown						Active	Cisco SNMPv2 - Exa	V2
220.0191 D/Dice Printer Konica Minota Hency S22C-MM 97 System Using Clight Active Case SMMPA-2-bit V2 20.02101 10.20.0210 Unknown Generic SMMP 43 System Heatby Clight Active Case SMMPA-2-bit V2 20.0200 10.20.0208 Unknown Generic SMMP 52 System Heatby Clight Active Case SMMPA-2-bit V2 20.0209 10.20.0208 Unknown Generic SMMP 53 System Heatby Clight Active Case SMMPA-2-bit V2 20.0209 10.20.020 Unknown Generic SMMP 138 System Heatby Clight Active Case SMMPA-2-bit V2 20.020 Case SMMPA-2-bit V2 System Heatby Clight Active Case SMMPA-2-bit V2 20.023 Unknown Generic SMMP 13 System Heatby Clight Active Case SMMPA-2-bit V2 20.023 Unknown Generic SMMP 3 System Heatby Clight	220.011 102.020191 Urbics introls Fary/S2 222-KM 25 System 1More CUG1 Active Caco SMM2-2: Exa V2 200.011 102.0201 Urbicsom Generic (SMP 48 System Heating CUG1 Active Caco SMM2-2: Exa V2 200.013 102.02024 Urbicsom Generic (SMP 53 System Heating CUG1 Active Caco SMM2-2: Exa V2 200.013 102.02027 Telephory 100 Active Caco SMM2-2: Exa V2 200.026 112.02029 Telephory 135 System Heating CUG1 Active Caco SMM2-2: Exa V2 200.026 112.0029 Telephory 0.01 Active Caco SMM2-2: Exa V2 200.026 112.0029 Urbicsom Generic (SMP 11 System Heating CUG1 Active Caco SMM2-2: Exa V2 200.026 Urbicsom Generic (SMP 13 System Heating CUG1 Active Caco SMM2-2: Exa V2 200.026 Urbicsom Generic (SMP 3 System Heating CUG1 Active Caco SMM2-2: Exa V2 200.041 12.002.051 Urbicsom Generic (SMP 3 System Heating CUG1 Activ											
2020201 102.00.201 Unknown Generic (SMP 48 System Featry CUG1 Active Caso SMPA-2-Ex V2 2020200 102.00.200 Telphony Quitum) Teor 53 System Featry CUG1 Active Caso SMPA-2-Ex V2 20.0200 102.00.200 Telphony Quitum) Teor 53 System Featry CUG1 Active Caso SMPA-2-Ex V2 20.0202 Unknown Generic (SMP 138 System Featry CUG1 Active Caso SMPA-2-Ex V2 20.0202 Unknown Generic (SMP 138 System Featry CUG1 Active Caso SMPA-2-Ex V2 20.0202 Unknown Generic (SMP 17 System Featry CUG1 Active Caso SMPA-2-Ex V2 20.0202 Unknown Generic (SMP 17 System Featry CUG1 Active Caso SMPA-2-Ex V2 20.021 Unknown Generic (SMP 14 System Featry CUG1 Active Caso SMPA-2-Ex V2 20.031 Unknown Generic (SMP 14 System Featry CUG1 Active Caso SMPA-2-Ex V2 20.041 Unknown Generic (SMP 14	202021 11020201 Unknown Generic [SMMP 45 System Heathy CUG1 Adve Caco SMMP2-Exa V2 202020 11220202 Telephony Odernic [SMMP 52 System Heathy CUG1 Adve Caco SMMP2-Exa V2 202020 11220202 Telephony Odernic [SMMP 1128 System Heathy CUG1 Adve Caco SMMP2-Exa V2 202022 Unknown Generic [SMMP 1138 System Heathy CUG1 Adve Caco SMMP2-Exa V2 202023 Unknown Generic [SMMP 113 System Heathy CUG1 Adve Caco SMMP2-Exa V2 202024 Unknown Generic [SMMP 115 System Heathy CUG1 Adve Caco SMMP2-Exa V2 202035 Unknown Generic [SMMP 115 System Heathy CUG1 Adve Caco SMMP2-Exa V2 202036 Unknown Generic [SMMP 112 System Heathy CUG1 Adve Caco SMMP2-Exa V2 202037 Tel20258 Unknown Generic [SMMP 145 System Heathy CUG1 Adve Caco SMMP2-Exa V2 202036 Unknown Generic [SMMP 145 <td></td>											
220.036 102.00.038 Unknown Opency (SMMP 52 System Heatry Culo1 Active Caso SMMP2-Ex V2 20.0209 120.0.020 Unknown Generic (SMMP 53 System Heatry Culo1 Active Caso SMMP2-Ex V2 20.0209 102.0.020 Unknown Generic (SMMP 138 System Heatry Culo1 Active Caso SMMP2-Ex V2 20.026 102.0.020 Unknown Generic (SMP 171 System Heatry Culo1 Active Caso SMMP2-Ex V2 20.026 102.0.020 Unknown Generic (SMP 171 System Heatry Culo1 Active Caso SMP2-Ex V2 20.059 Unknown Generic (SMP 3 System Heatry Culo1 Active Caso SMP2-Ex V2 20.051 Unknown Generic (SMP 3 System Heatry Culo1 Active Caso SMP2-Ex V2 20.051 Unknown Generic (SMP 8 System Heatry Culo1 <td>20.2030 19.20.2036 Unknown Generic [SMMP 52 System Mathy Cli01 Active Caco SMMP.2-Ext V2 20.2030 10.20.0230 Unknown Generic [SMMP 13.8 System Mathy Cli01 Active Caco SMMP.2-Ext V2 20.2030 10.20.0230 Unknown Generic [SMMP 13.8 System Mathy Cli01 Active Caco SMMP.2-Ext V2 20.0230 Unknown Generic [SMMP 17.1 System Mathy Cli01 Active Caco SMMP.2-Ext V2 20.0230 Minitown Generic [SMMP 17.1 System Mathy Cli01 Active Caco SMMP.2-Ext V2 20.0230 Minitown Active Caco SMMP.2-Ext V2 System Mathy Cli01 Active Caco SMMP.2-Ext V2 20.0230 Unknown Generic [SMMP 3 System Heathy Cli01 Active Caco SMMP.2-Ext V2 20.031 Mil20.051 Unknown Generic [SMMP 3 System Heathy Cli01 Active Clac SMMP.2-Ext V2 20.041 Mil20.051 Unknown Generic [SMMP 84 System Heathy Cli01 Active 20.041 Mil20.051</td> <td></td>	20.2030 19.20.2036 Unknown Generic [SMMP 52 System Mathy Cli01 Active Caco SMMP.2-Ext V2 20.2030 10.20.0230 Unknown Generic [SMMP 13.8 System Mathy Cli01 Active Caco SMMP.2-Ext V2 20.2030 10.20.0230 Unknown Generic [SMMP 13.8 System Mathy Cli01 Active Caco SMMP.2-Ext V2 20.0230 Unknown Generic [SMMP 17.1 System Mathy Cli01 Active Caco SMMP.2-Ext V2 20.0230 Minitown Generic [SMMP 17.1 System Mathy Cli01 Active Caco SMMP.2-Ext V2 20.0230 Minitown Active Caco SMMP.2-Ext V2 System Mathy Cli01 Active Caco SMMP.2-Ext V2 20.0230 Unknown Generic [SMMP 3 System Heathy Cli01 Active Caco SMMP.2-Ext V2 20.031 Mil20.051 Unknown Generic [SMMP 3 System Heathy Cli01 Active Clac SMMP.2-Ext V2 20.041 Mil20.051 Unknown Generic [SMMP 84 System Heathy Cli01 Active 20.041 Mil20.051											
20.039 10.20.039 Tephony Outhum Tenar 5.3 System Heathy CuG1 Active Caso SMIPA-2-ba V2 20.020 10.20.022 Ukinown Generic SMIP 38 System Heathy CuG1 Active Caso SMIPA-2-ba V2 20.052 10.20.022 Ukinown Generic SMIP 171 System Heathy CuG1 Active Caso SMIPA-2-ba V2 20.05 10.20.05.2 Ukinown Generic SMIP 3 System Heathy CuG1 Active Caso SMIPA-2-ba V2 20.05.5 10.20.05.9 Ukinown Generic SMIP 3 System Heathy CuG1 Active Caso SMIPA-2-ba V2 20.05.1 10.20.05.1 Ukinown Generic SMIP 3 System Heathy CuG1 Active Caso SMIPA-2-ba V2 20.06.1 Ukinown Generic SMIP 3 System Heathy CuG1 Active Caso SMIPA-2-ba V2 20.06.1 Ukinown Generic SMIP 84 System <t< td=""><td>202030 1020239 Tesphony Outhun Timor 53 System Heathy CUG1 A.dve Cisc SHMP2-C:sA/2 202022 Ukikowi Generic [SHMP 135 System Heathy CUG1 A.dve Cisc SHMP2-C:sA/2 202022 Ukikowi Generic [SHMP 135 System Heathy CUG1 A.dve Cisc SHMP2-C:sA/2 202023 Ukikowi Generic [SHMP 13 System Heathy CUG1 A.dve Cisc SHMP2-C:sA/2 20203 Ukikowi Generic [SHMP S System Heathy CUG1 A.dve Cisc SHMP2-C:sA/2 20205 Ukikowi Generic [SHMP System Heathy CUG1 A.dve Cisc SHMP2-C:sA/2 20205 Ukikowi Generic [SHMP 3 System Heathy CUG1 A.dve Cisc SHMP2-C:sA/2 20205 Ukikowi Generic [SHMP 142 System Heathy CUG1 A.dve Cisc SHMP2-C:sA/2 20205 Ukikowi Generic [SHMP 142 System Heathy CUG1 A.dve Cisc SHMP2-C:sA/2 20205 Ukikowi Generic [SHMP 142 System Heathy CUG1 A.dve Cis</td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td></t<>	202030 1020239 Tesphony Outhun Timor 53 System Heathy CUG1 A.dve Cisc SHMP2-C:sA/2 202022 Ukikowi Generic [SHMP 135 System Heathy CUG1 A.dve Cisc SHMP2-C:sA/2 202022 Ukikowi Generic [SHMP 135 System Heathy CUG1 A.dve Cisc SHMP2-C:sA/2 202023 Ukikowi Generic [SHMP 13 System Heathy CUG1 A.dve Cisc SHMP2-C:sA/2 20203 Ukikowi Generic [SHMP S System Heathy CUG1 A.dve Cisc SHMP2-C:sA/2 20205 Ukikowi Generic [SHMP System Heathy CUG1 A.dve Cisc SHMP2-C:sA/2 20205 Ukikowi Generic [SHMP 3 System Heathy CUG1 A.dve Cisc SHMP2-C:sA/2 20205 Ukikowi Generic [SHMP 142 System Heathy CUG1 A.dve Cisc SHMP2-C:sA/2 20205 Ukikowi Generic [SHMP 142 System Heathy CUG1 A.dve Cisc SHMP2-C:sA/2 20205 Ukikowi Generic [SHMP 142 System Heathy CUG1 A.dve Cis											
220.222 Usanown Generic (SMMP 138 System Teamy Culoi Active Caso SMM2-2-Ex V2 220.25 200.25 2	20.022 10.00 522 Unknown Generic [SMMP 138 System Methy Cli01 Active Caso SMMP 2: Cas V2 20.05 Unknown Generic [SMMP 11 System Heathy Cli01 Active Caso SMMP 2: Cas V2 20.05 10.20 0.5% Unknown Active Caso SMMP 2: Cas V2 Cli01 Active Caso SMMP 2: Cas V2 20.05 10.20 0.5% Unknown Active Caso SMMP 2: Cas V2 Cli01 Active Caso SMMP 2: Cas V2 20.05 10.20 0.5% Unknown Generic [SMMP 3 System Heathy Cli01 Active Caso SMMP 2: Cas V2 20.05.01 10.20 0.5% Unknown Generic [SMMP 3 System Heathy Cli01 Active Caso SMMP 2: Cas V2 20.06.11 10.20 0.5% Unknown Generic [SMMP 84 System Heathy Cli01 Active Caso SMMP 2: Cas V2 20.06.11 Holzon SMMP Cli02 Active Caso SMMP 2: Cas V2 Main Active Caso SMMP 2: Cas V2 20.06.11 Holzon SMMP Cli02 Active Caso SMMP 2: Cas V2 Main Active Caso SMMP 2: Cas V2 20.06.11 Holzon SMMP 2: Cas V2 Main Active Cas Cas V2 Main Active Cas Cas											
20.026 10.20.036 Undnown Generic [SMP 171 System Heathy CUG1 Achre Cao SMPA-2-Ex V2 20.052 10.20.059 Undnown ASRC* Compared Copin (DEI 5 System Heathy CUG1 Achre Cao SMPA-2-Ex V2 20.053 10.20.059 Undnown Generic [SMP 3 System Heathy CUG1 Achre Cao SMPA-2-Ex V2 20.053 10.20.061 Undnown Generic [SMP 84 System Heathy CUG1 Achre 20.054 Undnown Generic [SMP 84 System Heathy CUG1 Achre 20.054 Undnown Generic [SMP 84 System Heathy CUG1 Achre 20.053 10.20.061 Undnown Generic [SMP 84 System Heathy CUG1 Achre 20.054 Undnown Generic [SMP 84 System Heathy CUG1 Achre 20.057 Undnown Generic [SMP 84 System Heathy CUG1 Achre 20.057 Undnown Generic [SMP 84 System Heathy CUG1 Achre 20.058 Undnown Generic [SMP	2005 102005 Unknown Genci (SMMP 11 System Heating Cl01 Active Cloc SMMP2-Exa V2 20052 Ukknown ASBYC (Compare Cegn (DBM 5 System Heating Cl01 Active Cloc SMMP2-Exa V2 20053 1020059 Ukknown Gencir (SMMP 3 System Heating Cl01 Active Cloc SMMP2-Exa V2 20061 1020059 Ukknown Gencir (SMMP 84 System Heating Cl01 Active Cloc SMMP2-Exa V2 20061 1020059 Ukknown Gencir (SMMP 84 System Heating Cl03 Active Cloc SMMP2-Exa V2 20061 1020051 Ukknown Gencir (SMMP 84 System Heating Cl03 Active Cloc SMMP2-Exa V2 20061 1020051 Ukknown Gencir (SMMP 84 System Heating Cl03 Active Cloc SMMP2-Exa V2 20061 Ukknown Gencir (SMMP 84 System Heating Cl03 Active Cloc SMMP2-Exa V2 20061 Ukknown Gencir (SMMP 84 System Heating Cl03 Active Cloc SMMP2-Exa V2 20061 Ukknown											
20059 1020059 Uninown ARKY Compater Cop. (DEM 5 System Featby CUG1 Active Caso SMM2-2-Ex V2 20059 1020059 Uninown Generic (SMMP 3 System Featby CUG1 Active Caso SMM2-2-Ex V2 20051 1020059 Uninown Generic (SMMP 84 System Featby CUG1 Active Caso SMM2-2-Ex V2 20051 1020059 Uninown Generic (SMMP 84 System Featby CUG1 Active Caso SMM2-2-Ex V2 20051 1020059 Uninown Generic (SMMP 84 System Featby CUG1 Active Caso SMM2-2-Ex V2 20051 1020059 Uninown Generic (SMMP 84 System Featby CUG1 Active 20052 Active Caso SMM2-2-Ex V2 Active Caso SMM2-2-Ex V2 Active Caso SMM2-2-Ex V2 20053 Uninown Generic (SMMP 84 System Featby CUG1 Active Caso SMM2-2-Ex V2 20054 Caso SMM2-2-Ex V2 Active Caso SMM2-2-Ex V2 Active Caso SMM2-2-Ex V2 20055 Caso SMM2-2-Ex V2 Caso SMM2-2-Ex V2 Caso SMM2-2-Ex V2 Caso SMM2-2	20059 1020059 Ukinown ASEV Computer Corp. 10EM 5 System Mathy CUG1 Active Caso SMM2-2: Exa V2 20059 1020059 Ukinown Generic SMMP 3 System Heating CUG1 Active Caso SMM2-2: Exa V2 20063 1020059 Ukinown Generic SMMP 84 System Heating CUG1 Active Caso SMM2-2: Exa V2 20063 1020059 Ukinown Generic SMMP 84 System Heating CUG1 Active Caso SMM2-2: Exa V2 20063 1020059 Ukinown Generic SMMP 84 System Heating CUG1 Active Caso SMM2-2: Exa V2 20063 1020059 Ukinown Generic SMMP 84 System Heating CUG1 Active Caso SMM2-2: Exa V2 20063 1020059 Ukinown Generic SMMP 84 System Heating CUG1 Active Caso SMM2-2: Exa V2 20063 1020059 Sector Label Active Caso SMM2-2: Exa V2 Label Active Caso											
20059 10.20.09 Unknown Generic [SMP 3 System Heatry CUG1 Active Caoc SMPA-2-Ex V2 20.063 10.20.061 Unknown Generic [SMP 84 System Heatry CUG1 Active Caoc SMPA-2-Ex V2 20.063 10.20.061 Unknown Generic [SMP 84 System Heatry CUG1 Active Caoc SMPA-2-Ex V2 20.07 Unknown Generic [SMP 84 System Heatry CUG1 Active Caoc SMPA-2-Ex V2 20.07 Unknown Generic [SMP 84 System Heatry CUG1 Active Caoc SMPA-2-Ex V2 20.07 Unknown Generic [SMP 84 System Heatry CUG1 Active 20.07 Unknown Generic [SMP 84 System Heatry CUG1 Active 20.07 Unknown Generic [SMP 84 System Heatry CUG1 Active 20.07 Unknown Generic [SMP 84 System Heatry CUG1 Active 20.07 Unknown Generic [SMP 10 Active Loc Active Loc Active 20.07 Unknown Generic [SMP <td< td=""><td>20059 1020059 Unknown Generic SMMP 3 System Heathy Clic1 Active Cloco SMM2-C-Exe V2 20061 1020051 Unknown Generic SMMP 84 System Heathy Clic1 Active Cloco SMM2-C-Exe V2 20061 1020051 Unknown Generic SMMP 84 System Heathy Clic1 Active Clic20051 Active 20062 Clic20051 Unknown Generic SMMP 84 System Heathy Clic1 Active Clic20051 20063 Unknown Generic SMMP 84 System Heathy Clic21 Active Clic20051 20064 Lic20051 Lic20051 Lic20051 Lic20051 Lic20051 Lic20051 20070 Lic20051 Lic20051 Lic20</td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td></td<>	20059 1020059 Unknown Generic SMMP 3 System Heathy Clic1 Active Cloco SMM2-C-Exe V2 20061 1020051 Unknown Generic SMMP 84 System Heathy Clic1 Active Cloco SMM2-C-Exe V2 20061 1020051 Unknown Generic SMMP 84 System Heathy Clic1 Active Clic20051 Active 20062 Clic20051 Unknown Generic SMMP 84 System Heathy Clic1 Active Clic20051 20063 Unknown Generic SMMP 84 System Heathy Clic21 Active Clic20051 20064 Lic20051 Lic20051 Lic20051 Lic20051 Lic20051 Lic20051 20070 Lic20051 Lic20051 Lic20											
20063 10220.061 Uninown Genero; SMMP 84 System Hastby CU01 Active Service Hart-2-barks Administration	20.063 Version 200.051 Unknown Generic (SMMP B4 System Versity CUC) Active Exercise Control Administration Administration Control (UC) Active Cont											
Administration: A LDELTE Selected Davides LMORTY by Tempile LLLAR Device Logs E LCRAR Device Logs E LCRAR Device Logs E LORDULE Maintenance Compo Lobabid Comange Understance Mode: LDashed LDashed LDashed LDashed LDashed Conce Celection	Characteristics Constraints LMDRT: Severation LMDRT: Severation LCEAR Devices Logs LCEAR Devices Logs LCEAR Devices Logs LCEAR Devices Logs LCEAR Devices Logs LCEAR Devices Logs LCEAR Devices Logs Constraints Constraints Constraints Constraints Constraints Constraints Constraints LCEAR LEnabled Constraints LCEAR LEnabled Constraints Constraints LCEAR LCEAR Constraints Constraints LCEAR LCEAR Constraints LCEAR LCEA											
	LSystem Align SIMMP Read Credential:									a	Iministration: DELETE Selected Devik MODIFY By Template CLEAR Device Logs CREATE Asset Record SCHEDULE Maintenan FIND Cohection Label D ange Collection Sta Active Disabled Samed With Collector Enabled with collector Disabled ange Collector Gro. CUG1	E uplicates te: nce Mode: ion p:

- 3. In the **Device Manager** page, select the checkbox for each SL1 appliance in your SL1 system. This includes both primary and secondary Database Servers.
- 4. In the Select Action drop-down list, select the following:
 - Change User Maintenance Mode: Enabled without Collection. This option puts the selected devices into user maintenance mode with collection disabled. The devices will remain in this state until you or another user disables user maintenance mode.
- 5. Click the [Go] button.

Deploying the Update

During deployment, avoid the following tasks:

- Running integrations and third-party applications that access the SL1 database or manipulate data on SL1
- Running discovery sessions
- Running nightly discovery
- Bringing HA/DR out of maintenance mode

- Adding new SL1 Appliances
- Importing a new patch
- Adding Data Collectors to a Collector Group
- Removing Data Collectors from a Collector Group
- Rebalancing a Collector Group
- Killing processes related to patching and upgrading
- Run reporting jobs
- Unpausing the proc mgr process

After you have imported and staged an update to SL1, run the pre-upgrade check, and fixed all errors found by the pre-upgrade check, you can either immediately deploy the update or deploy the update at a later time.

When you deploy an update, the update is installed on all appliances that have already been staged.

NOTE: When you deploy an update, SL1 checks to ensure that you have already deployed all required updates. If you have not, SL1 will generate an error message specifying the updates you must deploy before continuing with the current update.

To deploy a software update on your appliances:

- 1. Make sure that you have imported and staged the update file.
- 2. Go to the **System Updates** page (System > Tools > Updates).
- 3. In the **System Updates** page, find the software update you want to deploy. Click the lightning bolt icon (🖉) to deploy the software.

NOTE: If SL1 is still staging the patch when you click the lightning-bolt icon (\checkmark), SL1 will wait until staging has completed before deploying the updates to each ScienceLogic appliance.

- 4. The software update will be deployed to all appliances in your SL1 system that have already been staged. If one or more appliances in your SL1 system have been successfully staged, SL1 will deploy the update to those appliances.
- 5. During deployment, the Deployment Status column can have one of the following statuses:
 - --. No deployment request is active, and software has not been deployed on any SL1 appliances.
 - Scheduled. The SL1 system is aware of the deployment request and is preparing for deployment.
 - In Progress. Deployment is in progress but has not completed.
 - Complete. Deployment has completed, and all appliances are updated.
 - Incomplete. Deployment has completed, and one or more, but not all, appliances are updated.
 - Canceled. User manually canceled the deployment.

- Outdated. The current update is not the latest or has already been installed.
- Failed. An unexpected error occurred in the deployment process. Contact ScienceLogic Support.

NOTE: For details on the deployment process, go to the **System Updates** page, find the entry for the software you are interested in, go to its **Deployment Status** column, and click the log icon (a).

Troubleshooting System Update

The troubleshooting tool for System Update provides diagnostics. These can be useful when System Update does not work as expected.

To use the troubleshooting tool:

- 1. Either go to the console of any SL1 appliance or use SSH to access the appliance
- 2. Enter the following at the shell prompt:

```
sudo sysuptb -h
```

3. For more information about each argument, enter the following at the shell prompt:

```
sudo sysuptb <argument> -h
```

Available Commands

• This command executes all troubleshooting tests for System Update.

```
sudo sysuptb all <optionally -x name of test to exclude>
 • Example:
    sudo sysuptb all
    Executing filestore tests
    912 / 912 [------] 100.00%
    14 p/s
    Filestore test summary: [Total: 912, Intact: 912, Incomplete: 0, Corrupt:
    01
    Executing test for deleted appliances in patch history
    No deleted appliances were found in the patch history
    Executing test for invalid file id in patch schedules
    No patch schedules were found to have invalid file id
    Executing test for RPM database corruption
    RPM database is intact
    Executing test to check if filestore is empty
    Filestore has 1026 files
    Executing test for deactivating services
    Service test summary: [Total: 1, Active: 1, Inactive: 0, Healed: 0,
    Skipped: 0, Failed (to heal): 0]
    Executing test for free disk space
    Free disk space test summary: [Total: 2, Pass: 2, Failed: 0]
    Executing test for service errors
    Service error test summary: [Total: 2, Without Errors: 2, Restarted: 0,
    Failed: 01
    Executing hosts file check for IPV6 entry (::1) for localhost
    An entry for :: 1 is already present in the hosts file
```

Proxy is not configured for yum. Executing test for hung yum process No yum processes found Yum process summary: [Total: 0, Hung: 0]

- This command searches the logs for errors that match a service name and restarts services if any errors are found.
 - sudo sysuptb check-service-error <optionally -s name_of_service>
 If you do not provide the name of a service, the command searches the logs for errors for
 siloupdate-pkgserver.service and silopupdate-spool.service.
 - Example:

```
sudo sysuptb check-service-error
Executing test for service errors
Service error test summary: [Total: 2, Without Errors: 2, Restarted: 0,
Failed: 0]
```

• This command removes deleted SL1 appliances from the history of system updates so that they SL1 does not search for them during update.

sudo sysuptb clear-mids

• Example:

sudo sysuptb clear-mids
Executing test for deleted appliances in patch history
No deleted appliances were found in the patch history

• This command cancels al schedule updates that include an invalid ID for the patch file.

sudo sysuptb clear-schedule

• Example:

sudo sysuptb clear-schedule

Executing test for invalid file id in patch schedules No patch schedules were found to have invalid file id

• This command checks the filestore of downloaded packages for corrupt files and marks the corrupt files as incomplete.

sudo sysuptb filestore

• Example:

Filestore test summary: [Total: 912, Intact: 912, Incomplete: 0, Corrupt:
0]

• This command checks the file system for available free space.

sudo sysuptb free-space <optionally, -d path for drive = minimum size>

If you do not provide the path and minimum size of the directory, the command examines /var to make sure it has 300MB of free space and / to make sure it has 1GB of free space.

• Example:

```
sudo sysuptb free-space --disk /var=300MB
Executing test for free disk space
Free disk space test summary: [Total: 1, Pass: 1, Failed: 0]
```

• This command checks for update services that are stuck in a deactivating state and then heals them.

sudo sysuptb heal-service <optionally -s service_name>

If you do not specify a service, the command examines the service em7 patch manager.service.

• Example:

sudo sysuptb heal-service

```
Executing test for deactivating services
Service test summary: [Total: 1, Active: 1, Inactive: 0, Healed: 0,
Skipped: 0, Failed (to heal): 0]
```

• This command checks the /etc/hosts file for an entry for IPv6 for the current server (like a loopback address). If no entry exists, the command adds ::1 to the /etc/hosts file.

sudo sysuptb hosts

• Example:

sudo sysuptb hosts

Executing hosts file check for IPV6 entry (::1) for localhost An entry for ::1 is already present in the hosts file

• This command check is the filestore that holds the upgrade packages is empty.

sudo sysuptb is-filestore-empty

• Example:

sudo sysuptb is-filestore-empty

Executing test to check if filestore is empty Filestore has 1026 files

• This command checks the RPM database on /var/lib/rpm for corruption. If the command detects corruption, the output includes steps for remediation.

sudo sysuptb rpmdb

• Example:

sudo sysuptb rpmdb

```
Executing test for RPM database corruption RPM database is intact
```

• This command checks for a yum process which is hung.

sudo sysuptb yum-proc <optionally, -t timeout_in_minutes>

If you do not specify a running time, in minutes, the command searches for yum processes that have been running for more than 120 minutes.

• Example:

```
sudo sysuptb yum-proc
Executing test for hung yum process
No yum processes found
Yum process summary: [Total: 0, Hung: 0]
```

• This command checks if yum is configured with proxy. If so, the command removes the proxy configuration.

sudo sysuptb yum-proxy

• Example:

sudo sysuptb yum-proxy

```
Proxy is not configured for yum.
```

Monitoring Deployment

For SL1 versions 8.12.0 and later, you can monitor deployment. To do so:

- 1. Either go to the console of the Database Server or use SSH to access the Database Server.
- 2. Enter the following at the shell prompt:

monitor_deploy

3. You should see something like this:

× root@dw-sm-db1-patch-10-2-12-113:/tmp

Every 1.0s: bash -c monitor_deploy

System Update Vitals

I	Service Name	I	Status	I	RunTime	I	HealthCheck	
I	em7_patch_manager	I	active(running)	I	2h18min	I	Good	
L	siloupdate-spool	1	active(running)	I	2h28min	I	Good	
L	siloupdate-pkgserver	1	active(running)	I	2h27min	I	Good	
I	mariadb	I	active(running)	I	21h	I	Good	I

Deployment Process Stats

Deployment Schedule ID	: 4
Deployment Status	: Completed
No. Of system_patcher processes	: 0
No. Of deploy-module processes	: 0
Deployment Started at	: 2019-04-25 16:06:30
Deployment Completed at	: 2019-04-25 16:18:54
Deployment Run Time	: 00:12:24
Version Updated Count	: 4 [8.13.0.smailappan_EM_26803_stop_building_el5_throwawayr428]
Deployment Summary	: [Eligible=4, Complete=2, Failed=1, TimedOut=1]
<pre>_ Completed mid(s)</pre>	: [2,1]
∖_ Failed mid(s)	: [6]
∖_ TimedOut mid(s)	: [5]
Module Level Status	
proc_mgr Status	: Unpaused
deploy-module Status	: Completed
deploy-module Completed at	: 2019-04-25 16:16:35
Press CTRL-C to exit	

- System Update Vitals. Displays the current status of the services that are required for System Update.
- Deployment Process Stats. Displays status of deployment on all SL1 appliances.
- Module Level Status. Displays the status of the three deployment steps.

Putting All SL1 Appliances Out of Maintenance Mode

To disable user maintenance mode for all the SL1 appliances in your SL1 system:

- 1. Go to the **Appliance Manager** page. Note the list of SL1 appliances in your system.
- 2. Go to the **Device Manager** page (Registry > Devices > Device Manager):

ce Manager Devices Found [176]									Actions	Report	Reset	Guide
Device Name *	IP Address	Device Category	Device Class Sub-class	DID		Organization	Current State	Collection Group	Collection State	SNMP Credential	SNMP Version	
							>=Health -	1				1
10-Forward	10.20.0.195	Servers	NET-SNMP FreeBSD	54	System		AHealthy	auga	Active	Cisco SNMPv2 - E		
Avi 10.20.0.108	10.20.0.108	Network Router	Cisco Systems 2501	72	System			CUG1	Active	Cisco SNMPV2 - E		H12 &
9.110.20.0.123	10.20.0.108	Network Router	Cisco Systems 2201 Cisco Systems 7206VXR	112	System		Minor	CUG1	Active	Cisco SNMPv2 - E		10 N
10.20.0.13	10.20.0.12	Unknown	Generic I SNMP	107	System		A Healthy	CUG1	Active	Cisco SNMPv2 - E		m118
10.20.0.135	10.20.0.135		Cisco Systems Catalyst 3508G-XL	131	System		Allealthy	CUG1	Active	Cisco SNMPv2 - E		1000
20.0.141	10.20.0.141		Cisco Systems Catalyst WS-C6009-CatOS	118	System		Healthy	CUG1	Active	Cisco SNMPv2 - E		10 10 N
20.0.146	10.20.0.146		Netopia I Netopia 3346 v8.2r1	2	System		Heathy	CUG1	Active	Cisco SNMPv2 - E		_
20.0.147	10.20.0.147		Netopia Netopia 3381 v8.0.10	175	System		Heathy	CUG1	Active	Cisco SNMPv2 - E		_
20.0.148	10.20.0.148		Netopia Netopia (R3100, R45xx, R7xx0, R9	163	System		Healthy	CUG1	Active	Cisco SNMPv2 - E		_
20.0.149	10.20.0.149		Netopia R7200-T	162	System		Healthy	CUG1	Active	Cisco SNMPv2 - E		
20.0.151	10.20.0.151	Unknown	Generic I SNMP	141	System		Heathy	CUG1	Active	Cisco SNMPv2 - E		
20.0.160	10.20.0.160	Unknown	Generic I SNMP	165	System		Healthy	CUG1	Active	Cisco SNMPv2 - E		
20.0.163	10.20.0.163	Unknown	Generic SNMP	164	System		Heathy	CUG1	Active	Cisco SNMPv2 - E		
20.0.175	10 20 0 175	Unknown	Generic I SNMP	44	System		Healthy	CUG1	Active	Cisco SNMPv2 - E		_
20.0.176	10.20.0.176	Unknown	Konica Corporation OEM	41	System		A Minor	CUG1	Active	Cisco SNMPv2 - E		-
20.0.190	10.20.0.190	Unknown	Generic SNMP	56	System		Minor	CUG1	Active	Cisco SNMPv2 - E		_
20.0.191	10.20.0.191	Office.Printers	Konica Minota I Fiery X3e 22C-KM	57	System		1 Minor	CUG1	Active	Cisco SNMPv2 - E		-
20.0.201	10.20.0.201	Unknown	Generic I SNMP	48	System		Healthy	CUG1	Active	Cisco SNMPv2 - E		
20.0.208	10.20.0.208	Unknown	Generic SNMP	52	System		Heathy	CUG1	Active	Cisco SNMPv2 - E		-
20.0.209	10.20.0.209	Telephony	Quintum I Tenor	53	System		Heathy	CUG1	Active	Cisco SNMPv2 - E		
20.0.222	10.20.0.222	Unknown	Generic SNMP	138	System		Heathy	CUG1	Active	Cisco SNMPv2 - E		
20.0.26	10 20 0 26	Unknown	Generic I SNMP	171	System		Heathy	CUG1	Active	Cisco SNMPv2 - E		_
20.0.52	10.20.0.52	Unknown	ASKEY Computer Corp. I DEM	5	System		Heathy	CUG1	Active	Cisco SNMPv2 - E		
20.0.59	10.20.0.59	Unknown	Generic SNMP	3	System		Healthy	CUG1	Active	Cisco SNMPv2 - E		_
20.0.61	10.20.0.61	Unknown	Generic I SNMP	84	System		Heathy	CUG1	Active	Cisco ShimPy2 - C		_
										Select Action) diministration: LDELTE Selected Dit LMODIFY By Templat LCEAR Device Logs LCEAR Device Logs LCEAR Device Logs LCEAR Device Lasser Reco- LOBeabled Trange Collection 12 Lactive Linabled with Colec- Linabled with Colec- Linabled with Colector G Logist Dange Collector G LCUG1 Move To Organizati	e sord ance el Duplicate State: anance M tion lection roup:	
ing Page: 1]										LSystem Vign SNMP Read C		-

- 3. In the **Device Manager** page, select the checkbox for each SL1 appliance in your SL1 system.
- 4. In the **Select Action** drop-down list, select the following:
 - Change User Maintenance Mode: Disabled. This option disables user maintenance mode for the selected devices.
- 5. Click the **[Go]** button.

CAUTION: Refer to the release notes for your current release to determine if you must upgrade MariaDB after upgrading.

CAUTION: Refer to the release notes for your current release to determine if you must reboot all SL1 appliances after upgrading.

Upgrading SL1 Extended Architecture

As of January 1, 2021, new installations of SL1 Extended Architecture are available only on SaaS deployments.

For existing on-premises deployments of SL1 Extended Architecture, please contact ScienceLogic Customer Support for upgrade documentation and help with technical issues.

Manual Steps for Updates to 8.4.x and Earlier Systems

If you upgraded from an 8.4.x system or earlier, you must manually apply the following changes to every Message Collector and All-In-One Appliance in your SL1 system:

- 1. Either go to the console or use SSH to access the SL1 appliance.
- 2. Log in as user em7admin with the appropriate password.
- 3. Enter the following at the command line:

sudo vi /etc/siteconfig/siloconf.siteconfig

4. Locate the following line:

eventmanager = syslog,trap,internal

NOTE: On an All-In-One Appliance, this line will include additional entries in the comma-delimited list.

5. Add ",agent" to the end of the line. The line should now look like this:

eventmanager = syslog,trap,internal,agent

- 6. Save the file and exit vi (:wq).
- 7. At the command line, enter the following command to rebuild the configuration file:

sudo /opt/em7/share/scripts/generate-silo-conf.py > /etc/silo.conf

8.4.2 included a new feature for Ticketing. The Note Editor for tickets includes a drop-down menu where the user can specify that the note be saved as Plain Text or HTML. Ticket notes created in the API can also be saved as Plain Text or HTML. HTML is the default format for ticket notes in both the Note Editor and the API.

This new feature required a change to the database schema that will be performed immediately after a system is upgraded to 8.4.2 or later for the first time. If your system has not been upgraded to 8.4.2 or later, this schema change will be performed after upgrading to 8.6.0.

During the post-patch process, all exiting ticket notes will be migrated to the new schema in batches. During the migration, all ticket notes will be unavailable. The user interface and API will not display ticket notes. Ticket notes cannot be viewed or updated during the post-patch process. On a system that included 2,000,000 ticket notes, this process took approximately 6 hours.

If you require access to all ticket notes immediately after installing an 8.4.2 or later release, contact ScienceLogic Customer Support for details on manually updating the database schema before you upgrade to 8.4.2 or later.

Automatically Upgrading MariaDB with a Script

NOTE: Refer to the release notes for your current release to determine if you must upgrade MariaDB. Not every SL1 update requires an upgrade of for MariaDB.

SL1 will automatically update MariaDB-client, MariaDB-common, and MariaDB-shared RPMs but will not update the MariaDB Server RPM. You must update the MariaDB Server RPM.

SL1 10.1.0 and later releases include the **module_upgrade_mariadb** script to automatically upgrade MariaDB server.

CAUTION: You should store all custom configuration settings for each MariaDB database in the file /etc/siteconfig/mysql.siteconfig. If you have added custom settings to the file /etc/my.cnf.d/silo_ mysql.cnf, those changes will be overwritten each time you upgrade MariaDB. Before upgrading, copy any custom settings to the file /etc/siteconfig/mysql.siteconfig. SL1 will save these custom settings and apply them after you upgrade MariaDB.

The module_upgrade_mariadb script:

- Upgrades the following SL1 appliances:
 - All Database Servers
 - All-In-One Appliances
 - Data Collectors
 - Message Collectors
- Upgrades High Availability (HA) and Disaster Recovery (DR) systems
- Includes a "test only" option before executing upgrade
- Enforces upgrading the primary Database Server before upgrading secondary Database Server and the Data Collectors.
- Will skip SL1 appliances that have already been updated
- Logs entire sequence of commands and output for later analysis
- Stores log files in /data/logs/module upgrade mariadb.log and /data/logs/.upgrade mariadb.log
- Checks for differences between current configuration and version you are about to install and spawns an alert. To skip this check, use the -s -s option

To upgrade MariaDB, perform the following:

- 1. Either go to the console of the Database Server or use SSH to access the Database Server.
- 2. At the shell prompt, enter the following:

sudo /opt/em7/bin/module_upgrade_mariadb -m all

3. To see all the options for the *module_upgrade_mariadb* script, enter the following at the shell prompt:

/opt/em7/bin/module_upgrade_mariadb -h

```
Usage: module_upgrade_mariadb -m <module_id> [-t|--test] [-y|--assumeyes] [-s|-
-skip_conf_file_error][-p|--pool size <number_of_modules>][-h|--help]
```

- 4. The script includes these options:
 - -m parameter specifies the SL1 appliances that you want to upgrade. You can specify:
 - -m < mid1, mid2...midN> provides a comma-separated module IDs.
 - -m all : upgrade all appliances (Database Servers, All-In-One Appliances, Data Collectors, and Message Collectors).
 - -m all -db : upgrade all Database Servers.
 - -m all-cu : upgrade all Data Collectors and Message Collectors.
 - -t parameter specifies not to upgrade but instead to run a test of the upgrade script.
 - -y parameter specifies to automatically enter "yes" at all prompts.
 - -s parameter specifies to ignore errors in the MySQL configuration files and proceed with the upgrade.
 - -p parameter specifies the number of Data Collectors that you want to upgrade simultaneously. Database Servers will be upgraded one at a time. Possible values are 1 - 20. The default value is 1.
 - -p < number_of_modules > is the number of Data Collectors to upgrade simultaneously. Values are 1 - 20. The default value is 1.
- 5. To view the status of the automatic upgrade, enter the following:

```
monitor_upgrade_mariadb
```

Additional Steps for MariaDB Upgrades in 10.1.x

SL1 10.1.x includes an upgrade to MariaDB. The upgrade did not include a tool, jemalloc, that helps manage memory usage.

NOTE: This section applies only to the following release
--

- 10.1.0
- 10.1.1
- 10.1.2
- 10.1.3
- 10.1.4
- 10.1.4.1

- 10.1.4.2
- 10.1.5
- 10.1.5.1

For SL1 versions later than 10.1.5.1, jemalloc is included with the platform. For SL1 versions prior to 10.1.0, jemalloc is included with the platform.

To avoid problems with memory usage on Database Servers, perform the following steps after upgrading MariaDB for 10.1.x.

NOTE: Perform these steps first on the active Database Server and then on each additional Database Server in your SL1 System.

- 1. Open an SSH session to the Database Server.
- 2. To verify that the Database Server is not currently running jemalloc, enter the following at the shell prompt:

silo_mysql -e 'show global variables like "version_malloc_library"'
If the Database Server is not currently running jemalloc, the shell will display the following:

Variable Name	Value
version_malloc_library	system

3. Search for the file /usr/lib64/libjemalloc.so.1.

If the file does not exist, contact ScienceLogic Customer Support to request the file jemalloc-3.6.0-1.el7.x86_64.rpm.

To install the RPM, use a file-transfer utility, copy the file to a directory on the SL1 appliance. Then enter the following at the shell prompt:

```
cd /usr/lib64
```

sudo yum install jemalloc-3.6.0-1.el7.x86_64.rpm

4. Create the file /etc/systemd/system/mariadb.service.d/jemalloc.conf:

vi /etc/systemd/system/mariadb.service.d/jemalloc.conf

5. Add the following lines to the file:

[Service]

Environment="LD_PRELOAD=/usr/lib64/libjemalloc.so.1"

- 6. Save and close the file.
- 7. Reload the systemd config files:

sudo systemctl daemon-reload

8. Restart the Database Server:

To restart the **standalone Database Server** or the **primary Database Server in a cluster**, enter the following:

sudo systemctl restart mariadb

To restart each secondary Database Server in a cluster:

a. Open an SSH session to the secondary Database Server. At the shell prompt, enter:

coro_config

- b. Select 1.
- c. When prompted to put the Database Server into maintenance, select y.
- d. Open an SSH session to the primary Database Server. To pause SL1, enter the following at the shell prompt:

```
sudo touch /etm/.proc mgr pause
```

e. In the SSH session for the secondary Database Server, restart MariaDB:

```
crm resource restart mysql
```

f. After MariaDB has restarted successfully on the secondary Database Server, return to the SSH session on the primary Database Server. Remove the pause file for SL1:

sudo rm /tmp/.proc mgr pause

g. In the SSH session on the secondary Database Server, take the Database Server out of maintenance. At the shell prompt, enter:

coro_config

- h. Select 1.
- i. When prompted to take the Database Server out of maintenance, select y.
- 9. To verify that jemalloc is running on the Database Server, enter the following at the shell prompt:

silo_mysql -e 'show global variables like "version_malloc_library"'
If the Database Server is currently running jemalloc, the shell will display something like the following:

Variable Name	Value
/	jemalloc 3.6.0-0- g46c0af68bd248b04df75e4f92d5fb804c3d75340

10. Perform these steps on each Database Server in your SL1 system.

Manually Upgrading MariaDB

NOTE: Refer to the release notes for your current release to determine if you must upgrade MariaDB. Not every SL1 update requires an upgrade of for MariaDB.

If you prefer to upgrade MariaDB manually, the following sections describe how to upgrade the MariaDB server for different SL1 appliance types and architectures.

When you update MariaDB, you must update the following SL1 appliances:

- All Database Servers
- All-In-One Appliances

- Data Collectors
- Message Collectors

CAUTION: You should store all custom configuration settings for each MariaDB database in the file /etc/siteconfig/mysql.siteconfig. If you have added custom settings to the file /etc/my.cnf.d/silo_ mysql.cnf, those changes will be overwritten each time you upgrade MariaDB. Before upgrading, copy any custom settings to the file /etc/siteconfig/mysql.siteconfig. SL1 will save these custom settings and apply them after you upgrade MariaDB.

Download RPMs to SL1 Appliances

Before upgrading MariaDB, you must copy the RPMs from the primary Database Server to the Database Servers, All-In-One Appliances, Data Collectors, and Message Collectors in your SL1 system. To do this.

- 1. Open an SSH session to the Database Server.
- 2. To download the latest RPMs from the Database Server, enter the following at the shell prompt:

```
curl -Lk -u "<SL1 admin user name>:<SL1 admin password>"
http://localhost:10080/MariaDB-server-`rpm -q --queryformat '%{VERSION}-%
{RELEASE}.%{ARCH}' MariaDB-client`.rpm > /tmp/MariaDB-server.rpm
curl -Lk -u "<SL1 admin user name>:<SL1 admin password>"
http://localhost:10080/`repoquery --repoid em7-os --queryformat '%{NAME}-%
{VERSION}-%{RELEASE}.%{ARCH}.rpm' galera-4` > /tmp/galera-4.rpm
```

3. To Navigate to /tmp directory, enter the following:

cd /tmp

- 4. Use SCP or another secure copy program to copy these files to the /tmp directory on each on each Database Server, All-In-One Appliance, Data Collector, and Message Collector:
 - MariaDDB-server.rpm
 - galera-4.rpm

CAUTION: : To conserve disk space, ScienceLogic recommends you delete the RPMs from the /tmp directory the on the Database Servers, All-In-One Appliances, Data Collectors, and Message Collectors in your SL1 system after you successfully upgrade MariaDB.

Manually Upgrade Two Database Servers Configured for High Availability or Disaster Recovery

To upgrade a High Availability or Disaster Recovery cluster, perform the following steps:

WARNING: The system will be unavailable when performing these steps.

Step 1: On the Secondary Database Server

You must put the secondary Database Server in maintenance mode. To do this:

- 1. Open an SSH session to the Database Server.
- 2. At the shell prompt, enter:

sudo -s

- 3. When prompted, enter the administrator password.
- 4. At the shell prompt, enter:

coro config

- 5. The following prompt appears:
 - 1) Enable Maintenance
 - 2) Option Disabled
 - 3) Promote DRBD
 - 4) Stop Pacemaker
 - 5) Resource Status
 - 6) Quit
- 6. Enter "1".

Step 2: On the Primary Database Server

1. To determine the current installed version of the RPMs:

sudo rpm -qa ^MariaDB-*

2. To stop SL1 and MariaDB, enter the following at the shell prompt:

sudo systemctl stop em7

- sudo systemctl stop mariadb.service
- 3. To stop the MySQL resource, enter the following:

sudo crm resource stop mysql

- 4. To save the current enabled state for mariadb.service, enter the following:
 - export MSRV=`sudo systemctl is-enabled mariadb.service`
- 5. To remove the older version of MariaDB-server, enter the following:

sudo rpm --nodeps -ev MariaDB-server

6. To replace the Galera package and install the new MariaDB-server package, enter the following:

```
sudo yum --disablerepo=* swap -- remove galera -- install /tmp/galera-4.rpm
```

```
sudo yum --disablerepo=* install /tmp/MariaDB-server.rpm
```

7. To remove incompatible backup packages, enter the following:

sudo yum remove percona-xtrabackup

NOTE: If the "yum remove" command fails, it means that the package does not exist on the SL1 appliance. You can ignore the error message.

8. To regenerate the configuration file for MariaDB, enter the following:

sudo /opt/em7/share/scripts/generate-my-conf.py -o /etc/my.cnf.d/silo_mysql.cnf

9. To re-start MariaDB, enter the following:

sudo systemctl daemon-reload

sudo systemctl start mariadb

10. To restart the MySQL resource:

sudo crm resource start mysql

11. To restore the mariadb.service enabled state, enter the following:

sudo systemctl \${MSRV::-1} mariadb.service

12. To upgrade the internal configuration for the database, enter the following:

sudo mysql_upgrade -u root -p

13. To restart the em7 service:

sudo systemctl start em7

sudo rpm -qa ^MariaDB-*

14. To stop SL1 and MariaDB, enter the following at the shell prompt:

sudo systemctl stop em7

sudo systemctl stop mariadb.service

15. To stop the MySQL resource, enter the following:

sudo crm resource stop mysql

16. To save the current enabled state for mariadb.service, enter the following:

export MSRV=`sudo systemctl is-enabled mariadb.service`

- 17. To remove the older version of MariaDB-server, enter the following:
 - sudo rpm --nodeps -ev MariaDB-server
- 18. To replace the Galera package and install the new MariaDB-server package, enter the following:

```
sudo yum --disablerepo=* swap -- remove galera -- install /tmp/galera-4.rpm
```

sudo yum --disablerepo=* install /tmp/MariaDB-server.rpm

19. To remove incompatible backup packages, enter the following:

sudo yum remove percona-xtrabackup

NOTE: If the "yum remove" command fails, it means that the package does not exist on the SL1 appliance. You can ignore the error message.

20. To regenerate the configuration file for MariaDB, enter the following:

sudo /opt/em7/share/scripts/generate-my-conf.py -o /etc/my.cnf.d/silo_mysql.cnf

21. To re-start MariaDB, enter the following:

sudo systemctl daemon-reload

sudo systemctl start mariadb

22. To restart the MySQL resource:

sudo crm resource start mysql

23. To restore the mariadb.service enabled state, enter the following:

```
sudo systemctl ${MSRV::-1} mariadb.service
```

24. To upgrade the internal configuration for the database, enter the following:

```
sudo mysql_upgrade -u root -p
```

25. To restart the em7 service:

```
sudo systemctl start em7
```

Step 3: On the Secondary Database Server

1. To determine the current installed version of the RPMs:

```
sudo rpm -qa ^MariaDB-*
```

2. To save the current enabled state for mariadb.service, enter the following:

export MSRV=`sudo systemctl is-enabled mariadb.service`

3. To remove the older version of MariaDB-server, enter the following:

sudo rpm --nodeps -ev MariaDB-server

4. To replace the Galera package and install the new MariaDB-server package, enter the following:

```
sudo yum --disablerepo=* swap -- remove galera -- install /tmp/galera-4.rpm
```

```
sudo yum --disablerepo=* install /tmp/MariaDB-server.rpm
```

5. To remove incompatible backup packages, enter the following:

sudo yum remove percona-xtrabackup

NOTE: If the "yum remove" command fails, it means that the package does not exist on the SL1 appliance. You can ignore the error message.

- 6. To regenerate the configuration file for MariaDB, enter the following:
- sudo /opt/em7/share/scripts/generate-my-conf.py -o /etc/my.cnf.d/silo_mysql.cnf 7. To restore the mariadb.service enabled state, enter the following:
 - sudo systemctl \${MSRV::-1} mariadb.service
- 8. To take the secondary Database Server out of maintenance mode, enter the following at the shell prompt: sudo -s
- 9. When prompted, enter the administrator password.
- 10. At the shell prompt, enter:

coro config

- 11. The following prompt appears:
 - 1) Disable Maintenance
 - 2) Option Disabled
 - 3) Promote DRBD
 - 4) Stop Pacemaker
 - 5) Resource Status

Manually Upgrade Three Database Servers Configured for High Availability and Disaster Recovery

To upgrade a High Availability/Disaster Recovery cluster, perform the following steps:

WARNING: The system will be unavailable when performing these steps.

Step 1: On the Secondary Database Server

You must put the secondary Database Server in maintenance mode. To do this:

- 1. Open an SSH session to the Database Server.
- 2. At the shell prompt, enter:
 - sudo -s
- 3. When prompted, enter the administrator password.
- 4. At the shell prompt, enter:

coro config

- 5. The following prompt appears:
 - 1) Enable Maintenance
 - 2) Option Disabled
 - 3) Promote DRBD
 - 4) Stop Pacemaker
 - 5) Resource Status
 - 6) Quit
- 6. Enter "1".

Step 2: On the Primary Database Server

1. To determine the current installed version of the RPMs:

```
sudo rpm -qa ^MariaDB-*
```

2. To stop SL1 and MariaDB, enter the following at the shell prompt:

```
sudo systemctl stop em7
```

- sudo systemctl stop mariadb.service
- 3. To stop the MySQL resource, enter the following:

sudo crm resource stop mysql

4. To save the current enabled state for mariadb.service, enter the following:

export MSRV=`sudo systemctl is-enabled mariadb.service`

5. To remove the older version of MariaDB-server, enter the following:

```
sudo rpm --nodeps -ev MariaDB-server
```

6. To replace the Galera package and install the new MariaDB-server package, enter the following:

```
sudo yum --disablerepo=* swap -- remove galera -- install /tmp/galera-4.rpm
```

```
sudo yum --disablerepo=* install /tmp/MariaDB-server.rpm
```

- 7. To remove incompatible backup packages, enter the following:
 - sudo yum remove percona-xtrabackup

NOTE: If the "yum remove" command fails, it means that the package does not exist on the SL1 appliance. You can ignore the error message.

8. To regenerate the configuration file for MariaDB, enter the following:

```
sudo /opt/em7/share/scripts/generate-my-conf.py -o /etc/my.cnf.d/silo_mysql.cnf
9. To re-start MariaDB, enter the following:
```

sudo systemctl daemon-reload

sudo systemctl start mariadb

10. To restart the MySQL resource:

sudo crm resource start mysql

11. To restore the mariadb.service enabled state, enter the following:

sudo systemctl \${MSRV::-1} mariadb.service

12. To upgrade the internal configuration for the database, enter the following:

sudo mysql_upgrade -u root -p

13. To restart the em7 service:

sudo systemctl start em7

Step 3: On the Secondary Database Server

1. To save the current enabled state for mariadb.service, enter the following:

export MSRV=`sudo systemctl is-enabled mariadb.service`

2. To remove the older version of MariaDB-server, enter the following:

sudo rpm --nodeps -ev MariaDB-server

3. To replace the Galera package and install the new MariaDB-server package, enter the following:

```
sudo yum --disablerepo=* swap -- remove galera -- install /tmp/galera-4.rpm
```

sudo yum --disablerepo=* install /tmp/MariaDB-server.rpm

4. To remove incompatible backup packages, enter the following:

sudo yum remove percona-xtrabackup

NOTE: If the "yum remove" command fails, it means that the package does not exist on the SL1 appliance. You can ignore the error message.

5. To regenerate the configuration file for MariaDB, enter the following:

sudo /opt/em7/share/scripts/generate-my-conf.py -o /etc/my.cnf.d/silo_mysql.cnf6. To restore the mariadb.service enabled state, enter the following:

sudo systemctl \${MSRV::-1} mariadb.service

7. At the shell prompt, enter:

sudo -s

- 8. When prompted, enter the administrator password.
- 9. At the shell prompt, enter:

coro config

- 10. The following prompt appears:
 - 1) Disable Maintenance
 - 2) Option Disabled
 - 3) Promote DRBD
 - 4) Stop Pacemaker
 - 5) Resource Status

```
6) Quit
```

```
11. Enter "1".
```

Step 4: On the Disaster Recovery Database Server

- 1. Open an SSH session to the Disaster Recovery Database Server.
- 2. At the shell prompt, enter:

sudo -s

- 3. When prompted, enter the administrator password.
- 4. To save the current enabled state for mariadb.service, enter the following:
 - export MSRV=`sudo systemctl is-enabled mariadb.service`
- 5. To remove the older version of MariaDB-server, enter the following:
 - sudo rpm --nodeps -ev MariaDB-server
- 6. To replace the Galera package and install the new MariaDB-server package, enter the following:

```
sudo yum --disablerepo=* swap -- remove galera -- install /tmp/galera-4.rpm
```

sudo yum --disablerepo=* install /tmp/MariaDB-server.rpm

7. To remove incompatible backup packages, enter the following:

sudo yum remove percona-xtrabackup

NOTE: If the "yum remove" command fails, it means that the package does not exist on the SL1 appliance. You can ignore the error message.

8. To regenerate the configuration file for MariaDB, enter the following:

sudo /opt/em7/share/scripts/generate-my-conf.py -o /etc/my.cnf.d/silo_mysql.cnf
9. To restore the mariadb.service enabled state, enter the following:

```
sudo systemctl ${MSRV::-1} mariadb.service
```

Manually Upgrading Standalone Database Servers, All-In-One Appliances, Data Collectors, and Message Collectors

To upgrade MariaDB on one or more Database Servers that are not configured for high availability or disaster recovery, a single All-In-One Appliance, one or more Data Collectors, or one or more Message Collectors, perform the following steps:

WARNING: The Database Server, All-In-One Appliance, Data Collector, or Message Collector will be unavailable when performing these steps.

- 1. Go to the console or open an SSH session to the SL1 appliance.
- 2. To stop SL1 and mariadb, enter the following at the shell prompt:

sudo systemctl stop em7

sudo systemctl stop mariadb.service

- 3. To save the current enabled state for the mariadb.service, enter the following:
 - export MSRV=`sudo systemctl is-enabled mariadb.service`
- 4. To remove the older version of MariaDB-server, enter the following:

sudo rpm --nodeps -ev MariaDB-server

5. To replace the Galera package and install the new MariaDB-server package, enter the following:

```
sudo yum --disablerepo=* swap -- remove galera -- install /tmp/galera-4.rpm
```

- sudo yum --disablerepo=* install /tmp/MariaDB-server.rpm
- 6. To remove incompatible backup packages, enter the following:

sudo yum remove percona-xtrabackup

NOTE: If the "yum remove" command fails, it means that the package does not exist on the SL1 appliance. You can ignore the error message.

7. To regenerate the configuration file for MariaDB, enter the following:

sudo /opt/em7/share/scripts/generate-my-conf.py -o /etc/my.cnf.d/silo mysql.cnf

8. To re-start MariaDB, enter the following:

sudo systemctl daemon-reload

sudo systemctl start mariadb

9. To restore the mariadb.service enabled state, enter the following:

sudo systemctl \${MSRV::-1} mariadb.service

10. To upgrade the internal configuration for the database, enter the following:

sudo mysql_upgrade -u root -p

11. To restart the em7 service:

sudo systemctl start em7

12. Repeat all the steps in this section on each non-HA/DR Database Server, All-In-One Appliance, Data Collector, and Message Collector.

Additional Steps for MariaDB Upgrades in 10.1.x

SL1 10.1.x includes an upgrade to MariaDB. The upgrade did not include a tool, jemalloc, that helps manage memory usage.

NOTE: This section applies only to the following releases:

• 10.1.0

• 10.1.1

- 10.1.2
- 10.1.3
- 10.1.4
- 10.1.4.1
- 10.1.4.2
- 10.1.5
- 10.1.5.1

For SL1 versions later than 10.1.5.1, jemalloc is included with the platform. For SL1 versions prior to 10.1.0, jemalloc is included with the platform.

To avoid problems with memory usage on Database Servers, perform the following steps after upgrading MariaDB for 10.1.x.

NOTE: Perform these steps first on the active Database Server and then on each additional Database Server in your SL1 System.

- 1. Open an SSH session to the Database Server.
- 2. To verify that the Database Server is not currently running jemalloc, enter the following at the shell prompt:

silo_mysql -e 'show global variables like "version_malloc_library"'
If the Database Server is not currently running jemalloc, the shell will display the following:

	Variable Name	Value
Ī	version_malloc_library	system

3. Search for the file /usr/lib64/libjemalloc.so.1.

If the file does not exist, contact ScienceLogic Customer Support to request the file jemalloc-3.6.0-1.el7.x86_64.rpm.

To install the RPM, use a file-transfer utility, copy the file to a directory on the SL1 appliance. Then enter the following at the shell prompt:

```
cd /usr/lib64
```

sudo yum install jemalloc-3.6.0-1.el7.x86_64.rpm

- 4. Create the file /etc/systemd/system/mariadb.service.d/jemalloc.conf:
 - vi /etc/systemd/system/mariadb.service.d/jemalloc.conf
- 5. Add the following lines to the file:

[Service]

```
Environment="LD PRELOAD=/usr/lib64/libjemalloc.so.1"
```

- 6. Save and close the file.
- 7. Reload the systemd config files:

sudo systemctl daemon-reload

8. Restart the Database Server:

To restart the **standalone Database Server** or the **primary Database Server in a cluster**, enter the following:

sudo systemctl restart mariadb To restart each **secondary Database Server in a cluster**:

a. Open an SSH session to the secondary Database Server. At the shell prompt, enter:

coro_config

- b. Select 1.
- c. When prompted to put the Database Server into maintenance, select y.
- d. Open an SSH session to the primary Database Server. To pause SL1, enter the following at the shell prompt:

```
sudo touch /etm/.proc_mgr_pause
```

e. In the SSH session for the secondary Database Server, restart MariaDB:

```
crm resource restart mysql
```

f. After MariaDB has restarted successfully on the secondary Database Server, return to the SSH session on the primary Database Server. Remove the pause file for SL1:

```
sudo rm /tmp/.proc_mgr_pause
```

g. In the SSH session on the secondary Database Server, take the Database Server out of maintenance. At the shell prompt, enter:

```
coro_config
```

```
h. Select 1.
```

- i. When prompted to take the Database Server out of maintenance, select y.
- 9. To verify that jemalloc is running on the Database Server, enter the following at the shell prompt:

silo_mysql -e 'show global variables like "version_malloc_library"'
If the Database Server is currently running jemalloc, the shell will display something like the following:

Variable Name	Value
version_malloc_library	jemalloc 3.6.0-0- g46c0af68bd248b04df75e4f92d5fb804c3d75340

10. Perform these steps on each Database Server in your SL1 system.

Rebooting Appliances in the SL1 Distributed Stack

NOTE: Refer to the release notes for your current release to determine if you must reboot all SL1 appliances. Not every SL1 update requires rebooting.

When an upgrade requires a reboot, use the steps listed in this section to reboot all SL1 appliances in the Distributed stack.

Rebooting the Administration Portal

You can reboot Administration Portals either from the user interface or from the command line.

Rebooting Multiple Administration Portals

If your SL1 system includes multiple Administration Portals, you can remotely reboot Administration Portals from another Administration Portal. To do so:

- 1. Go to the Appliance Manager page (System > Settings > Appliances).
- 2. Select the checkboxes for the SL1 appliances you want to reboot.
- 3. In the [Select Action] menu, select Reboot and click the [Go] button.
- 4. Click the **[OK]** button when the "Are you sure you want to reboot the selected appliances?" message is displayed.
- 5. During the reboot, the user interface for the affected Administration Portal unavailable.
- 6. When the reboot has completed, the **Audit Logs** page (System > Monitor > Audit Logs) will include an entry for each appliance that was rebooted.

Rebooting a Single Administration Portal

If your SL1 system include only a single Administration Portal, perform the following steps to reboot that Administration Portal:

- 1. Either go to the console of the Database Server or use SSH to access the Database Server.
- 2. Log in as em7admin with the appropriate password.
- 3. At the shell prompt, execute the following:

```
python -m silo_common.admin_toolbox <appliance_ID> "/usr/bin/sudo
/usr/sbin/shutdown -r +1"
where:
```

• appliance_ID is the appliance ID for the Data Collector, Message Collector, or Administration Portal.

Rebooting Data Collectors and Message Collectors

You can reboot Data Collectors and Message Collectors either from the user interface or from the command line.

Rebooting Data Collectors and Message Collectors from the Appliance Manager page

From the SL1 user interface, perform the following steps to reboot a Data Collector or a Message Collector:

- 1. Go to the Appliance Manager page (Appliance Manager).
- 2. Select the checkbox for each SL1 appliance you want to reboot.
- 3. In the [Select Action] menu, select Reboot and click the [Go] button.
- 4. Click the **[OK]** button when the "Are you sure you want to reboot the selected appliances?" message is displayed.
- 5. During the reboot, go to the **System Logs** page (System > Monitor > System Logs). You should see this message:

Major: Could not connect to module (5) database USING SSL=TRUE: Error attempting to connect to database with SSL enabled True: (2003, 'Can't connect to MySQL server on '10.2.12.77' (113 "No route to host")')

6. When the reboot has completed, the **Audit Logs** page (System > Monitor > Audit Logs) will include an entry for each appliance that was rebooted.

Rebooting Data Collectors and Message Collectors from the Command Line

From the console of the Database Server or SSH to the Database Server, perform the following steps to reboot Data Collector or Message Collector:

- 1. Either go to the console of a Database Server or SSH to access the Database Server.
- 2. Log in as **em7admin** with the appropriate password.
- 3. At the shell prompt, execute the following:

```
python -m silo_common.admin_toolbox <appliance_ID> "/usr/bin/sudo
/usr/sbin/shutdown -r +1"
where:
```

• appliance ID is the appliance ID for the Data Collector, Message Collector, or Administration Portal.

Rebooting Standalone All-In-One Appliance and Standalone Database Server

Perform the following steps to reboot a standalone All-In-One Appliance or a standalone Database Server:

- 1. Either go to the console or use SSH to access the SL1 appliance.
- 2. Log in as **em7admin** with the appropriate password.

3. Execute the following commands on the SL1 appliance to pause the system and shutdown MariaDB.

sudo touch /tmp/.proc_mgr_pause

sudo systemctl stop mariadb

4. Execute the following command on the appliance to reboot the SL1 appliance:

sudo reboot

- 5. After the SL1 appliance has rebooted, either go to the console or use SSH to access the SL1 appliance.
- 6. Log in as **em7admin** with the appropriate password.
- Execute the following command on the appliance to un-pause the system: sudo rm /tmp/.proc mgr pause

Rebooting Two Database Servers Configured for Disaster Recovery

Perform the following steps to reboot two Database Servers configured for Disaster Recovery:

- 1. Either go to the console of the **primary** Database Server or use SSH to access the primary Database Server.
- 2. Log in as *em7admin* with the appropriate password.
- First, you should check the status of both Database Servers. To do this, enter the following at the shell prompt:

cat /proc/drbd

4. Your output will look like this:

```
1: cs:Connected ro:Primary/Secondary ds:UpToDate/UpToDate C r----
ns:17567744 al:0 bm:1072 lo:0 pe:0 ua:0 ap:0 ep:1 wo:b oos:12521012
```

5. Execute the following commands on the **primary** Database Server to pause the system and shutdown MariaDB. Enter the password for the em7admin user when prompted:

```
sudo touch /tmp/.proc_mgr_pause
sudo systemctl stop pacemaker
sudo systemctl stop mariadb
```

- 6. Execute the following command on the **primary** Database Server to reboot the appliance: sudo reboot
- 7. After the primary appliance has rebooted, log in to the console of the primary Database Server again.
- 8. Execute the following commands on the **primary** Database Server:

sudo rm /tmp/.proc_mgr_pause

- 9. Enter the password for the em7admin user and confirm the command when prompted.
- 10. Log in to the secondary Database Server as the em7admin user using the console or SSH.
- 11. Execute the following command on the **secondary** Database Server to reboot the appliance: sudo reboot
- 12. Enter the password for the em7admin user when prompted.

Rebooting Two Database Servers in a High Availability Cluster

Perform the following steps to reboot two Database Servers in a high availability cluster:

- 1. Either go to the console of the **secondary** Database Server or use SSH to access the **secondary** Database Server.
- 2. Log in as **em7admin** with the appropriate password.
- 3. First, you should check the status of both Database Servers. To do this, enter the following at the shell prompt:

cat /proc/drbd

4. Your output will look like this:

```
1: cs:Connected ro:Secondary/Primary ds:UpToDate/UpToDate C r----
ns:17567744 al:0 bm:1072 lo:0 pe:0 ua:0 ap:0 ep:1 wo:b oos:12521012
```

NOTE: If your output includes "ro:Secondary/Primary", but does not include "UpToDate/UpToDate", data is being synchronized between the two appliances. You must wait until data synchronization has finished before rebooting.

- Execute the following command on the secondary Database Server to stop the cluster service: sudo systemct1 stop pacemaker
- 6. Enter the password for the em7admin user when prompted.
- 7. Either go to the console of the primary Database Server or use SSH to access the primary Database Server.
- 8. Log in as em7admin with the appropriate password.
- 9. Execute the following commands on the **primary** Database Server to pause the system and stop the cluster service. Enter the password for the em7admin user when prompted:

sudo touch /tmp/.proc_mgr_pause
sudo systemctl stop pacemaker
sudo systemctl stop mariadb

10. Execute the following command on the **primary** Database Server to reboot the appliance:

sudo reboot

- 11. After the **primary** Database Server has rebooted, either go to the console of the **primary** Database Server or use SSH to access the **primary** Database Server.
- 12. Log in as **em7admin** with the appropriate password.
- Execute the following command on the primary Database Server: sudo rm /tmp/.proc_mgr_pause
- 14. Enter the password for the em7admin user and confirm the command when prompted.

- 15. Either go to the console of the **secondary** Database Server or use SSH to access the **secondary** Database Server.
- 16. Log in as **em7admin** with the appropriate password.
- Execute the following command on the **secondary** Database Server:
 sudo reboot
- 18. Enter the password for the em7admin user when prompted.

Rebooting Three Database Servers Configured for High Availability and Disaster Recovery

Perform the following steps to reboot three Database Servers configured for high availability and disaster recovery. In this configuration, two Database Servers are configured as a High Availability cluster and one Database Server is configured for Disaster Recovery.

- 1. Either go to the console of the **secondary** Database Server in the HA cluster or use SSH to access the **secondary** Database Server in the HA cluster,
- 2. Log in as em7admin with the appropriate password.
- 3. First, you should check the status of both Database Servers in the HA cluster. To do this, enter the following at the shell prompt:

cat /proc/drbd

4. Your output will look like this:

```
10: cs:Connected ro:Secondary/Primary ds:UpToDate/UpToDate C r----
ns:17567744 al:0 bm:1072 lo:0 pe:0 ua:0 ap:0 ep:1 wo:b oos:12521012
```

NOTE: If your output includes "ro:Secondary/Primary", but does not include "UpToDate/UpToDate", data is being synchronized between the two appliances. You must wait until data synchronization has finished before rebooting.

5. To stop the cluster service, execute the following command on the **secondary** Database Server in the HA cluster:

sudo systemctl stop pacemaker

- 6. Enter the password for the em7admin user when prompted.
- 7. Either go to the console of the **primary** Database Server in the HA cluster or use SSH to access the **primary** Database Server in the HA cluster.
- 8. Log in as *em7admin* with the appropriate password.
- 9. To pause the system and stop the cluster service, execute the following commands on the **primary** Database Server in the HA cluster :

sudo touch /tmp/.proc_mgr_pause
sudo systemctl stop pacemaker

sudo systemctl stop mariadb

- 10. Enter the password for the em7admin user when prompted
- 11. To reboot the **primary** Database Server in the HA cluster, the following command on the **primary** Database Server in the HA cluster:

sudo reboot

- 12. After the **primary** Database Server in the HA cluster has rebooted, either go to the console of the **primary** Database Server in the HA cluster or use SSH to access the **primary** Database Server in the HA cluster.
- 13. Execute the following command on the **primary** Database Server in the HA cluster:

sudo rm /tmp/.proc_mgr_pause

- 14. Enter the password for the em7admin user and confirm the command when prompted.
- 15. Either go to the console of the **secondary** Database Server in the HA cluster or use SSH to access the **secondary** Database Server in the HA cluster.
- 16. Log in as **em7admin** with the appropriate password.
- 17. Execute the following command on the **secondary** Database Server in the HA cluster to reboot the appliance:

sudo reboot

- 18. Enter the password for the em7admin user when prompted.
- 19. Either go to the console of the Database Server for Disaster Recovery or use SSH to access the Database Server for Disaster Recovery.
- 20. Log in as em7admin with the appropriate password.
- 21. Execute the following command on the Database Server for Disaster Recovery to reboot the appliance: sudo reboot
- 22. Enter the password for the em7admin user when prompted.

Restoring Settings for NextUl

To restore the backup of the custom settings in the NextUI:

- 1. Login to the console of the Database Server or SSH to the Database Server.
- 2. Open a shell session.
- 3. Enter the following at the shell prompt:

cp /opt/em7/nextui/nextui.env.backup /opt/em7/nextui/nextui.env

Restoring the SSL Certificate

To restore your SSL Certificates:

- 1. Login to the console of the Database Server or SSH to the Database Server.
- 2. Open a shell session.
- 3. Enter the following at the shell prompt:
 - cp /etc/nginx/silossl.key.bak /etc/nginx/silossl.key
 - cp /etc/nginx/silossl.pem.bak /etc/nginx/silossl.pem
- 4. Repeat these steps on each Database Server in your SL1 system.

Resetting the Timeout for PhoneHome Watchdog

You can manually re-set the settings for the PhoneHome Watchdog server back to the settings you used before the upgrade.

To edit the settings for the watchdog service:

- 1. Log in to the console of the Data Collector as the root user or open an SSH session on the Data Collector.
- 2. At the command line, type the following:

```
phonehome watchdog view
```

3. You should see something like the following:

```
Current settings:
autosync: yes
interval: 120
state: enabled
autoreconnect: yes
timeoutcount: 1
check: default
```

- 4. Note the settings for *interval* and *timeoutcount*, so you can restore them after the upgrade.
- 5. To change the settings for SL1 upgrade, type the following at the command line:

sudo phonehome watchdog set interval=<previous setting>; sudo phonehome watchdog set timeoutcount=<previous setting>; systemctl stop em7_ph_watchdog; systemctl start em7_ph_watchdog;

- 6. Repeat these steps on each Data Collector.
- 7. Repeat these steps on each , Message Collector.
- 8. Repeat these steps on each Database Server.

Updating Default PowerPacks

Every time you install a software update on your appliances, ScienceLogic recommends that you also install the updates for all the PowerPacks that were included in the software update.

ScienceLogic includes multiple PowerPacks in the default installation of SL1. When you apply an update to your system, new versions of the default PowerPacks will be automatically imported in to your system. If a PowerPack is included in an update and is not currently installed on your system, SL1 will automatically install the PowerPack. If a PowerPack is included in an update and is currently installed on your system, SL1 will automatically import (but not install) the PowerPack.

If PowerPacks have been imported into your system but have not been installed, the **Update** column appears in the **PowerPack Manager** page (System > Manage > PowerPacks). For each PowerPack that has been imported to your system but has not been installed, the lightning bolt icon (\checkmark) appears in the **Update** field on the **PowerPack Manager** page.

To install the updates for multiple PowerPacks:

1. Go to the **PowerPack Manager** page (System > Manage > PowerPacks).

	Version	Update	Publisher	Apps	Events	Classes	Reports	Widgets	Dashbds	Actions	Creds	Tckt Tpl	DashSL1	Dev Tpl		Edited By	Last Edited	
a simple DCM app	3		ScienceLogic, Inc.	24		21									169	em7admin	2019-07-25 14:15:22	Í
Microsoft PowerPack Test Creds	1.7	No	ScienceLogic, Inc.								21				177	em7admin	2019-07-26 15:16:28	6
SNMP Dynamic Application Ref	1.0	No	ScienceLogic, Inc.	25										21	179	em7admin	2019-07-26 15:56:25	
2-level DCM app test	1.1	No	ScienceLogic, Inc.	24	21	2									186	em7admin	2019-07-30 08:28:38	
3Com Base Pack	1	No	ScienceLogic, Inc.			298 🏹									30	em7admin	2019-07-25 11:17:02	
Alcatel-Lucent Base Pack	1	No	ScienceLogic, Inc.			233 🎤									130	em7admin	2019-07-25 11:18:45	
Alteon Base Pack	1.3	No	ScienceLogic, Inc.	23	25	26									114	em7admin	2019-07-25 11:18:27	
Amazon Web Services	113	No	ScienceLogic, Inc.	211	222	<u>2</u> 149	23		<u>2</u> 13	25	23				41	em7admin	2019-07-25 11:17:23	
APC Base Pack	7.3.6	No	ScienceLogic, Inc.	29	27	230									48	em7admin	2019-07-25 11:17:32	
Application Management Pack	1	No	ScienceLogic, Inc.		24										5	em7admin	2019-07-25 11:16:39	
Arista Networks: Base	1.0	No	ScienceLogic, Inc.			265									120	em7admin	2019-07-25 11:18:35	
Aruba Base Pack	1.1	No	ScienceLogic, Inc.	23											146	em7admin	2019-07-25 11:18:58	
AskEM7 Query Widgets	7.2.3	No	ScienceLogic, Inc.					23							34	em7admin	2019-07-25 11:17:07	
Attachmate Base Pack	1.1	No	ScienceLogic, Inc.			<u>Z</u> 13									56	em7admin	2019-07-25 11:17:35	
Avaya Base Pack	7.3.5	No	ScienceLogic, Inc.			<u></u> 43									92	em7admin	2019-07-25 11:17:58	
Avocent ACS Pack	7.3.6	No	ScienceLogic, Inc.	24											147	em7admin	2019-07-25 11:18:58	
Avocent Base Pack	1.1	No	ScienceLogic, Inc.	23		26									54	em7admin	2019-07-25 11:17:35	
Blue Coat Base Pack	1.2	No	ScienceLogic, Inc.	21	22	210										[Select Action] Administration		

- 2. In the PowerPack Manager page, select the checkbox for each PowerPack you want to install.
- 3. In the Select Action drop-down field (in the lower right), choose Update PowerPack(s).
- 4. SL1 will display the following message before updating the PowerPack(s):

```
Update the selected PowerPacks?
NOTE: Any customizations to items contained in updated PowerPacks will be
overwritten by the version contained within the more recently imported PowerPack
file.
```

Click the [OK] button to continue the installation. Click the [Cancel] button to quit the update.

 Click the [Go] button. If you completed the update, updated information about the PowerPack will appear in the PowerPack Manager page. All the items in the PowerPack will be automatically installed in your SL1 system. **NOTE**: You can install multiple PowerPacks with the **Select Action** drop-down list only if each selected PowerPack includes an embedded Installation Key. PowerPacks that do not include embedded Installation Keys will fail to install.

NOTE: The Enable Selective PowerPack Field Protection field on the Behavior Settings page (System > Settings > Behavior) affects how updates behave. If the Enable Selective PowerPack Field Protection checkbox is selected, certain fields in Event Policies, Dynamic Applications, and Device Classes will not be updated.

Configuring Subscription Billing

If your SL1 system is configured to communicate with the ScienceLogic billing server, usage data will be sent automatically from your SL1 system to the ScienceLogic billing server once a day. After the ScienceLogic billing server receives the usage data, SL1 will automatically mark the license usage file as delivered.

Sending usage data to the ScienceLogic billing server ensures that your bill is accurate and that ScienceLogic can continue making improvements to the SL1 products.

To determine if you have correctly configured Subscription Billing:

- Go to the System Usage page (System > Monitor > System Usage). Click the [Subscription]button and choose License Data Delivery Status.
- For air-gapped SL1 systems, the value of *Summary Date* should be within the past 48 hours.
- For SL1 systems that connect to ScienceLogic, the value of *Summary Date* should be within the past 48 hours and the value of *Delivery Status* is 1.

For details on configuring subscription billing, see the **Subscription Billing** manual.

Chapter

6

Monitoring and Maintaining SL1

Overview

This chapter describes how to manage user access, manage scheduled tasks, and more.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon (=).
- To view a page containing all the menu options, click the Advanced menu icon (…).

This chapter includes the following topics:

Monitoring and Managing User Access	184
Managing Scheduled Tasks	187
Monitoring Overall System Usage and Statistics	190
Viewing an Overview of All Events	191
Viewing Events by Appliance and Event Source	193

Monitoring and Managing User Access

The Access Sessions page allows administrators to monitor user logins and logouts to the user interface.

From this page, you can also:

- End a user's session.
- View a list of accounts that are locked out of the user interface due to invalid username and password.
- Unlock accounts that are locked out of the user interface.

Viewing Information about Each Access Session

The **Access Sessions** page displays a list of recent logins to the user interface. To view the **Access Sessions** page:

1. Go to the Access Sessions page (System > Monitor > Access Logs).

User Account	Last Address	State	Login Time Last-Ht Time	Logout Time	Session Duration	Session ID
em7admin	10.128.36.60	Logged In	2017-05-02 16:27:15 2017-05-02 16:	27:15	14 si	ecs 64bmr9tlaqabv20aijgokeorc7
em7admin	10.128.36.59	Logged In	2017-05-02 12:12:53 2017-05-02 12:	12:53	4 hrs 14 mins 36 s	ecs 2dd1eumog80i5bl2k2757dk35
em7admin	10.128.36.67	Logged Out	2017-05-01 13:13:11 2017-05-01 16:	50:55 2017-05-01 16:50:55	3 hrs 37 mins 44 s	ecs qql3rd490g3fnaanmlg7alf3d6
4. em7admin	10.128.36.67	Logged Out	2017-05-01 10:30:09 2017-05-01 11:	14:24 2017-05-01 11:44:24	1 hr 14 mins 15 s	ecs brfinp2si0n6bh63f08og168u6
5. em7admin	10.128.36.69	Expired	2017-04-28 15:17:59 2017-04-28 15:	17:59 2017-04-28 15:17:59	0 5	ecs jg0eo41mtbaa26uo3bh0ciqsn4
5. em7admin	10.128.39.251	Expired	2017-04-26 15:47:57 2017-04-26 15:	47:57 2017-04-26 15:47:57	0 s	ecs jm23accrd5o8ftman9h6k538g2
7. em7admin	10.128.36.102	Expired	2017-04-25 09:03:21 2017-04-25 09:	03:21 2017-04-25 09:03:21	0 5	ecs rj6qasl0jhtjokh0ld9f4pgpb1
3. em7admin	10.128.39.224	Logged Out	2017-04-21 12:48:52 2017-04-21 15:	10:40 2017-04-21 15:10:40	2 hrs 21 mins 48 s	ecs jvbcu3np3iburda7ignfadnbg0
9. em7admin	10.128.39.216	Expired	2017-04-21 13:02:34 2017-04-21 13:	02:34 2017-04-21 13:02:34	0 s	ecs 5olkottecs7o75ab1gloith2b1
), em7admin	10.128.36.68	Logged Out	2017-04-20 11:46:49 2017-04-20 16:	02:13 2017-04-20 16:02:13	4 hrs 15 mins 24 s	ecs 98lbgbuphgunca88thgb7gi4a0
1. em7admin	10.128.39.182	Expired	2017-04-20 15:31:21 2017-04-20 15:	31:21 2017-04-20 15:31:21	0 54	ecs 0p0pqh6q1qg2svo4hhngfl6ff1
2. em7admin	10.128.36.68	Expired	2017-04-20 11:46:48 2017-04-20 11:	16:48 2017-04-20 11:46:48	0 5	ecs ja0n1a74d5cssrsh1aqmucd633
3. em7admin	10.128.36.91	Expired	2017-04-19 12:56:38 2017-04-19 12	56:38 2017-04-19 12:56:38	0 s	ecs 780ns7cmg0e238gtboftnqnoi2
4. em7admin	10.128.36.43	Logged Out	2017-04-18 09:59:26 2017-04-18 16:	17:04 2017-04-18 16:17:04	6 hrs 17 mins 38 s	ecs afnt0gb7032olfk3mu5opiggh6
5. em7admin	10.128.36.53	Expired	2017-04-18 15:22:25 2017-04-18 15:	22:25 2017-04-18 15:22:25	0 s	ecs ikiv2k1kqpv1qdoj7u0cg5bpl5
5. em7admin	10.128.36.53	Expired	2017-04-18 13:45:34 2017-04-18 15:	22:25 2017-04-18 15:22:25	1 hr 36 mins 51 s	ecs ikiv2k1kqpv1qdoj7u0cg5bpl5
7. em7admin	10.128.36.53	Expired	2017-04-18 11:49:16 2017-04-18 13:	45:34 2017-04-18 13:45:34	1 hr 56 mins 18 s	ecs ikiv2k1kqpv1qdoj7u0cg5bpl5
3. em7admin	10.128.39.235	Expired	2017-04-17 12:57:57 2017-04-18 11:	9:16 2017-04-18 11:49:16	22 hrs 51 mins 19 s	ecs ikiv2k1kqpv1qdoj7u0cg5bpl5
9. em7admin	10.128.39.231	Logged Out	2017-04-17 16:28:25 2017-04-17 17:	19:34 2017-04-17 17:19:34	51 mins 9 s	ecs 08uaq2rsr1ucttqihki9kj43o5
), em7admin	10.128.39.219	Expired	2017-04-14 16:13:11 2017-04-14 16:	13:11 2017-04-14 16:13:11	0 s	ecs glb0kl90d4b5m0gtpkoi2u2gm3
1. em7admin	10.128.39.228	Expired	2017-04-14 10:26:50 2017-04-14 11:	80:54 2017-04-14 11:30:54	1 hr 4 mins 4 s	ecs gk8cj5vfm58m0cuhb7363no261
2. em7admin	10.128.39.228	Expired	2017-04-14 11:30:54 2017-04-14 11:	80:54 2017-04-14 11:30:54	0 5	ecs gk8cj5vfm58m0cuhb7363no261
3. em7admin	10.128.39.219	Expired	2017-04-14 10:43:12 2017-04-14 10:	43:12 2017-04-14 10:43:12	0 s	ecs u7hgf4p6nr1hf5jg8s4k3abaj0
4. em7admin	10.128.36.43	Logged Out	2017-04-13 16:28:48 2017-04-13 16:	41:18 2017-04-13 16:41:18	12 mins 30 s	ecs 7nb23ncvb6boho34hespk8i3o1
5. em7admin	10.128.39.142	Expired	2017-04-13 12:22:58 2017-04-13 12:	22:58 2017-04-13 12:22:58	0 s	ecs cgktpavbplksd296knq041us67
5. em7admin	10.128.39.175	Logged Out	2017-04-12 10:29:16 2017-04-12 16:	58:43 2017-04-12 16:58:43	6 hrs 29 mins 27 s	ecs ohtfpmcaajuvqjrmjs1c7jron4

- 2. For each session, the Access Sessions page displays:
 - User Account. Username of person logging in to the user interface.
 - Last Address. IP address from which the user accessed the user interface.
 - State. Current status of the user. The choices are:
 - Active. User is currently logged in to the user interface.
 - Expired. User's session in the user interface was killed.
 - Logged Out. User logged out of the user interface.

- Never Used. User logged in to the user interface and did not perform any tasks before the session was killed.
- Login Time. Date and time at which the user logged in.
- Last-Hit Time. Date and time at which the user last loaded a page in the user interface.
- Logout Time. Date and time at which the user logged out.
- Session Duration. Length of time between login and logout.
- Session ID. Unique numeric ID assigned to each user session.

Deleting a User's Session

From the **Access Sessions** page, you can end a user's session in the user interface. The user must log in again to access the user interface. The status of the session will be "expired".

To end a user's session:

1. Go to the Access Sessions page (System > Monitor > Access Logs).

User Account	Last Address	State	Login Time	Last-Hit Time •	Logout Time	Session Duration	Session ID
em7admin	10.128.36.60	Logged In	2017-05-02 16:27:15	2017-05-02 16:27:15	-	14 secs	54bmr9tlaqabv20aijgokeorc7
m7admin	10.128.36.59	Logged In	2017-05-02 12:12:53	2017-05-02 12:12:53	-	4 hrs 14 mins 36 secs	2dd1eumog80i5bl2k2757dk35
m7admin	10.128.36.67	Logged Out	2017-05-01 13:13:11	2017-05-01 16:50:55	2017-05-01 16:50:55	3 hrs 37 mins 44 secs	qql3rd490g3fnaanmlg7alf3d6
em7admin	10.128.36.67	Logged Out	2017-05-01 10:30:09	2017-05-01 11:44:24	2017-05-01 11:44:24	1 hr 14 mins 15 secs	orfinp2si0n6bh63f08og168u6
em7admin	10.128.36.69	Expired	2017-04-28 15:17:59	2017-04-28 15:17:59	2017-04-28 15:17:59	0 secs .	g0eo41mtbaa26uo3bh0ciqsn4
em7admin	10.128.39.251	Expired	2017-04-26 15:47:57	2017-04-26 15:47:57	2017-04-26 15:47:57	0 secs	m23accrd5o8ftman9h6k538g2
em7admin	10.128.36.102	Expired	2017-04-25 09:03:21	2017-04-25 09:03:21	2017-04-25 09:03:21	0 secs	j6qasl0jhtjokh0ld9f4pgpb1
em7admin	10.128.39.224	Logged Out	2017-04-21 12:48:52	2017-04-21 15:10:40	2017-04-21 15:10:40	2 hrs 21 mins 48 secs	vbcu3np3iburda7ignfadnbg0
em7admin	10.128.39.216	Expired	2017-04-21 13:02:34	2017-04-21 13:02:34	2017-04-21 13:02:34	0 secs	5oikottecs7o75ab1gloifh2b1
em7admin	10.128.36.68	Logged Out	2017-04-20 11:46:49	2017-04-20 16:02:13	2017-04-20 16:02:13	4 hrs 15 mins 24 secs	98lbgbuphgunca88thgb7gi4a0
em7admin	10.128.39.182	Expired	2017-04-20 15:31:21	2017-04-20 15:31:21	2017-04-20 15:31:21	0 secs	DpOpqh6q1qg2svo4hhngfl6ff1
em7admin	10.128.36.68	Expired	2017-04-20 11:46:48	2017-04-20 11:46:48	2017-04-20 11:46:48	0 secs .	a0n1a74d5cssrsh1aqmucd633
em7admin	10.128.36.91	Expired	2017-04-19 12:58:38	2017-04-19 12:56:38	2017-04-19 12:56:38	0 secs	780ns7cmg0e238gtboftnqnoi2
em7admin	10.128.36.43	Logged Out	2017-04-18 09:59:26	2017-04-18 16:17:04	2017-04-18 16:17:04	6 hrs 17 mins 38 secs	afnt0gb7032olfk3mu5oplggh6
em7admin	10.128.36.53	Expired	2017-04-18 15:22:25	2017-04-18 15:22:25	2017-04-18 15:22:25	0 secs	kiv2k1kqpv1qdoj7u0cg5bpl5
em7admin	10.128.36.53	Expired	2017-04-18 13:45:34	2017-04-18 15:22:25	2017-04-18 15:22:25	1 hr 36 mins 51 secs	kiv2k1kqpv1qdoj7u0cg5bpl5
em7admin	10.128.36.53	Expired	2017-04-18 11:49:16	2017-04-18 13:45:34	2017-04-18 13:45:34	1 hr 56 mins 18 secs	kiv2k1kqpv1qdoj7u0cg5bpl5
em7admin	10.128.39.235	Expired	2017-04-17 12:57:57	2017-04-18 11:49:16	2017-04-18 11:49:16	22 hrs 51 mins 19 secs	kiv2k1kqpv1qdoj7u0cg5bpl5
em7admin	10.128.39.231	Logged Out	2017-04-17 16:28:25	2017-04-17 17:19:34	2017-04-17 17:19:34	51 mins 9 secs	08uaq2rsr1ucttqihki9kj43o5
em7admin	10.128.39.219	Expired	2017-04-14 16:13:11	2017-04-14 16:13:11	2017-04-14 16:13:11	0 secs	glb0kl90d4b5m0gtpkoi2u2gm3
em7admin	10.128.39.228	Expired	2017-04-14 10:26:50	2017-04-14 11:30:54	2017-04-14 11:30:54	1 hr 4 mins 4 secs	gk8cj5vfm58m0cuhb7363no261
em7admin	10.128.39.228	Expired	2017-04-14 11:30:54	2017-04-14 11:30:54	2017-04-14 11:30:54	0 secs	gk8cj5vfm58m0cuhb7363no261
em7admin	10.128.39.219	Expired	2017-04-14 10:43:12	2017-04-14 10:43:12	2017-04-14 10:43:12	0 secs	u7hgf4p6nr1hf5jg8s4k3abaj0
em7admin	10.128.36.43	Logged Out	2017-04-13 16:28:48	2017-04-13 16:41:18	2017-04-13 16:41:18	12 mins 30 secs	7nb23ncvb6boho34hespk8i3o1
em7admin	10.128.39.142	Expired	2017-04-13 12:22:58	2017-04-13 12:22:58	2017-04-13 12:22:58	0 secs	gktpavbplksd296knq041us67
em7admin	10.128.39.175	Logged Out	2017-04-12 10:29:16	2017-04-12 16:58:43	2017-04-12 16:58:43	6 hrs 29 mins 27 secs	ohtfpmcaajuvqjrmjs1c7jron4

- 2. In the Access Sessions page, find the session you want to end. Click the checkbox (2) for that session.
- 3. Click the **Select Actions** field (in the lower right of the page) and then select *Kill user session*. Click the **[Go]** button
- 4. Each selected session is ended. The user associated with each selected session is logged out of the user interface. The status of the session changes to "expired".

NOTE: After ending a user's session, that user can immediately log in to the user interface again. To prevent a user from logging in to the user interface, you must disable the user's account. For information on user accounts, see the manual **Organizations and Users**.

Viewing Lockouts and Unlocking Lockouts

If a user enters incorrect login information multiple times in a row, that username, the user's IP address, or both will be locked out of the user interface.

To view lockouts or restore login privileges to locked out users:

- 1. Go to the Access Sessions page (System > Monitor > Access Logs).
- 2. In the Access Sessions page, click the [Lockouts] button.
- 3. The **Account Lockouts** modal page allows administrators to view a list of locked-out accounts and to restore login privileges to locked out users.

Attempt Account From Address Attempt Time Trys 1. ttesterson 192.168.37.12 2012-03-20 18:59:00 3 Image: The start of the	Account Lockouts			Close / Esc
Attempt Account From Address Attempt Time Trys 1. ttesterson 192.168.37.12 2012-03-20 18:59:00 3				
1. ttesterson 192.168.37.12 2012-03-20 18:59:00 3	Accout Lock-Outs - by User	name		
Copyright © 2003 - 2012 ScienceLogic, Inc. All rights reserved.	1. ttesterson	192.168.37.12	2012-03-20 18:59:00	3 💣
Copyright © 2003 - 2012 ScienceLogic, Inc. All rights reserved.				
opping in a zora zorz odenaczegia, ina zni ngila leseved.	Convright © 2003 - 2012 Science	Logic Inc. All rights reserved		
	oopyright o 2000 - 2012 oolende	Logio, mo. An iigno reserved.		

- 4. The Account Lockouts modal page displays the following about each lockout:
 - Attempt Account. Username that caused the lockout.
 - From Address. IP address from which the failed login attempts originated.
 - Attempt Time. Date and time at which lockout occurred.
 - Tries. Number of times user tried to log in to the user interface.
- 5. To remove the lock for the user account and allow logins from the username and/or IP address, click the bomb icon ().

Global Settings for Lockouts

The platform includes global settings that define how lockouts behave. In the *Behavior Settings* page (System > Settings > Behavior), the following fields affect lock-outs:

- Account Lockout Type
- Account Lockout Attempts
- Account Lockout Duration
- Lockout Contact Information

Audit Logs

For additional information about users and their actions in the platform, you can view the **Audit Logs** page. The **Audit Logs** page provides a complete audit trail for the platform. The **Audit Logs** page displays a record of all actions in the platform that are generated by users or by managed elements. For details, see the section on *Audit Logs*.

Managing Scheduled Tasks

The **Schedule Manager** page (Registry > Schedules > Schedule Manager) allows you to view and manage all the scheduled processes you have defined in your system.

You can define scheduled processes in the following pages:

- Report Scheduler. (For more information, see the **Reports** manual.)
- My Work Schedule. (For more information, see the **Organizations and Users** manual.)
- Recurring Ticketing Scheduler. (For more information, see the *Ticketing* manual.)
- Discovery Control Panel. (For more information, see the Discovery and Credentials manual.)
- Dashboards. (For more information, see the **Dashboards** manual.)
- IT Service Editor. (For more information, see the *IT Services* manual.)

- Device Manager. (For more information, see the Device Management manual.)
- Backup Management. (For more information, see the section on Configuration Backups.)

Viewing the List of Schedules

The **Schedule Manager** page (Registry > Schedules > Schedule Manager) displays the following about each schedule:

	Schedule Summary •	Schedule Description	Event ID	sch id	Context	Timezone	Start Time	Duration	Recurrence Interval	End Date	Last Run	Owner	Organization	<u>∨isibility</u>	Enable	헲
1.	SAC Daily Discovery Maint	SAC Daily Discovery Mainter	175	0	Discovery	America/Chicago	2017-10-01 08:00:00	30 minute Ev	ery 2 Days	2018-10-01 08:00:00		AutoRegUser	System	World	Yes	Ī
2.	SAC Daily Report Maint	SAC Daily Asset List Report	158	54	Reports	America/New_York	2017-10-01 08:00:00	30 minute Ev	ery 1 Day	2018-10-01 08:00:00		AutoRegUser	System	World	Yes	
3.	SAC Hourly Ticket Maint	SAC Hourly Ticket Maintenar	155	40	Tickets	America/New_York	2017-10-01 08:00:00	30 minute Ev	ery 24 Hours	2018-10-01 08:00:00		AutoRegUser	System	World	Yes	
		SAC One Time Device Maint		66	Devices	America/New_York	2017-10-01 08:00:00	30 minute			-	AutoRegUser	System	World	Yes	
5.	SAC One Time Dev Maint	SAC One Time Device Maint	t 153	62	Devices	America/New_York	2017-10-01 08:00:00	30 minute				AutoRegUser	System	World	Yes	
		SAC Weekly IT Service Sche		0	IT Services	America/New_York	2017-10-01 08:00:00	30 minute Ev	ery 1 Week	2018-10-01 08:00:00		AutoRegUser	System	World	Yes	
7.	sch_1	sch_1: admin-system-world	166	0	Discovery	America/New_York	2017-10-01 08:00:00	30 minute				em7admin	System	World	Yes	
8.	sch_2	sch_2: admin-system-org	167	0	Discovery	America/New_York	2017-10-01 08:00:00	30 minute				em7admin	System	Organiza	Yes	
9.	sch_4	sch_4: admin-system-world	169	0	Discovery	America/New_York	2017-10-01 08:00:00	30 minute				sac_user1	SAC_Scheduler_To	World	Yes	
D.	sch_5	sch_5: admin-system-org	170	0	Discovery	America/New_York	2017-10-01 08:00:00	30 minute				sac_user1	SAC_Scheduler_Te	Organiza	Yes	
1.	sch_7	sch_7: admin-system-world	172	0	Discovery	America/New_York	2017-10-01 08:00:00	30 minute				sac_user2	System	World	Yes	
2.	sch_8	sch_8: admin-system-org	173	0	Discovery	America/New_York	2017-10-01 08:00:00	30 minute				sac_user2	System	Organiza	Yes	
3.	Scrum Fu Pandas Discover	-	32	0	Discovery	America/New_York	2016-07-25 23:00:00	30 minute Ev	ery 1 Day		2017-01-17 23:30:00	em7admin	System	World	Yes	
4.	Scrummy Bears Discovery		33	0	Discovery	America/New_York	2016-07-25 23:00:00	30 minute Ev	ery 1 Day		2017-01-17 23:30:00	em7admin	System	World	Yes	
5.	System Patch Install - versio		34	682	Patches	UTC	2016-07-26 21:15:00	30 minute Ev	ery 0 Minutes		2016-07-26 21:45:00	em7admin	System	World	Yes	1
6.	System Patch Install - versio		50	1714	Patches	UTC	2016-10-11 18:33:00	30 minute Ev	ery 0 Minutes		2016-10-11 19:03:00	em7admin	System	World	Yes	
7.	System Patch Install - versio		58	2169	Patches	UTC	2016-11-09 21:13:00	30 minute Ev	ery 0 Minutes		2016-11-09 21:43:00	em7admin	System	World	Yes	1
в.	System Patch Install - versio		125	2530	Patches	UTC	2016-12-11 19:28:00	30 minute Ev	ery 0 Minutes		2016-12-11 19:58:00	em7admin	System	World	Yes	

- Schedule Summary. Displays the name assigned to the scheduled process.
- Schedule Description. Displays a description of the scheduled process.
- **Event ID**. Displays a unique, numeric ID for the scheduled process. SL1 automatically creates this ID for each scheduled process.
- sch id. Displays a unique, numeric ID for the schedule. SL1 automatically creates this ID for each schedule.
- Context. Displays the area of SL1 upon which the schedule works.
- Timezone. Displays the time zone associated with the scheduled process.
- Start Time. Displays the date and time at which the scheduled process will begin.
- Duration. Displays the duration, in minutes, which the scheduled process occurs.
- Recurrence Interval. If applicable, displays the interval at which the scheduled process recurs.
- End Date. If applicable, displays the date and time on which the scheduled process will recur.
- Last Run. If applicable, displays the date and time the scheduled process most recently ran.
- Owner. Displays the username of the owner of the scheduled process.
- Organization. Displays the organization to which the scheduled process is assigned.

- Visibility. Displays the visibility level for the scheduled process. Possible values are "Private", "Organization", or "World".
- Enabled. Specifies if the scheduled process is enabled. Possible values are "Yes" or "No".

Enabling or Disabling One or More Schedules

You can enable or disable one or more scheduled process from the **Schedule Manager** page (Registry > Schedules > Schedule Manager). To do this:

1. Go to the **Schedule Manager** page (Registry > Schedules > Schedule Manager).

Schedule Summary *	Schedule Description	Event ID	sch id	Context	Timezone	Start Time	Duration	Recurrence Interval	End Date	Last Run	Owner	Organization		Enable
AC Daily Discovery Maint	SAC Daily Discovery Mainter	175	0	Discovery	America/Chicago	2017-10-01 08:00:00	30 minute Ev	ery 2 Days	2018-10-01 08:00:00		AutoRegUser	System	World	Yes
AC Daily Report Maint	SAC Daily Asset List Report	158	54	Reports	America/New_York	2017-10-01 08:00:00	30 minute Ev	ery 1 Day	2018-10-01 08:00:00		AutoRegUser	System	World	Yes
SAC Hourly Ticket Maint	SAC Hourly Ticket Maintenar	155	40	Tickets	America/New_York	2017-10-01 08:00:00	30 minute Ev	ery 24 Hours	2018-10-01 08:00:00		AutoRegUser	System	World	Yes
AC One Time Dev Maint	SAC One Time Device Maint	165	66	Devices	America/New_York	2017-10-01 08:00:00	30 minute				AutoRegUser	System	World	Yes
AC One Time Dev Maint	SAC One Time Device Maint	153	62	Devices	America/New_York	2017-10-01 08:00:00	30 minute				AutoRegUser	System	World	Yes
AC Weekly IT Service Mai	n SAC Weekly IT Service Sche	160	0	IT Services	America/New_York	2017-10-01 08:00:00	30 minute Ev	ery 1 Week	2018-10-01 08:00:00		AutoRegUser	System	World	Yes
ch_1	sch_1: admin-system-world	166	0	Discovery	America/New_York	2017-10-01 08:00:00	30 minute				em7admin	System	World	Yes
ch_2	sch_2: admin-system-org	167	0	Discovery	America/New_York	2017-10-01 08:00:00	30 minute				em7admin	System	Organiza	Yes
ch_4	sch_4: admin-system-world	169	0	Discovery	America/New_York	2017-10-01 08:00:00	30 minute				sac_user1	SAC_Scheduler_T	World	Yes
ch_5	sch_5: admin-system-org	170	0	Discovery	America/New_York	2017-10-01 08:00:00	30 minute				sac_user1	SAC_Scheduler_T	Organiza	Yes
ch_7	sch_7: admin-system-world	172	0	Discovery	America/New_York	2017-10-01 08:00:00	30 minute				sac_user2	System	World	Yes
ch_8	sch_8: admin-system-org	173	0	Discovery	America/New_York	2017-10-01 08:00:00	30 minute				sac_user2	System	Organiza	Yes
Crum Fu Pandas Discover		32	0	Discovery	America/New_York	2016-07-25 23:00:00	30 minute Ev	ery 1 Day		2017-01-17 23:30:00	em7admin	System	World	Yes
crummy Bears Discovery		33	0	Discovery	America/New_York	2016-07-25 23:00:00	30 minute Ev	ery 1 Day		2017-01-17 23:30:00	em7admin	System	World	Yes
System Patch Install - versi	o	34	682	Patches	UTC	2016-07-26 21:15:00	30 minute Ev	ery 0 Minutes		2016-07-26 21:45:00	em7admin	System	World	Yes
- System Patch Install - versi	o	50	1714	Patches	UTC	2016-10-11 18:33:00	30 minute Ev	ery 0 Minutes		2016-10-11 19:03:00	em7admin	System	World	Yes
System Patch Install - versi	o	58	2169	Patches	UTC	2016-11-09 21:13:00	30 minute Ev	ery 0 Minutes		2016-11-09 21:43:00	em7admin	System	World	Yes
System Patch Install - versi	0	125	2530	Patches	UTC	2016-12-11 19:28:00	30 minute Ev	ery 0 Minutes		2016-12-11 19:58:00	em7admin	System	World	Yes
											[Select Acti Administr			

- 2. Select the checkbox icon for each scheduled process you want to enable or disable.
- 3. Click the **Select Action** menu and choose Enable Schedules or Disable Schedules.
- 4. Click the **[Go]** button.

Deleting One or More Schedules

You can delete one or more scheduled process from the **Schedule Manager** page (Registry > Schedules > Schedule Manager). To do this:

1. Go to the Schedule Manager page (Registry > Schedules > Schedule Manager).

Schedule Summary •	Schedule Description	Event ID	sch_id	Context	Timezone	Start Time	Duration	Recurrence Interval	End Date	Last Run	Owner	Organization		Enable	2
SAC Daily Disa susse Maint	SAC Daily Discovery Mainte	175	0	Discovery	America (Chinana	2017-10-01 08:00:00	20 minute E	verv 2 Davs	2018-10-01 08:00:00		AutoRegUser	System	World	Yes	
SAC Daily Discovery Maint	SAC Daily Asset List Report		54	Reports		2017-10-01 08:00:00	30 minute E		2018-10-01 08:00:00		AutoRegUser	System		Yes	
	SAC Hourly Ticket Maintena		40	Tickets		2017-10-01 08:00:00		very 1 Day	2018-10-01 08:00:00		AutoRegUser	System		Yes	iii
· · · · · · · · · · · · · · · · · · ·	SAC One Time Device Maint		66	Devices	-	2017-10-01 08:00:00	30 minute				AutoRegUser	System		Yes	
	SAC One Time Device Maint		62	Devices	-	2017-10-01 08:00:00	30 minute				AutoRegUser	System		Yes	шř
	SAC Weekly IT Service Sch		0	IT Services		2017-10-01 08:00:00		verv 1 Week	2018-10-01 08:00:00		AutoRegUser	System		Yes	
sch 1	sch 1: admin-system-world		0	Discovery		2017-10-01 08:00:00	30 minute		2010-10-01-00.00.00		em7admin	System		Yes	ыř
sch 2	sch 2: admin-system-org		0	Discovery		2017-10-01 08:00:00	30 minute				em7admin	System	Organiza		
sch_4	sch_4: admin-system-world		0	Discovery		2017-10-01 08:00:00	30 minute				sac_user1	SAC Scheduler T		Yes	шř
sch 5	sch 5; admin-system-org		0	Discovery		2017-10-01 08:00:00	30 minute				sac user1	SAC Scheduler T			1
sch 7	sch 7: admin-system-world		0	Discovery	-	2017-10-01 08:00:00	30 minute				sac user2	System	-	Yes	шř
sch 8	sch 8: admin-system-org		0	Discovery		2017-10-01 08:00:00	30 minute				sac user2	System	Organiza '		11
Scrum Fu Pandas Discover		32	0	Discovery	-	2016-07-25 23:00:00	30 minute E	very 1 Day		2017-01-17 23:30:00	em7admin	System		Yes	шř
Scrummy Bears Discovery		33	0	Discovery		2016-07-25 23:00:00	30 minute E			2017-01-17 23:30:00	em7admin	System		Yes	1
System Patch Install - versio		34	682	Patches		2016-07-26 21:15:00		very 0 Minutes		2016-07-26 21:45:00	em7admin	System		Yes	Шř
System Patch Install - versio		50	1714	Patches	UTC	2016-10-11 18:33:00		very 0 Minutes		2016-10-11 19:03:00	em7admin	System		Yes	1
System Patch Install - versio		58	2169	Patches	UTC	2016-11-09 21:13:00		very 0 Minutes		2016-11-09 21:43:00	em7admin	System		Yes	Шř
System Patch Install - versio		125	2530	Patches	UTC	2016-12-11 19:28:00		very 0 Minutes		2016-12-11 19:58:00	em7admin	System		Yes	11
											[Select Acti				_

- 2. Select the checkbox icon for each scheduled process you want to delete.
- 3. Click the Select Action menu and choose Delete Schedules.
- 4. Click the **[Go]** button.

Monitoring Overall System Usage and Statistics


The System Usage page displays:

- Tables that show the type and number of each type of task performed by SL1
- An optional line graph that displays system usage. To enable the display of this graph, go to the **Behavior Settings** page (System > Settings > Behavior) and uncheck the *Hide Perpetual License Count* checkbox. The graph displays the following metrics over time:
 - **Capacity**. The total monitoring capacity of the system. This value is determined by the license(s) for the Database Server(s) or All-In-One Appliance(s) in the system.
 - Number of Devices. The number of devices currently discovered in the system.
 - **System Usage**. The amount of **Capacity** that the devices in the system are currently using. This value is the sum of the **Device Ratings** for all devices in the system. The **Device Rating** for each device is calculated daily and is based on the number of collections performed for that device.

• If you have a subscription license, you can also generate reports about subscription licensing.

To view the **System Usage** page:

- 1. Go to the **System Usage** page (System > Monitor > System Usage).
- 2. The **System Usage** page appears:




Viewing an Overview of All Events


The **Event Overview** page provides a graphical overview of all events in SL1.

To view the **Event Overview** page:


1. Go to the **Event Overview** page (System > Monitor > Event Overview).




2. The **Event Overview** page displays the following reports:



- Number of Events by Severity. This graph displays event distribution by severity for the last 24 hours and for the last 7 days.
 - The y-axis displays the number of events.
 - The x-axis displays severity.
 - The red line represents events in the last 24 hours.
 - The blue line represents events in the last 7 days.
 - Mousing over a data point in the red line displays the number of events of the specified severity in the last 24 hours.
 - Mousing over a data point on the blue line displays the number of events of the specified severity in the last 7 days.



- Most Common Event Types. This pie graph displays the ten most frequently occurring events for the last 7 days.
 - Each slice of the pie represents an event type. The legend on the left maps each slice color to an event and lists the actual number of events of that type.
 - The graph displays percent. Compared to the total number of occurrences for the top ten events, each slice displays the percent that belong to a specific event.



- Mean Time-to-Resolution. This bar graph displays the number of events generated in the last 24 hours, 7 days, 14 days, and 30 days, and their average resolution time.
 - The y-axis displays the number of events.
 - The x-axis displays the time span. There is a bar for 24 hours, 7 days, 14 days, and 30 days.
 - The red bars represent the actual number of events associated with the time-to-resolution.
 - The blue bars represent the average number of events associated with the time-to-resolution.
 - Mousing over a bar displays the number of events associated with the time-to-resolution.

Viewing Events by Appliance and Event Source

The **Event Statistics** page displays a graph of the number of events processed by a selected Database Server, Data Collector, or Message Collector.

To generate the report:

1. Go to the **Event Statistics** page (System > Monitor > Event Statistics).



- 2. In the **Event Statistics** page, supply values in the following fields:
 - **Appliance**. In the field in the upper left, select from the list of all Database Servers, Data Collectors, and Message Collectors.
 - Event Type. In the field in the upper right, select from the list of event types. The choices are:
 - Syslog. Event was generated from standard system log generated by device.
 - Internal. Event was generated by SL1.
 - Trap. Event was generated by an SNMP trap.
 - Dynamic. Event was generated by a monitoring application running on the device.
 - API. The event was generated by an external API.
 - Email. The event was generated by an incoming email.
- 3. The graph displays the average number of events processed by the selected appliance, for the selected duration.
 - The y-axis displays the average number of events.
 - The x-axis displays time. The increments vary depending upon the selected data type (from the **[Options]** menu) and the date range (from the **Date Range Selection** pane).
 - Mousing over any point in any line displays the value at that time-point in the **Mouse-over** column in the **Data Table** pane.

• You can use your mouse to scroll the report to the left and right.

Chapter



Admin Notifier

Overview

This chapter describes the **Admin Notifier**, which alerts administrator users upon login to any issues on monitored SL1 appliances that could lead to an outage (for example, if the database is running out of space). After login the Admin Notifier displays a banner if any of the filtered events are found so that you can take action on the issues immediately.

This chapter includes the following topics:

How Does the Admin Notifier Work?	196
Admin Notifier in the Classic SL1 User Interface	197
What Issues Does the Admin Notifier Monitor?	197

How Does the Admin Notifier Work?

When certain events are present that could lead to a system outage, the Admin Notifier appears in SL1 for administrator users at login and persists as a banner at the top of the screen until no qualifying events are found. (If you are using the classic SL1 user interface, the Admin Notifier has additional functions. See Admin Notifier in the Classic SL1 User Interface.) The Admin Notifier monitors your SL1 appliances for the events listed in the table in What Issues Does the Admin Notifier Monitor.

Upon login to SL1, administrators will see the following modal if qualifying events are found. Click **[OK]** to continue or click **[View Events]** to go to an admin Events page.

System Warning		
You have 6 events which may lead	i to SL1 sy	stem failure.
	ок	View Events

The System Warning banner, shown below, will persist across the user interface until all of the qualifying events have been acknowledged.

88	۵	ORGANIZATION	SEVERITY	NAME	MESSAGE	AGE	TICKET ID	COUNT	EVENT NOTE	MASKED EVENTS	ACKNOWLEDGE	CLEAR	0
▲	~	System	Critical	jtaylor-VIP	Appliance, jtaylor-db1-166-191 has differing variables	1 day 2 hours		27	Ð	Q Masked	✓ Acknowledge	X Clear] _
	~	System	Critical	junylor-VIP	Appliance, jtaylor-db2-166-192 has differing variables	1 day 2 hours		27	Ð	Q Masked	 Acknowledge 	X Clear] _
0	~	System	 Major 	jtaylor-VIP	Configuration file /etc/drbd.dl/0.res does not match ac.	1 day 2 hours		27	E	Q Masked	✓ Acknowledge	X Clear) .
ඩ	~	System	Major	jtaylor-VIP	Configuration file /etc/my.cnl.d/silo_mysql.cnl does no.	1 day 2 hours		27	Ð	Q Masked	✓ Acknowledge	X Clear) .
5	~	System	Major	jtaylor-VIP	Configuration file /etc/silo.conf does not match across	1 day 2 hours		27	Ð	Q Masked	✓ Acknowledge	× Clear] .
ê.	~	System	Critical	jtaylor-db1-166-191	/var: File system usage exceeded critical threshold: Lim.	21 hours 54 mins		88	Ð		✓ Acknowledge	X Clear	

To interact with the banner, you can click one of the buttons that appears on the banner:

- **Dismiss**. Hides the banner for the duration of your session or until another qualifying event is logged. If qualifying events are still present, the banner will reappear upon your next login.
- **Snooze**. Hides the banner for 15 minutes. If qualifying events are still present after 15 minutes, the banner will reappear.
- View. Opens the Events page with a filter applied that shows only the admin events.

Admin Notifier in the Classic SL1 User Interface

The System Warning banner appears as shown below in the classic SL1 user interface.

	is <u>V</u> iews	Events	Tickets Reports Begistry System Preference	es .									_
Console Events F	Found [6]								Action	s Klosk		Reset	Guid
View: 0 Save D	Delete 🦄 🗄 Search: 🛛	Organization	•									ause	Refre
Organization -	Name -	Type	Event Message	Severity -	Acknowledged	Ticket	Age / Elapsed	Last Detected +	EIQ	Source	Count	Notify	
L				[s=Healty 1				A 1)
System	Jtaylor-db1-166-191	Device	Arr: File system usage exceeded critical threshold: Limit: 1.0%, Actual: 10.00%	Ontical	Ø _	-	21 hrs 53 mins	2021-03-05 15:15:11	208	Internal	88	-	08
System	taylor-VIP	Device	Appliance, itaylor-db1-166-191 has differing variables in the mysql.siteconif, silo_mysql.	Ottoal	o _	-	1 day 2 hrs	2021-03-05 15:00:43	63	Dynamic Dynamic	27	-	88
System	taylor-VIP	Device	Appliance, jtaylor-db2-166-192 has differing variables in the siloconf.sileconfig file(s)	Ortical	0	-	1 day 2 hrs	2021-03-05 15:00:43	64	Dynamic	27	-	08
System	al jtaylor-VIP	Device	Configuration file /etc/silo.conf does not match across DB appliances.	Major	0	-	1 day 2 hrs	2021-03-05 15:00:43	67	Dynamic	27		03
System	#Jaylor-VIP	Device	Configuration file /etc/my.cnf.d/silo_mysql.cnf does not match across DB appliances.	Major	Ø _	-	1 day 2 hrs	2021-03-05 15:00:43	66	Dynamic	27	-	03
System	at jtaylor-VIP	Device	Configuration file /etc/drbd.dir0.res does not match across DB appliances.	Major	Ø _	-	1 day 2 hrs	2021-03-05 15:00:43	65	Dynamic	27	-	03
													-
													Ack

What Issues Does the Admin Notifier Monitor?

The following table includes the events that might appear in the Admin Notifier, the Dynamic Application that triggers the event, the severity of the event, and references that can help you resolve the problem before it causes an outage. Knowledge Base Articles (KBA) are found on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).

Event Name	Dynamic Application	Severity	Reference
Support: Database Config - License expires in less than 14 days	Support: Database Configuration	Critical	Renew license. Seethe chapter on <i>Licensing and Configuring an</i> <i>Appliance</i> in the <i>Installation</i> manual or Knowledge Base Article 4978 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: DRBD Proxy License Expiration Eminent	Support: DRBD Proxy License Expiration	Critical	Renew license. See the chapter on Licensing and Configuring an Appliance in the Installation manual or Knowledge Base Article 4979 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
InnoDB Space: Critical Threshold	Support: InnoDB Size	Critical	See the chapter on Device Thresholds and Data Retention in the Device Management manual or Knowledge Base Article 49870 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: SL1 Config - Appliance Not Licensed	Support: SL1 Configuration	Critical	License your SL1 appliance. See the chapter on <i>Licensing and Configuring an</i> <i>Appliance</i> in the <i>Installation</i> manual or Knowledge Base Article 4981 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: MariaDB Config - InnoDB Force Recovery Non-Zero Value	Support: MariaDB Configuration	Critical	See Knowledge Base Article 4982 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Poller: File system usage exceeded (critical) threshold	Internal	Critical	See Knowledge Base Article 4983 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: Appliance Validation Not Monitored	Support: Appliance Validation	Major	Discover all appliances as devices.
Support: Appliance Validation Minimum AIO Requirements Not Met	Support: Appliance Validation	Major	See Knowledge Base Article 4984 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: Appliance Validation Minimum AP Requirements Not Met	Support: Appliance Validation	Major	See Knowledge Base Article 4985 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: Appliance Validation Minimum DB Requirements Not Met	Support: Appliance Validation	Major	See Knowledge Base Article 4986 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).

Event Name	Dynamic Application	Severity	Reference
Support: Appliance Validation Minimum DC Requirements Not Met	Support: Appliance Validation	Major	See Knowledge Base Article 4987 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: Appliance Validation Minimum MC Requirements Not Met	Support: Appliance Validation	Major	See Knowledge Base Article 4988 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: API Message Backlog Has Exceeded Threshold	Support: Async Message Backlog Performance	Major	See Knowledge Base Article 4989 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: Syslog Message Backlog Has Exceeded Threshold	Support: Async Message Backlog Performance	Major	See Knowledge Base Article 4990 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: Trap Message Backlog Has Exceeded Threshold	Support: Async Message Backlog Performance	Major	See Knowledge Base Article 4991 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: Cluster Resource Template Outdated	Support: Cluster Configuration	Major	See Knowledge Base Article 4992 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: DNS Resolution - Invalid Response	Support: Database Configuration	Major	See Knowledge Base Article 4993 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: SL1 will run out of space in less than 14 days	Support: DB Space Estimator	Critical	See Knowledge Base Article 4994 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Mail Backlog: Critical	Support: Mail Backlog	Critical	See Knowledge Base Article 4995 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: MariaDB Config - File per table	Support: MariaDB Configuration	Critical	See Knowledge Base Article 4996 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: MariaDB Connections High - Critical	Support: MariaDB Performance	Critical	See Knowledge Base Article 4997 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: High Rows Behind High	Support: Rows Behind	Critical	See Knowledge Base Article 4998 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: Medium	Support: Rows Behind	Major	See Knowledge Base Article 4999 on the ScienceLogic

Event Name	Dynamic Application	Severity	Reference
Rows Behind High			Support website (https://support.sciencelogic.com/s/knowledge).
Siteconfig Check: Differing Variable	Support: Siteconfig Check	Critical	See Knowledge Base Article 5000 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Siteconfig Check: Missing Variable	Support: Siteconfig Check	Critical	See Knowledge Base Article 5001 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: SL1 Config - Bad Timezone	Support: SL1 Configuration	Critical	Reset timezone to UTC. See Knowledge Base Article 5002 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: SL1 Config - Pause file detected	Support: SL1 Configuration	Critical	The system is not currently collecting any information. See Knowledge Base Article 5003 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: Out of Memory - Process Has Been Killed	Syslog	Major	See Knowledge Base Article 5004 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: MariaDB Error	Syslog	Major	See Knowledge Base Article 5005 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).

For more information about Data Pulls and Rows Behind, watch the video at https://www.youtube.com/watch?v=DfH5hhlpHeg.

Chapter

7

Diagnostic Tools

Overview

This chapter describes some diagnostic tools for troubleshooting and diagnosing problems in SL1.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon (三).
- To view a page containing all the menu options, click the Advanced menu icon (…).

This chapter includes the following topics:

ScienceLogic SL1 Self-Monitoring	
Viewing Information About ScienceLogic Processes	
Viewing the List of ScienceLogic Processes	203
Searching and Filtering the List of ScienceLogic Processes	205
Editing the Parameters of a ScienceLogic Process	
Debugging a Process and Viewing Debug Logs	
Viewing Information About Unhandled Exceptions	
Viewing the List of Unhandled Exceptions	
Searching and Filtering the list of Unhandled Exceptions	211
Saving the Unhandled Exception to the Local Computer	
Viewing the Output of the System Status Script	
Viewing the Database Tables on the Database Server	
Accessing the Database Tool	213

Disabling Normalization, Re-Enabling Normalization, and Backfilling Raw Data	
Enable Logging for Data Pull Storage Objects	
Enable	
Disable	
Controlling Log Settings	
Setting UI Developer Log Levels	
Setting UI/REST MySQL Query Log Levels	
Configuring Advanced Log Settings	
Downloading Logs from the PHP Developer Logs page	

ScienceLogic SL1 Self-Monitoring

SL1 includes a self-monitoring PowerPack that is included by default with SL1 releases. This PowerPack is called "ScienceLogic Support Pack".

This self-monitoring PowerPack:

- ensures all SL1 appliances are monitored and running the same version of SL1
- ensures that all SL1 appliances appear in the Device Manager page (Registry > Devices > Device Manager)
- ensures that configuration files on SL1 appliances are kept in sync
- ensures that configuration files on SL1 clusters are kept in sync
- monitors the health and configuration of MariaDB
- generates alerts when system resources like disk-space are approaching capacity
- monitors DNS entries for Database Servers and All-In-One appliances
- monitors long-running processes and queries
- monitors out-of-memory conditions
- ensures that CRM and corosync configurations are up to date
- ensures that configuration files match among HA Database Servers
- monitors crucial SL1 processes like datapull and config_push
- monitors "rows behind" situations and generates alerts
- monitors and fixes backlogs of email messages
- generates alerts if any of the following files differ:
 - /etc/my.cnf.d/silo_mysql.cnf
 - /etc/silo.conf
 - /etc/siteconfig/mysql.siteconfig
 - /etc/siteconfig/siloconf.siteconfig

Viewing Information About ScienceLogic Processes

The **Process Manager** page allows you to view a list of ScienceLogic processes and optionally define parameters for those processes. These processes gather, manipulate, and publish the data used in SL1.

CAUTION: ScienceLogic recommends that you do not edit the values in this page without first consulting ScienceLogic. Incorrect values can severely disrupt ScienceLogic platform operations.

ScienceLogic processes fall into three scheduling categories or Frequencies:

- Asynchronous. The process is launched in response to a system event or user request.
- Scheduled. The process is launched on a regular schedule.
- Always. The process always runs while SL1 is running.

SL1 performs many tasks in parallel:

- Through a modular design, allowing functions to be distributed to multiple processing platforms.
- Through multi-processing, where multiple instances of a process run simultaneously.

The Process Manager page allows you to view and edit the parameters of system processes.

Viewing the List of ScienceLogic Processes

To view the list of process in the **Process Manager** page:

1. Go to the **Process Manager** page (System > Settings > Admin Processes).

	Process Name •	Program File	Frequency		Async Throttle		Time Factor	Run Length	State	Debug	<u>ID</u>	Edited By	Edit Date
[All
	Application & Report Server: Remote diagnostic	em7_httpd_admin	0						Enabled	Disabled	54	em7admin	2009-06-29 14:06:59
1	PApplication & Report Server: Scheduled Report Runner	scheduled_report_run.py	-1		25		15	15	Enabled	Disabled	58	em7admin	2009-07-14 12:20:00
Ĵ	Application & Report Server: Secure	em7_httpsd	0						Enabled	Disabled	53	em7admin	2009-06-29 14:06:59
1	Application & Report Server: Standard	em7_httpd	0						Enabled	Disabled	52	em7admin	2009-06-29 14:06:59
Į,	PData Collection: Async Dynamic App Collection	async_dynamic_collect.py	-1		2		15	15	Enabled	Disabled	129	em7admin	2010-03-04 11:53:41
Ĵ,	PData Collection: Availability	availability collect.py	5	2		30	5	30	Enabled	Disabled	10	em7admin	2009-06-29 14:06:59
Ĵ.	PData Collection: CDP Collection	cdp_collect.py	120	0		30	0	120	Enabled	Disabled	33	em7admin	2010-03-26 10:37:39
ĩ	PData Collection: Critical Availability	em7_cavaild	0						Enabled	Disabled	47	em7admin	2009-06-29 14:06:59
Ĩ	PData Collection: Critical Port	em7_pollc	0						Enabled	Disabled	48	em7admin	2009-06-29 14:06:59
ī	PData Collection: DNS Policy Monitoring	dns collect.py	5	2		30	5	30	Enabled	Disabled	29	em7admin	2009-06-29 14:06:59
Ĩ	PData Collection: Dynamic App	dynamic_collect.py	1	0		20	15	16	Enabled	Disabled	11	em7admin	2009-06-29 14:06:59
1	PData Collection: Dynamic Refresh	dynamic_check.py	1440	200		30	0	1440	Enabled	Disabled	28	em7admin	2009-06-29 14:06:59
Ĩ	PData Collection: E-Mail Round-Trip	email_rt_collect.py	5	3		30	0	5	Enabled	Disabled	30	em7admin	2009-06-29 14:06:59
1	PData Collection: Filesystem statistics	filesystem_stats_collect.py	5	0		30	0	5	Enabled	Disabled	32	em7admin	2009-06-29 14:06:59
Ĩ	PData Collection: Host Filesystem Inventory	filesystem_inventory_collect.py	120	44		30	0	120	Enabled	Disabled	31	em7admin	2009-06-29 14:06:59
1	PData Collection: Interface Bandwidth	if_collect.py	1	0		20	10	11	Enabled	Disabled	12	em7admin	2009-06-29 14:06:59
Ĩ	PData Collection: L3 Topology Collection	I3topology_collect.py	120	90		30	1	240	Enabled	Disabled	34	em7admin	2010-03-26 10:37:39
1	PData Collection: OS Process	process_collect.py	120	0		20	0	120	Enabled	Disabled	14	em7admin	2009-06-29 14:06:59
Ī	PData Collection: OS Process Check	process_check.py	5	4		20	2	15	Enabled	Disabled	15	em7admin	2009-06-29 14:06:59
1	PData Collection: OS Service	service_collect.py	120	20		20	0	120	Enabled	Disabled	16	em7admin	2009-06-29 14:06:59
Į	PData Collection: OS Service Check	service_check.py	5	0		30	2	15	Enabled	Disabled	17	em7admin	2009-06-29 14:06:59
1	PData Collection: RSS Event Feed	rss_collect.py	10	0		30	0	10	Enabled	Disabled	23	em7admin	2009-06-29 14:06:59
Ĩ	PData Collection: SNMP Detail	snmp_detail_collect.py	5	0		30	0	5	Enabled	Disabled	24	em7admin	2009-06-29 14:06:59
1	PData Collection: TCP Port Monitor	port_collect.py	5	0		30	0	5	Enabled	Disabled	20	em7admin	2009-06-29 14:06:59
Ĵ	PData Collection: Topology	topology collect.py	60	12		30	0	60	Enabled	Disabled	25	em7admin	2009-06-29 14:06:59

- 2. The **Process Manager** page displays information about each ScienceLogic process. The **Process Manager** page displays the following for each process:
 - Process Name. Name of the process.
 - Program File. Name of the executable file associated with the process.
 - Frequency. Frequency with which the platform launches the process. Possible values are:
 - Asynchronous. The process is launched in response to a system event or user request.
 - Always. The process always runs while SL1 is running.
 - Scheduled. The process runs at intervals ranging from 1 Minute to Daily.
 - *Runtime Offset*. This field applies only to scheduled processes and allows the platform to stagger the launch of a process. The field specifies the number of minutes after the default scheduled time to execute a process. The default scheduled time at which processes are initially executed is midnight UTC. So if a process has a *Frequency* of 5 *Minutes* and the *Runtime Offset* is set to "2", the process will execute at two minutes past UTC midnight, seven minutes past UTC midnight, 12 minutes past UTC midnight, etc. Choices range from 0–1439.
 - Async Throttle. This field applies only to asynchronous processes. This field indicates the number of jobs per process that can run simultaneously.
 - **Batch Factor**. This field applies only to scheduled processes and determines how many multithreaded child processes are spawned on each execution of the process.

number of tasks a process is responsible for completing/**Batch Factor** = number of child processes that will be spawned

- The number of tasks is typically determined by the number of devices the process is collecting data from.
- The maximum number of child processes is limited by the number of CPUs installed in the SL1 appliance that runs the process.

NOTE: **Batch Factor** defines the maximum number of worker processes or child processes. This value has precedence over the value specified in the section of this manual on **Tuning Collector Groups in the silo.conf File**.

• *Time Factor*. Determines how long the process can run before being stopped by the process manager. This setting only applies to asynchronous processes and scheduled processes. For asynchronous processes, this is the length of time an instance of the process can run. For scheduled processes, the value of *Time Factor* is used to calculate *Run Length*.

```
(Frequency * Time Factor) + Frequency = Run Length
```

For example, suppose a process runs every 15 minutes (as specified in the *Frequency* field). A *Time Factor* of 2 means the process is allowed to run for 45 minutes. A *Time Factor* of 0 means the process is allowed to run for 15 minutes.

- **Run Length**. Specifies how long the process can run before being stopped by the process manager. This number is based on the **Time Factor** for the process.
- State. Current operational state of the process. Possible values are:
 - Enabled. Process can run.
 - Disabled. Process cannot run.
- **Debug**. Specifies whether debugging information is enabled for the process. For more details on debugging a process, see the section **Debugging a Process**.
- ID. Unique numeric ID assigned to each process by SL1.
- Edited By. Date and time the process settings were last edited.
- Edit Date. Date and time the process settings were last edited.

Searching and Filtering the List of ScienceLogic Processes

The **Process Manager** page includes 13 filters, in the top row in the list of processes. You can specify one or more parameters to filter the display of processes. Only processes that meet all the filter criteria will be displayed in the **Process Manager** page.

You can filter by one or more of the following parameters. The list of processes is dynamically updated as you select each filter.

- For each filter except *Edit Date*, you must enter text to match against. SL1 will search for processes that match the text, including partial matches. Text matches are not case-sensitive. You can use the following special characters in each filter:
 - , (comma). Specifies an "or" operation. For example:

"dell, micro" would match all values that contain the string "dell" OR the string "micro".

• & (ampersand). Specifies an "and" operation. For example:

"dell & micro" would match all values that contain the string "dell" AND the string "micro".

• ! (exclamation mark). Specifies a "not" operation. For example:

"!dell" would match all values that do not contain the string "dell".

- **Process Name** You can enter text to match, including special characters (comma, ampersand, and exclamation mark), and the **Process Manager** page will display only processes that have a matching name.
- **Program File**. You can enter text to match, including special characters (comma, ampersand, and exclamation mark), and the **Process Manager** page will display only processes that have a matching program file.
- **Frequency**. You can enter text to match, including special characters (comma, ampersand, and exclamation mark), and the **Process Manager** page will display only processes that have a matching frequency number.

- **Runtime Offset**. You can enter text to match, including special characters (comma, ampersand, and exclamation mark), and the **Process Manager** page will display only processes that have a matching runtime offset.
- Async Throttle. You can enter text to match, including special characters (comma, ampersand, and exclamation mark), and the **Process Manager** page will display only processes that have a matching throttle number.
- **Batch Factor**. You can enter text to match, including special characters (comma, ampersand, and exclamation mark), and the **Process Manager** page will display only processes that have a matching batch factor.
- *Time Factor*. You can enter text to match, including special characters (comma, ampersand, and exclamation mark), and the **Process Manager** page will display only processes that have a matching time factor.
- **Run Length**. You can enter text to match, including special characters (comma, ampersand, and exclamation mark), and the **Process Manager** page will display only processes that have a matching run length.
- State. You can enter text to match, including special characters (comma, ampersand, and exclamation mark), and the **Process Manager** page will display only processes that have a matching state ("Enabled" or "Disabled").
- **Debug**. You can enter text to match, including special characters (comma, ampersand, and exclamation mark), and the **Process Manager** page will display only processes that have a matching debug state ("Enabled" or "Disabled").
- *ID*. You can enter text to match, including special characters (comma, ampersand, and exclamation mark), and the **Process Manager** page will display only processes that have a matching ScienceLogic process ID.
- *Edited By*. You can enter text to match, including special characters (comma, ampersand, and exclamation mark), and the **Process Manager** page will display only processes that have a matching "created by" or "edited by" value.
- *Edit Date*. You can select from a list of time periods. The **Process Manager** page will display only processes that have been created or edited within that time period:
 - All. Display all processes that match the other filters.
 - Last Minute. Display only processes that have been edited within the last minute.
 - Last Hour. Display only processes that have been edited within the last hour.
 - Last Day. Display only processes that have been edited within the last day.
 - Last Week. Display only processes that have been edited within the last week.
 - Last Month. Display only processes that have been edited within the last month.
 - Last Year. Display only processes that have been edited within the last year.

Editing the Parameters of a ScienceLogic Process

To view details about a specific process or edit the settings for a specific process:

CAUTION: ScienceLogic recommends that you do not edit the values in this page without first consulting ScienceLogic. Incorrect values can severely disrupt ScienceLogic platform operations.

- 1. Go to the **Process Manager** page (System > Settings > Admin Processes).
- 2. In the **Process Manager** page, find the process you want to edit. Click its wrench icon (*P*).

Process Name Data Collection: Dynamic Refresh Program File	C [Dail	Frequency y] Runtime Offset (Mins.)	▼ 😔	Appliance Types 😧 All-In-One Server [1] 🗹
dynamic_check.py Operating State	(203 (203	<u> </u>	v 0 v 0	Database [2] Administration Portal [3] Customer Portal [4] Data Online Invite [4]
Debug Mode	• 69 [0]	Time Factor (Mins.)	 	Data Collection Unit [5] 🗹 Message Collection Unit [6] 🗌 Integration Server [7] 🗌
[Disabled]	• <u>10</u>		_	Integration Server [7] Storage Node [8] Compute Node [9]

- 3. The Process Editor page appears and is populated with values from the selected process.
 - Process Name. Name of the process. This field is read-only and cannot be changed.
 - **Program File**. Name of the executable file associated with the process. This field is read-only and cannot be changed.
 - **Operating State**. Current operational state of the process. Specifies whether the process is enabled and able to run. Select from the drop-down list. The choices are:
 - Enabled. Process can run.
 - Disabled. Process cannot run.
 - **Debug Mode**. Enables or disables debugging information for a process. For more details on debugging a process, see the section **Debugging a Process**.

NOTE: You cannot enable debug mode for the process Message Collection: SNMP Trap.

- **Frequency**. This field appears only for scheduled processes and asynchronous processes. Specifies the frequency with which SL1 launches the process. Select from the drop-down list. The choices are:
 - Asynchronous. For asynchronous processes, this is the only available option. You cannot edit the frequency.
 - Scheduled. For scheduled processes, you can edit the frequency. You can select from intervals ranging from 1 Minute to Daily.

NOTE: If a process is set to a frequency of Asynchronous or Always, this field cannot be changed. If a process is set to a time interval, this field cannot be changed to Asynchronous or Always.

- Async Throttle. This field appears only for asynchronous processes. This field indicates the number of jobs per process that can run simultaneously. This setting only applies to asynchronous processes.
- **Runtime Offset**. This field only appears for scheduled processes. This field allows SL1 to stagger the launch of a process. The value specified in this field specifies minutes after the default scheduled time for a process. For example, if a process has a **Frequency** of 5 Minutes and the **Minute Offset** is set to "2", the process will execute at two minutes past the hour, seven minutes past the hour, 12 minutes past the hour, 17 minutes past the hour, etc. Choices range from 0–1439.
- **Batch Factor**. This field applies only to scheduled processes and determines how many multithreaded child processes are spawned on each execution of the process.

number of tasks a process is responsible for completing/**Batch Factor** = number of child processes that will be spawned

- The number of tasks is typically determined by the number of devices the process is collecting data from.
- The maximum number of child processes is limited by the number of CPUs installed in the SL1 appliance that runs the process.

NOTE: *Batch Factor* defines the maximum number of worker processes or child processes. This value has precedence over the value specified in the section of this manual on *Tuning Collector Groups in the silo.conf File*.

- *Time Factor*. This field appears only for scheduled processes and asynchronous processes. This field determines how long a process can run before being killed.
 - For scheduled processes, SL1 uses the formula (*Frequency* * *Time Factor*) + *Frequency*.

For example, suppose a process runs every 15 minutes. A factor of 2 means the process is allowed to run for 45 minutes. Factor of 0 means process is allowed to run for 15 minutes.

- For asynchronous processes, SL1 simply uses the value in this field as the number of minutes a process can run. This field does not appear for processes that are always running.
- Appliance Types. Specifies the appliance types where the process is allowed to run.

NOTE: All changes to the settings in the **Process Manager** page are logged in the **Audit Logs** page (System > Monitor > Audit Logs). The associated log entry will specify the user who altered a process, the process that was altered, and which settings for the process were changed.

4. If you make changes to one or more fields, click the **[Save]** button to save your changes.

Debugging a Process and Viewing Debug Logs

When you debug a process, you tell SL1 to use verbose logging for that process. You can then view SL1 log file to view the logs.

There might be circumstances where you have narrowed down a problem to a specific ScienceLogic process (for example, based on an error message or event). When this happens, you might find it helpful to turn on debugging for that process and view the debug logs.

WARNING: ScienceLogic recommends that you enable the debug option only while troubleshooting a problem and that you then immediately turn off debugging when you have completed troubleshooting. Don't leave the debug option enabled during normal operation of SL1. When you turn on debugging, SL1 will run significantly more slowly.

NOTE: You cannot enable debug mode for the process Message Collection: SNMP Trap.

To enable the debug option for a process:

- 1. In the **Process Manager** page, find the process you want to edit. Select its wrench icon (*P*).
- 2. The **Process Editor** page appears and is populated with values for the selected process.
- 3. Edit the following field:
 - **Debug**. Enables or disables debugging information for a process. Select Enabled.
- 4. Click the [Save] button in the Process Editor page.
- Log in to the console of the appliance where the process is running. Alternately, you can use SSH to open a shell session on the appliance. Log in as *em7admin* with the appropriate password. The default password is *em7admin*.

TIP: To view a list of IP addresses for all appliances in your system, go to the **Appliance Manager** page (System > Settings > Appliances).

6. If the process you are debugging is a process that has a *Frequency* of *Always*, you must restart the process to make it pick up the new debug status (enabled). To restart the process, enter the following at the shell prompt:

sudo service process_name restart
For example, if you were debugging the process for the event engine, you would enter:

```
sudo service em7_event restart
```

- 7. Navigate to the directory **/var/log/em7**. View the file **silo.log**. The most recent entries will be posted at the end of the file.
- 8. After you have finished troubleshooting the process, remember to disable debugging. If the process has a **Frequency** of Always, you must restart the process to make it pick up the new debug status (disabled).

Viewing Information About Unhandled Exceptions

An **exception** specifies that something happened "out of the norm" that is preventing the software from executing the next step. Exceptions are a specific type of error, usually the result of invalid input, missing input, or a network error that prevents communication between software modules. For most exceptions, SL1 will handle the exception by logging a specific error in the System Logs and will continue to run the process. However, **if the platform does not handle the exception**, the process will stop running, and SL1 will generate an error message describing **the unhandled exception**.

Viewing the List of Unhandled Exceptions

To view the list of unhandled exceptions for all appliances:

- 1. Go to the **Unhandled Exceptions** page (System > Monitor > Unhandled Exceptions).
- 2. The **Unhandled Exceptions** page displays the following for each unhandled exception:

	Exception Filename	Line	Exception Information	First Occurrence	Last Occurrence +	Count
				All	All	
	/usr/local/lib/python2.6/multiprocessing/pool.py	422	Traceback (most recent call last): File "/usr/local/silo/proc/silo common/misc.py", line 433, in n	2012-02-25 19:00:57	2012-03-21 13:00:43	116
j	/usr/local/silo/proc/silo db/normalizers/dynamic app normalize	357	izip argument #1 must support iteration	2012-03-20 10:01:00	2012-03-20 10:01:00	1
	/usr/local/silo/proc/silo_db/normalizers/dynamic_app_normalize	357	izip argument #1 must support iteration	2012-03-16 17:00:35	2012-03-16 17:00:35	1
	/usr/local/silo/proc/silo_db/normalizers/dynamic_app_normalize	357	izip argument #1 must support iteration	2012-03-13 20:01:18	2012-03-13 20:01:18	1

- Exception Filename. Full path of the file where the exception occurred.
- Line. Line number of the line in the file where the exception occurred.
- Exception Information. Error message associated with the exception.
- First Occurrence. Date and time of the first occurrence of the exception.
- Last Occurrence. Date and time of the last occurrence of the exception.
- Count. Number of times the exception has occurred.

Searching and Filtering the list of Unhandled Exceptions

The **Unhandled Exceptions** page includes six filters. You can filter the list of exceptions by one or multiple of the following parameters: exception filename, line number, exception descriptions, first occurrence, last occurrence, and count. Only exceptions that meet all the filter criteria will be displayed in the **Unhandled Exceptions** page.

You can filter by one or more of the following parameters. The list of devices is dynamically updated as you select each filter.

- For the first three filters, you must enter text to match against. SL1 will search for exceptions that match the text, including partial matches. Text matches are not case sensitive. You can use the following special characters in each filter:
 - , Specifies an "or" operation. For example:
 - "dell, micro" would match all values that contain the string "dell" OR the string "micro". • ! Specifies a "not" operation. For example:

"!dell" would match all values that do not contain the string "dell".

- Exception Filename. You can enter text to match, including special characters, and the Unhandled Exceptions page will display only exceptions that have a matching filename.
- Line. You can enter text to match, including special characters, and the Unhandled Exceptions page will display only exceptions that have a matching line number.
- Exception Information. You can enter text to match, including special characters, and the Unhandled Exceptions page will display only exceptions that have a matching description.
- *First Occurrence*. Only those exceptions that match all the previously selected fields and have the specified first occurrence date will be displayed. The choices are:
 - All. Display exceptions with all first occurrence dates.
 - Last Minute. Display only exceptions that first occurred within the last minute.
 - Last Hour. Display only exceptions that first occurred within the last hour.
 - Last Day. Display only exceptions that first occurred within the last day.
 - Last Week. Display only exceptions that first occurred within the last week.
 - Last Month. Display only exceptions that first occurred within the last month.
 - Last Year. Display only exceptions that first occurred within the last year.
- Last Occurrence. Only those exceptions that match all the previously selected fields and have the specified last occurrence date will be displayed. The choices are:
 - All. Display exceptions with all last occurrence dates.
 - Last Minute. Display only exceptions that last occurred within the last minute.
 - Last Hour. Display only exceptions that last occurred within the last hour.
 - Last Day. Display only exceptions that last occurred within the last day.
 - Last Week. Display only exceptions that last occurred within the last week.

- Last Month. Display only exceptions that last occurred within the last month.
- Last Year. Display only exceptions that last occurred within the last year.
- **Count**. You can enter text to match, including special characters, and the **Unhandled Exceptions** page will display only exceptions that have a matching count number.

Saving the Unhandled Exception to the Local Computer

You can save the full text of the unhandled exception to a file on your local computer. You can then view the text in a text editor.

To save the full text of the unhandled exception to a file:

- 1. Go to the **Unhandled Exceptions** page (System > Monitor > Unhandled Exceptions).
- 2. In the **Unhandled Exceptions** page, find the exception you want to save to a file. Click its green diskette icon (**B**).

Unl	handled Exceptions Exceptions Found [4]					Reset	Guio	de
	Exception Filename	Line	Exception Information	First Occurrence		Last Occurrence	Count	
				All	-	All	-	
1	/usr/local/lib/python2.6/multiprocessing/pool.py	422	Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in n	i€2012-02-25 19:00:5	7	2012-03-21 13:00:43	116	
2	/usr/local/silo/proc/silo_db/normalizers/dynamic_app_normalize	357	izip argument #1 must support iteration	2012-03-20 10:01:0	0	2012-03-20 10:01:00	1	
	/usr/local/silo/proc/silo_db/normalizers/dynamic_app_normalize		izip argument #1 must support iteration	2012-03-16 17:00:3	5	2012-03-16 17:00:35	1	
4	/usr/local/silo/proc/silo_db/normalizers/dynamic_app_normalize	357	izip argument #1 must support iteration	2012-03-13 20:01:1	8	2012-03-13 20:01:18	1	

3. When prompted, you can either immediately view the text file with a text editor or save the file to your local computer for viewing later.

Viewing the Output of the System Status Script

For each Database Server, Data Collector, and Message Collector, you can view the output of the system status script for that appliance. To do this:

1. Go to the Appliance Manager page (System > Settings > Appliances).

Арр	liance Manager Editing Applia	ance [10]												System Sta	atus Output Rese	:t	Guid
				(10.64-171-211-CU-RI	IP Address	(Data Collection Ur collector unit: 10.64	Descriptio		• •		e As						
	Name	IP Address	Module Type	Collector Group	Description	Build	MariaDB	Capacity	Allocation	ID	Validated	Endpoint	Edit Date	Edit User	Create Date		1
1.	A 10-64-171-200-CDB	10.64.171.200	Database	n/a	Database: 10.64.171.200	10.1.0 r2166	10.4.12	5,000	n/a	1	Yes	-	2020-06-25 15:39:58	em7admin	2020-06-25 15:39:58	۵.	6 ⁴
2.	A 10-64-171-201-AP	10.64.171.201	Administration Portal	n/a	AP: 10.64.171.201	10.1.0 r2166		n/a	n/a	18	Yes	-	2020-06-25 16:15:03	em7admin	2020-06-25 16:10:59		۵ ا
3.	A 10-64-171-203-CU-MOSS1	10.64.171.203	Data Collection Unit	CUG-MOSS	collector unit: 10.64.171.203	10.1.0 r2166	10.4.12	n/a	0	2	Yes	-	2020-06-25 16:18:28	em7admin	2020-06-25 16:09:37	🗟 🖌	o* 1
4.	A 10-64-171-204-CU-MOSS2	10.64.171.204	Data Collection Unit	CUG-MOSS	collector unit: 10.64.171.204	10.1.0 r2166	10.4.12	n/a	0	3	Yes		2020-06-25 16:23:12	em7admin	2020-06-25 16:09:38	۶ 🌶	6 *
6.	A 10-64-171-205-CU-UsualSuspects1	10.64.171.205	Data Collection Unit	CUG-UsualSuspects	collector unit: 10.64.171.205	10.1.0 r2166	10.4.12	n/a	0	4	Yes	-	2020-06-25 16:29:15	em7admin	2020-06-25 16:09:39	۷ 🖌	e"
	A 10-64-171-206-CU-UsualSuspects2	10.64.171.206	Data Collection Unit	CUG-UsualSuspects	collector unit: 10.64.171.206	10.1.0 r2166	10.4.12	n/a	0	5	Yes		2020-06-25 16:22:13	em7admin	2020-06-25 16:09:40	۶ 🌶	o ⁴
	A 10-64-171-207-CU-ScrumAndCoke	10.64.171.207	Data Collection Unit	CUG-SAC	collector unit: 10.64.171.207	10.1.0 r2166	10.4.12	n/a	0	6	Yes	-	2020-06-25 16:24:17	em7admin	2020-06-25 16:09:40	🗟 🖊	6 *
в.	A 10-64-171-208-CU-Shared	10.64.171.208	Data Collection Unit	CUG-Shared	collector unit: 10.64.171.208	10.1.0 r2166	10.4.12	n/a	2	7	Yes		2020-08-25 16:25:12	em7admin	2020-06-25 16:09:41	۶ 🌶	<u>م</u>
9.	A 10-64-171-209-CU-Knights	10.64.171.209	Data Collection Unit	CUG-Solutions3	collector unit: 10.64.171.209	10.1.0 r2166	10.4.12	n/a	89	8	Yes	-	2020-06-25 16:24:16	em7admin	2020-06-25 16:09:42	2 /	6
10.	A 10-64-171-210-CU-RebelScrum	10.64.171.210	Data Collection Unit	CUG-Solutions1	collector unit: 10.64.171.210	10.1.0 r2166	10.4.12	n/a	666	9	Yes	-	2020-08-25 16:24:12	em7admin	2020-06-25 16:09:43	۷ 🖌	6 *
11.	A 10-64-171-211-CU-RNGs	10.64.171.211	Data Collection Unit	CUG-Shared	collector unit: 10.64.171.211	10.1.0 r2166	10.4.12	n/a	3	10	Yes	-	2020-06-25 16:26:13	em7admin	2020-06-25 16:09:44	🗟 🖊	6
12.	A 10-64-171-212-CU-Starlord	10.64.171.212	Data Collection Unit	CUG-Solutions2	collector unit: 10.64.171.212	10.1.0 r2166	10.4.12	n/a	0	11	Yes		2020-06-25 16:24:14	em7admin	2020-06-25 16:09:45	۷ 🖌	6 *
13.	A 10-64-171-213-CU-Benedict	10.64.171.213	Data Collection Unit	CUG-Benedict	collector unit: 10.64.171.213	10.1.0 r2166	10.4.12	n/a	16	12	Yes	-	2020-06-25 16:26:17	em7admin	2020-06-25 16:09:45	3 1	6 *
14.	A 10-64-171-214-CU-50centos	10.64.171.214	Data Collection Unit	CUG-Solutions1	collector unit: 10.64.171.214	10.1.0 r2166	10.4.12	n/a	290	13	Yes		2020-06-25 16:26:15	em7admin	2020-06-25 16:09:46	۷ 🖌	6 *
15.	10-64-171-217-CU-RaceCondition1	10.64.171.217	Data Collection Unit	CUG-RaceCondition	collector unit: 10.64.171.217	10.1.0 r2166	10.4.12	n/a	0	15	Yes	-	2020-06-25 18:33:03	em7admin	2020-06-25 16:09:48	3 1	6
16.	10-64-171-218-CU-RaceCondition2	10.64.171.218	Data Collection Unit	CUG-RaceCondition	collector unit: 10.64.171.218	10.1.0 r2166	10.4.12	n/a	1	16	Yes	-	2020-06-25 16:24:15	em7admin	2020-06-25 16:09:49	3 /	e,
17.	10-64-171-219-CU-RaceCondition3	10.64.171.219	Data Collection Unit	CUG-RaceCondition	collector unit: 10.64.171.219	10.1.0 r2166	10.4.12	n/a	0	17	Yes		2020-06-25 16:24:28	em7admin	2020-06-25 16:09:50	۷ 🖌	5
8	A 10-64-171-216-MC	10.64.171.216	Message Collection Unit		collector unit: 10.64.171.216	10.1.0 r2166	10.4.12	n/a	n/a	14	Yes	10.64.171.216 🎝	2020-06-25 18:38:04	em7admin	2020-06-25 16:09:47	3 /	6 ⁴

- 2. Locate the Database Server, Data Collector, or Message Collector that you want to view diagnostic information about.
- 3. click on its magnifying-glass icon () to view the output of the system status script for that appliance.

For more information about system status reports, watch the video at https://www.youtube.com/watch?v=oGWVH9kJ2oY.

Viewing the Database Tables on the Database Server

In some circumstances, you might need to view the contents of the database tables (the permanent tables are stored on the Database Server). There are two ways to do this:

- Using the built-in Database Tools in the **Database Tool** page (System > Tools > DB Tool).
- Using the link to the phpMyAdmin interface in the **Appliance Manager** page (System > Settings > Appliances).

Accessing the Database Tool

The **Database Tool** page allows administrators to view information about the internal ScienceLogic databases and run SQL queries against those internal databases.

CAUTION: Contact ScienceLogic for details on using the **Database Tool** page and troubleshooting databases. Do not make changes to the database or run the Optimizer Tool without guidance from ScienceLogic.

To access the database tool:

1. Go to the **Database Tool** page (System > Tools > DB Tool).

abase Tool Database Suppo	Actions Reset Guide
Select Database	SQL Query
aster_access aster_biz aster_custom aster_debug aster_dev aster_dev aster_dev aster_vents master_logs]	SELECT FROM system_messages;
sev date_edit mo	
2 2012-02-22 20:19:32 1	1: proc_mgr received a close signal and is shutting itself down.
1 2012-02-22 21:43:20 1	11: Alert 395 returned true, but not firing: alert simulation mode is enabled
1 2012-02-22 23:59:54 1	11: Alert 367 returned true, but not firing: alert simulation mode is enabled
1 2012-02-23 01:04:47 1	11: Alert 370 returned true, but not firing: alert simulation mode is enabled
1 2012-02-23 01:22:51 1	11: Alert 1 returned true, but not firing: alert simulation mode is enabled
1 2012-02-23 01:22:51 1	11: Alert 1 returned true, but not firing: alert simulation mode is enabled
1 2012-02-25 20:00:35 1	82: Something unexpected happened during normalization for Dynamic App Raw Freq 20: izip argument #1 must support iteration
4 2012-02-26 00:00:58 1	143: Unhandled exception during collection, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_f F
4 2012-02-26 00:00:58 1	143: Unhandled exception on appliance: 1, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_f Fi
4 2012-02-26 02:00:38 1	143: Unhandled exception during collection, process IT Service: Service Management Engine: Traceback (most recent call last); File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_f f
4 2012-02-26 02:00:38 1	143: Unhandled exception on appliance: 1, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_f Fi
1 2012-02-27 07:00:38 1	82: Something unexpected happened during normalization for Dynamic App Raw Freq 20: izip argument #1 must support iteration
4 2012-02-27 14:00:50 1	143: Unhandled exception during collection, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_f f
4 2012-02-27 14:00:50 1	143: Unhandled exception on appliance: 1, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_f Fi
4 2012-02-27 22:00:38 1	143: Unhandled exception during collection, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_f F
4 2012-02-27 22:00:39 1	143: Unhandled exception on appliance: 1, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_f Fi
4 2012-02-28 04:00:58 1	143: Unhandled exception during collection, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_f F
4 0040 00 00 04-00-00 4	4 49. 11-b- dlud

- 2. To run an SQL query from the Database Tool page, enter values in the following fields:
 - Select Database. Select a database to query.
 - SQL Query. Enter an SQL query to execute against the selected database. For more information on each database and each table, use the options in the [Actions] menu.

NOTE: You must be familiar with SQL and know how to build a proper query before using the **Database Tool** page.

- 3. Click the **[Go]** button to execute the query.
- 4. The results from the query are displayed in the pane at the bottom of the page.
- 5. To view the reports about the a database(s), click the [Actions] menu. The following options are available:
 - **Engines**. Displays status information about the server's storage engines. For each engine, the modal page displays a description of the engine, whether the engine is supported by SL1, and whether or not the engine supports transactions, XA, and save points.
 - **Global Status**. Displays a list of global variables used in the database tables and the current value for each global variable.
 - InnoDB Variables. Displays a list of InnoDB variables used in SL1 and the value for each variable.
 - **Open Tables**. Displays a list of currently open tables. For each table, the modal page displays the database name, table name, whether the table is currently in use, and whether the table is currently locked.

• **Optimizer Tool**. Leads to the **Database Optimizer Tool** page, where you can choose to optimize, repair, check, flush, or analyze all the tables in a database.

CAUTION: Contact ScienceLogic for details on using the **Database Optimizer Tool** page. Do not run the Optimizer Tool without guidance from ScienceLogic.

- **Processes**. Displays a list of running threads on the databases and tables. For each process, the modal page displays the connection ID, the database user who issued the statement, the host name of the client that issued the statement, the affected database, the command, the time in seconds that the thread has been in its current state, the state of the thread, and any available description of the process.
- **Table Status**. Displays the status of each database table in the platform. For each table, the modal page displays the table name, the database engine, database version, row format, number of rows, average row-length, length of the data file, maximum length of the data file, length of the index file, number of allocated but unused bytes, the next auto-increment value, the create time for the table, the update time for the table, the table's character set and collation, the live checksum value, options used with CREATE TABLE, and any comments.
- Variables. Displays a list of all database system variables used in SL1 and the value of each variable.

Disabling Normalization, Re-Enabling Normalization, and Backfilling Raw Data

ScienceLogic does not recommend stopping normalization on Data Collectors. However, there are rare occasions where ScienceLogic Customer Support might ask you to disable normalization as part of troubleshooting.

To disable normalization:

- 1. Either go to the console of the Database Server or use SSH to access the Database Server.
- 2. Log in as user em7admin with the appropriate password.
- 3. Type the following at the command line:

sudo vi /etc/siteconfig/siloconf.siteconfig

- 4. This is the file where users can customize the silo.conf file. In step #7, you will execute a command that sends these changes to the system silo.conf file.
- 5. In the LOCAL section, add the following line:

rollups_disabled=ON

- 6. Save your changes and exit the file (:wq).
- 7. At the command line, type the following command to rebuild the configuration file:

```
sudo /opt/em7/share/scripts/generate-silo-conf.py > silo.conf
```

8. You must restart the data collection process to ensure they receive the change. Type the following at the command line:

sudo service em7_hfpulld restart
sudo service em7_lfpulld restart
sudo service em7 mfpulld restart

To re-enable normalization and normalize data that was collected while normalization was disabled:

- 1. Either go to the console of the Database Server or use SSH to access the Database Server.
- 2. Log in as user em7admin with the appropriate password.
- 3. Type the following at the command line:

sudo vi /etc/siteconfig/siloconf.siteconfig

- 4. This is the file where users can customize the silo.conf file. In step #7, you will execute a command that sends these changes to the system silo.conf file.
- 5. In the LOCAL section, add the following line:

rollups_disabled=OFF

- 6. Save your changes and exit the file (:wq).
- 7. At the command line, type the following command to rebuild the configuration file:

sudo /opt/em7/share/scripts/generate-silo-conf.py > silo.conf

8. You must restart the data collection process to ensure they receive the change. Type the following at the command line:

sudo service em7_hfpulld restart
sudo service em7_lfpulld restart
sudo service em7_mfpulld restart

At the command line, type the following to normalize the data that was collected while normalization was disabled:

```
[/opt/em7/backend/data_normalizer_backfill.py --database, <database> --dids <
[device IDs]> --start <start date> --end <end date> --workers <number of
workers>
```

NOTE: To get help, at the shell prompt, type "/opt/em7/backend/data normalizer backfill.py -h".

where:

- --database database. Specifies the database that you want to backfill with normalized data. The choices are:
 - data avail. Table that stores normalized data for availability.
 - data_cv. Table that stores normalized data for Web Content policies.

- data dns. Table that stores normalized data for DNS policies.
- data_email. Table that stores normalized data for Email Round-Trip policies.
- data ports. Table that stores normalized data for TCP-IP Ports policies.
- data procs. Table that stores normalized data for System Processes policies.
- data services. Table that stores normalized data for Windows Services policies.
- data storage. Table that stores normalized data for file systems.
- data tv. Table that stores normalized data for SOAP/XML Transaction policies.
- dynamic_app_data_appID. Table that stores normalized data for a Dynamic Application. Specify the application ID for the Dynamic Application.
- --dids device IDs. Specifies the device ID of the device or devices for which you want to normalize data.
 - You can specify a single device ID.
 - You can specify multiple device IDs, separated by commas and surrounded by square brackets.
 - If you do not specify any device IDs, SL1 will normalize the specified data for all devices in your system.
- --start start date. The timestamp that specifies the data to normalize. Raw data with a time stamp at this time
 or later will be normalized. SL1 will normalize data starting with this timestamp and ending with the end-date
 timestamp.
 - Specify the timestamp in the format yyyy-mm-dd hh:mm:ss, using a 24-hour clock. Surround the timestamp with single quotes.
- --end end date. The timestamp that specifies the data to normalize. Raw data with a time stamp at this time or earlier will be normalized. SL1 will normalize data starting with the start-date timestamp and ending with this timestamp.
 - Specify the timestamp in the format yyyy-mm-dd hh:mm:ss, using a 24-hour clock. Surround the timestamp with single quotes.
- --workers workers. Number of worker processes to assign to this task. This field is optional. Please consult ScienceLogic Customer Support for suggestions on worker processes.

For example:

```
python /opt/em7/backend/data_normalizer_backfill.py --database dynamic_app_data_16
--start '2017-10-01 00:00:00' --end '2017-10-10 00:00:00' --workers 10
```

This command normalizes raw data collected by the Dynamic Application with an application ID of 16, associated with all subscriber devices (no device IDs specified, so defaults to "all devices"), and that was collected between midnight on October 1, 2017 and midnight on October 10, 2017. The data_ normalizer_backfill.py code uses ten worker processes to perform the normalization.

Enable Logging for Data Pull Storage Objects

To investigate missed polls or slow database queries, you can temporarily enable logging for data pull storage objects. After you complete the diagnostics, you must disable logging for data pull storage objects, because the logging can affect the performance of data pull.

Enable

To enable logging for data pull storage objects:

- 1. Either go to the console of the Database Server or use SSH to access the Database Server.
- 2. Log in as an administrator.
- 3. At the shell prompt, enter the following:

sudo vi /etc/silo.conf

4. In the silo.conf file, add the following lines:

```
[DATAPULL]
log_storage_object_stats = 1
```

- 5. Save your changes to the file (:wq).
- 6. You must restart the data collection processes to ensure they receive the change. To do this, enter the following at the shell prompt:

```
sudo service em7_hfpulld restart
sudo service em7_lfpulld restart
sudo service em7_mfpulld restart
```

Disable

When you have completed your diagnostics, disable logging for data pull storage objects. To do this:

- 1. Either go to the console of the Database Server or use SSH to access the Database Server.
- 2. Log in as an administrator.
- 3. At the shell prompt, enter the following:

```
sudo vi /etc/silo.conf
```

4. In the silo.conf file, edit the following:

```
[DATAPULL]
log_storage_object_stats = 0
```

- 5. Save your changes to the file (:wq).
- 6. You must restart the data collection processes to ensure they receive the change. To do this, enter the following at the shell prompt:

sudo service em7_hfpulld restart
sudo service em7_lfpulld restart
sudo service em7_mfpulld restart

Controlling Log Settings

In rare cases, you may need to modify log levels or suppression of certain logs in SL1, usually at the request of ScienceLogic Customer Support. To do so, you will navigate to the **PHP Developer Logs** page (System > Tools > PHP Developer Logs). This section describes the options included on the PHP Developer Logs page.

NOTE: This page is only available in the classic user interface.

Setting UI Developer Log Levels

When configuring logging on an appliance, you must specify a log level. The log level controls the types of messages that are written to the user interface log file (em7php.log). Each type of message has an associated number; the log level is the sum of all enabled messages. The numbers and associated message types are:

- 1. Critical
- 2. Error
- 4. Warning
- 8. Info
- 16. Debug
- 32. Trace

To determine the log level, sum the numbers associated with each type of message you want to enable. For example, if you want to enable Critical, Error, and Warning messages, you would sum one, two, and four to get a log level value of seven.

Setting UI/REST MySQL Query Log Levels

The UI/REST MySQL Query Log Levels settings let you specify the log level for the mysqli.log. This log file collects every PHP-based call to MySQL and includes general information about the query. Determine the granularity of data you want and select one or more checkboxes.

- Error
- Warning
- Info (non-error)

Configuring Advanced Log Settings

In the Advanced Settings section, you can configure the date/time format you want

- Suppression List. This list acts as a bitmask to log entries. For example, to suppress all entries for css-em7, you would enter "css.em7::127", where 127 is the sum of all possible log levels. You can specify multiple suppressions in the list, separated by commas.
- Datetime Format. Specifies a user-defined date format that will be used for5 system logs. You can use any date variables supported by the PHP date function in this field.

NOTE: Seconds and milliseconds are always appended to the datetime stamp.

Downloading Logs from the PHP Developer Logs page

To download the logs from the **PHP Developer Logs** page (System > Tools > PHP Developer Logs):

- 1. Go to the **PHP Developer Logs** page (System > Tools > PHP Developer Logs
- 2. Under **Download Logs**, select a logfile to download.

The following video explains PHP Developer Logs: For more information about PHP Developer Logs, watch the video at https://www.youtube.com/watch?v=1fJ1pKEIIIQ.

COUNT(*)	module	name	cug_name
46	4	emanbwl013	PFZR_IRL_CG
16	18	emapuul021	PFZR_PUUR_CG
16	22	emarinl014	PFZR_IRL_CG

Chapter



Changing Passwords

Overview

This chapter describes how to:

• Change every administrator password used in SL1.

NOTE: Appliances installed as an AWS EC2 instance have the "root" operating system account disabled by default. During the setup process, the user "ec2-user" is automatically added to the operating system configuration. The ec2-user account can be used to perform administrative tasks that require SSH command-line access. The ec2-user account is permitted to perform all operating system commands using the "sudo" command without a password.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon (三).
- To view a page containing all the menu options, click the Advanced menu icon (…).

This chapter includes the following topics:

Disabling phpMyAdmin	
Changing the Password for the Default Account for the User Interface	
Changing the Password for the Default Console User	
Changing the Password for the Web Configuration Utility	
Changing Database Passwords	
Configuring a New Password on Collector Appliances	
Editing Silo.Conf	

Updating the master.system_settings_licenses Table	227
Changing the MySQL Root Password on Database Appliances	228
Recovering the Root MySQL Password	228
Recovering the MySQL SNMP User Account on Collector Appliance	229

Disabling phpMyAdmin

The phpMyAdmin interface provides a web interface for viewing and managing MySQL databases. By default, you can log in to the Database Server using the phpMyAdmin interface to view and manage the MySQL databases on all Database Servers, Data Collectors, and Message Collectors in the system.

To disable phpMyAdmin, you must disable the service and then disable the ports on which the service runs. To do this:

- 1. If you are using a distributed system, either go to the console of the Database Server or use SSH to access the Database Server. Open a shell session on the server. Log in as "root".
- 2. If you are using an All-In-One Appliance, either go to the console of the All-In-One Appliance or use SSH to access the All-In-One Appliance. Open a shell session on the server. Log in as "root".

NOTE: For details on enabling and using SSH, see the manual **System Administration**. For details and warnings about root access and instructions on how to make root access secure, see the manual **System Administration**.

- 3. Open a vi session to edit the file /etc/siteconfig/firewalld-rich-rules.siteconfig
- 4. Add the following lines:

```
rule service name="phpmyadmin" reject
rule port port="8008" protocol="tcp" reject
```

- 5. Save your changes and exit the file.
- 6. Tell SL1 to pick up the changes to firewalld. To do this, type the following at the command line:

sudo /opt/em7/share/scripts/update-firewalld-conf.py

7. Restart the firewall services so that the phpMyAdmin service and port 8008 will no longer be allowed. To do this, type the following at the command line:

sudo systemctl restart firewalld
sudo systemctl restart nginx

Changing the Password for the Default Account for the User Interface

To change the password for the default em7admin user account, which can be used to access the user interface, perform the following steps:

- 1. Go to the **User Accounts** page (Registry > Accounts > User Accounts).
- 2. Click the wrench icon (*P*) for the em7admin user. The **Account Permissions** page appears.

	1	
kcount Login Name em7admin Change Password Confirm Password Password Strength [[Good] Account Type [[Individual] Login State [[Active] Password Expiration [[Disabled]	Primary Organization [System] Theme [ScienceLogic Standard Theme] Time Zone [L. New_York] Autosync Time Zone With Local settings [Let The User Choose] Additional Organization Memberships [None) (All organizations) [AwesoCorp] [Joshing, Inc.]	Privilege Keys EM7 System Administration [1] Grant All [28] Basic User Privileges [30] Power-Pack Administration [31] Provisioning Access [55] Admin Portal UI Access [53] Subscription Management Ticketing [7] Ticketing - End User [8] [6] Ticketing - Operator
		[6] Ticketing - Operator [12] Ticketing - Administration Dashboards [13] Dashboard - Administration [14] Dashboard - View [15] Dashboard - View [15] Dashboard - Widget Developer Asset Management [16] Asset - View
[Documentation] [Facilities] [Help Desk] [Help Desk] [Provisioning] [Provisioning] [Service Level] rote: Looked ticket queues must be applied by queue administrator,		[17] Asset - Administration Knowledge Base [18] Knowledge Base - View [19] Knowledge Base - Administration Organizations [20] Org / User / Vendor - View [21] Org / User / Vendor - Administration

- 3. Enter the new password in the Change Password field.
- 4. Re-type the new password in the Confirm Password field.
- 5. Click the [Save] button. A pop-up window appears, asking you to confirm the change.
- 6. Click "OK" in the pop-up window. The message "Password Saved" is displayed.

Changing the Password for the Default Console User

To change the password for the default administrative user **em7admin** for console logins and SSH access:

- 1. Either go to the console of the SL1 appliance or use SSH to access the server.
- 2. Log in as user em7admin with the appropriate password. The default password is em7admin.

- At the shell prompt, type the following: passwd
- 4. When prompted, type and re-type the new password.

Changing the Password for the Web Configuration Utility

You can change the password for the Web Configuration Utility.

NOTE: If you want to change the password for the Web Configuration Utility on all SL1 appliances, you must log in to the Web Configuration Utility on each appliance and perform the steps in this section.

NOTE: You cannot change the username for the Web Configuration Utility. The username remains *em7admin*.

To change the password for the Web Configuration Utility:

- 1. Log in to the Web Configuration Utility. The **Configuration Utilities** page appears.
- 2. Click the **[Device Settings]** button. The **Settings** page appears.

ScienceLogic™ Web Configuration Utility	🕷 Home	Licensing	≓ Interfaces	Device Settings	C PhoneHome	€>Logout
		ngs appliance.				
Web Configuration Username em7admin Appliance Type Database	w	eb Config Passv	vord (change only	y) Confirm Web	Config Password	
Damage	Save					

- 3. In the **Settings** page, type the following:
 - Web Config Password (change only). Type the new password.
 - Confirm Web Config Password. Type the new password again.
- 4. Click [Save]
- 5. Perform steps 1-4 for each appliance for which you want to change the password for the Web Configuration Utility.

Changing Database Passwords

The following SL1 appliances include a database instance:

- All-In-One Appliances
- Database Servers
- Data Collectors
- Message Collectors

By default, SL1 appliances use the following user accounts to access appliance databases:

- ap_user. This user is used by the user interface to access the database on a Database Server or All-In-One Appliance. This user account exists only on the Administration Portal and does not exist by default on Data Collectors and Message Collectors. By default, this user has the user name apuser and the password apuser.
- **dbuser**. This user is used by ScienceLogic platform processes to access the database instance on all appliances. By default, this user has the user name **root**.

To change the password for the **ap_user** account, you must:

1. Configure a new password for the Administration Portal using the Web Configuration Utility for the Administration Portal.

To change the password for these *dbuser* account, you must:

- 1. Configure a new password in the database instance.
- 2. Configure SL1 to use the new password.

WARNING: Exercise caution when manipulating MySQL user accounts. Do not use these procedures unless you are confident and know how to undo changes, should something go wrong.

Configuring a New Password on Collector Appliances

Perform the following steps to change the password for a user on a Collector:

- 1. Either go to the console of the Database Server, All-In-One Appliance, Data Collector, or Message Collector or use SSH to access the server in CLI mode.
- 2. Log in as em7admin with the appropriate password.
- 3. Run the following command to launch the MySQL prompt: silo_mysql mysql
- 4. From the MySQL prompt, change the root password by running the following SQL query: UPDATE root SET password=PASSWORD('{new password}') WHERE User='root';

- 5. To effect the change immediately, run the following SQL query: FLUSH PRIVILEGES;
- 6. Ensure you can access the database with the new password. Exit the MySQL interface, and test by running the following command, entering the new password when prompted: mysql -u root -p
- 7. Edit the /etc/silo.conf file and change the **dbpasswd** variable to the new password. See **Editing** *Silo.Conf* for assistance.
- 8. From the SL1 interface, go to the **Appliances** page (System > Settings > Appliances) and retrieve the appliance ID for the Collector.

Appliances	Em7admin ∨	
Appliance Manager	System Status Output	Reset Guide
Host Name Model type Integration Server [7]	Save	
IP Address Description	Save As	
Name IP Address Module Type Collector Group Description Build Capacity Allocation ID V	alidated Edit Date Edit User Create	Date
1. 🖉 em7ao 🐞 CUG All In One 8.14.0.8ETA.r1484 2.100 88 1 Y	/es 2019-05-17 12:52:23 em7admin 2019-0	5-17 12:52:23 🧕 💣

- 9. Go to the DB Tool page (System > Tools > DB Tool), and enter the following query to allow the Database Appliance to access the MySQL database of the Collector: UPDATE master.system_settings_licenses SET db_pass='{new password}' WHERE id= {appliance ID} LIMIT 1;
- 10. Confirm in the Collector Status page (System > Monitor > Collector Status) that the Collector is available.

Editing Silo.Conf

- 1. Log in to the Web Configuration Utility. The **Configuration Utilities** page appears.
- 2. Click the [Device Settings] button. The Settings page appears.

ScienceL	.ogic™ Web Configuration Utility	# Home	🔦 Licensing	≓ Interfaces	Device Settings	C PhoneHome	➡Logout
		Setti nfigure your	ngs r appliance.				
Web Co em7admi Applianc All in One	се Туре		Web Config Pas	sword (change o	only) Confirm We	b Config Passwoi	rd
Edit Files chrony.co	Inf silo conf chrony d/servers.conf	Save					

3. In the Edit Files section, click silo.conf. The Silo.conf Editor modal appears:

Silo.conf Editor	
[LOCAL]	,
rootdir = /opt/em7	
vardir = /var/lib/em7	
logdir = /var/log/em7	
rundir = /run/em7	
ipaddress = 10.2.14.27	
dbdir = /data/db	
dbserver = 127.0.0.1	
dbport = 7706	
dbuser = root	
dbpasswd = em7admin	
portcheck = /usr/bin/nmap	
model_type = 1	
eventmanager = internal,api,email,syslog,trap,dynamic	
disable_itil_compliance = 1	
[SLADMIN]	
sladmin_user = em7admin	
sladmin_cred = Jz3jghaKrTn0cFmzQRSSPA_JltKECDAl8VU6Njvi828zrGgGEc99R5yV1eAtn_	
[CENTRAL]	
dbserver = 127.0.0.2	
dbport = 7706	
dbuser = root	
dbpasswd = em7admin	
	0.000
	Save

- 4. Edit the value assigned to **dbuser** and to **ap_user**. Assign the value you defined in the section **Configuring a New Password in the Database Instance**.
- 5. To save your changes, click **Save** and then close the modal.

Updating the master.system_settings_licenses Table

To update the master.system_settings_licenses table after you have changed the root password on a Data Collector or Message Collector:

- 1. Go to the Appliance Manager page (System > Settings > Appliances).
- 2. Locate the Data Collector or Message Collector in the list of appliances. Note the value in the *ID* column for the Data Collector or Message Collector.
- 3. Go to the **Database Tool** page (System > Tools > DB Tool).
- 4. Enter the following in the **SQL Query** field, replacing <new password> with the new password and <ID value of Collector> with the value you noted in step 2:

```
UPDATE master.system_settings_licenses SET db_user='root', db_pass=<new
password> WHERE id=<ID value of Collector>;
```

If you want to update all Data Collectors and Message Collectors with the same password, enter the following in the SQL Query field, replacing < new password> with the new password:

UPDATE master.system_settings_licenses SET db_user='root', db_pass='<new
password>' WHERE function in (5,6);

5. Click the **[Go]** button.

Changing the MySQL Root Password on Database Appliances

To change the MySQL root password on Database Appliances:

- 1. Either go to the console of the Database Server or use SSH to access the server in CLI mode.
- 2. Log in as **em7admin** with the appropriate password.

NOTE: If your Database Appliances are part of an HA cluster, place your HA cluster in maintenance mode using the steps found in the *High Availability and Disaster Recovery* manual.

- 3. Run the following command to launch the MySQL prompt: silo_mysql mysql
- 4. From the MySQL prompt, change the root password by running the following SQL query: UPDATE user SET password=PASSWORD('{new password}') WHERE User='root';
- 5. To effect this change immediately, run the following SQL query. Enter the new password when prompted. FLUSH PRIVILEGES;
- Edit the /etc/silo.conf file and change the dbpasswd variable to the new password in both the [LOCAL] and [CENTRAL] sections. mysql -u root -p

NOTE: If you have clustered database appliances, be sure to update the silo.conf file for all cluster members.

- 7. If you have admin portals, update the **dbpasswd** variable in silo.conf on all admin portals.
- If the Collectors' MySQL root user password is now different from the MySQL root user password on the Database Appliance, and the *db_pass* column in *master.system_settings_licenses* is "NULL", then the Database Appliance will attempt to use its own password to connect. Change the *db_pass* column for the Collectors to their root MySQL user password using the instructions in *Updating the master.system_settings_licenses Table*.
- If you placed your HA cluster into maintenance mode to perform these steps, remember to return it to ready mode by setting coro_config to option 1. For more information, see the *High Availability and Disaster Recovery* manual.

Recovering the Root MySQL Password

To reset the root MySQL password if you become locked out:

- 1. Either go to the console of the Database Server or use SSH to access the server in CLI mode.
- 2. Log in as **em7admin** with the appropriate password.
- 3. Stop the em7 and mariadb services by entering the following command: systemctl stop em7 mariadb

- 4. Start the mariadb service with the "--skip-grant-tables' option using the following commands: systemctl set-environment MYSQLD_OPTS="--skip-grant-tables" systemctl start mariadb
- 5. Access the MySQL database by using the following command: mysql -u root mysql
- 6. Reset the root password from the MySQL prompt: UPDATE user SET password=PASSWORD('{new password}') WHERE User='root';
- Stop the mariadb service again, unset the environment variable, and restart the service, using the following commands: systemctl stop mariadb

```
systemctl unset-environment MYSQLD_OPTS
systemctl start mariadb
```

- Ensure that you can access the MySQL database with the new password, using the following command and entering the new password when prompted: mysql -u root -p
- Restart the em7 service using the following command: systemctl start em7
- 10. Ensure that the password you set is also updated in the /etc/silo.conf dbpasswd variable.

Recovering the MySQL SNMP User Account on Collector Appliance

If you have removed the SNMP user account from the Collector's MySQL database in an attempt to harden your system, you must recover the account so that SL1 can insert incoming SNMP traps into the database for processing.

To restore the SNMP user account:

- 1. Either go to the console of the Database Server or use SSH to access the server in CLI mode.
- 2. Log in as **em7admin** with the appropriate password.
- 3. Run the following command to restore the SNMP user account: /opt/em7/share/scripts/em7_firstboot.d/30_trap_listener-db_init.sh

Chapter

Changing the IP Address of an SL1 Appliance

Overview

The IP address for an appliance is configured at installation. To change the IP address for an appliance after installation and preserve your SL1 license, use the workflows in this section.

Moving an SL1 appliance to a new network requires pre-planning. If your SL1 configuration includes one or more Administration Portals, PhoneHome Collectors, or is configured for High Availability or Disaster Recovery, you must perform additional steps after changing IP addresses. The steps in this section allow you to change the IP address for an SL1 appliance with minimal downtime.

NOTE: This procedure requires downtime, so plan to perform this procedure during a maintenance window.

CAUTION: Ensure console access to the appliance you are migrating in case of typographical or other errors that might prevent network access when changing IP addresses.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon (三).
- To view a page containing all the menu options, click the Advanced menu icon (…).

This chapter includes the following topics:

Changing the IP Address on an All-In-One Appliance	231
Step 1. Stop the EM7 Service	231
Step 2. Change the IP Address in the Configuration Files	231

Step 3. Change the IP Address in the /etc/hosts File	232
Step 4. Change the IP Address in the Network Interface Configuration File	232
Step 5. Update the IP Address in the MySQL Database	233
Step 6. Reboot the Appliance	234
Changing the IP Address on a Database Server	234
Step 1. Stop the EM7 Service	234
Step 2. Change the IP Address in the Configuration Files	235
Step 3. Change the IP Address in the /etc/hosts File	.235
Step 4. Change the IP Address in the Network Interface Configuration File	235
Step 5. Update the IP Address in the MySQL Database	237
Step 5a: For Database Servers Configured with PhoneHome	237
Step 5b For Clustered Database Appliances (using HA, DR, or HA+DR)	238
Step 6. Reboot the Appliance	240
Step 7. Change the Database Appliance IP Address in the Administration Portals, Data Collectors, and Message Collectors	240
Changing the IP Address on a Data Collector or Message Collector	243
Using the Web Configuration Utility to Change the IP Address of a Data Collector or Message Collector $$.	243
Using the Command Line to Change the IP Address of a Data Collector or Message Collector	245

Changing the IP Address on an All-In-One Appliance

To change the primary IP address of an All-In-One Appliance :

Step 1. Stop the EM7 Service

Before changing the IP address, you must stop the EM7 service. To stop the EM7 service:

- 1. Either go to the console of the SL1 appliance or use SSH to access the server.
- 2. Login as user **em7admin** with the appropriate password.
- 3. Enter the following at the command line:

sudo systemctl stop em7

Step 2. Change the IP Address in the Configuration Files

You must change the ipaddress value in the configuration files.

- 1. Either go to the console of the SL1 appliance or use SSH to access the server.
- 2. Enter the following at the command line:

```
sudo vi /etc/siteconfig/siloconf.siteconfig
```

3. Change the following line in the [LOCAL] section of the file to specify the new IP address:

ipaddress = new_IP_address

- 4. Save and quit the file (:wq).
- 5. Do steps 2-4 to change the IP address in the /etc/silo.conf file.

Step 3. Change the IP Address in the /etc/hosts File

If the /etc/hosts file includes an entry for the appliance, update the entry with the new IP address.

- 1. Either go to the console of the SL1 appliance or use SSH to access the server.
- 2. Enter the following at the command line:

sudo vi /etc/hosts

3. If you see an IP address for the All-In-One Appliance, change the IP address to the new IP address.

Step 4. Change the IP Address in the Network Interface Configuration File

NOTE: Be sure to set the IPADDR, PREFIX, GATEWAY and DNS# variables to the appropriate values for the new network. The PREFIX is the subnet mask in CIDR notation.

To change the IP address, Netmask, Gateway address, and DNS Server for an appliance in the ifconfig file:

- 1. Either go to the console of the SL1 appliance or use SSH to access the server.
- 2. Login as user em7admin with the appropriate password.
- 3. Enter the following at the command line:

sudo ifconfig

4. Your output will look like this:

```
ens32: flags=4163<UP, BROADCAST, RUNNING, MULTICAST> mtu 1500
inet 10.64.68.20 netmask 255.255.255.0 broadcast 10.64.68.255
inet6 fe80::250:56ff:fe84:455f prefixlen 64 scopeid 0x20<link>
ether 00:50:56:84:45:5f txqueuelen 1000 (Ethernet)
RX packets 1774927 bytes 161985469 (154.4 MiB)
RX errors 0 dropped 861 overruns 0 frame 0
TX packets 1586042 bytes 158898786 (151.5 MiB)
TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
lo: flags=73<UP,LOOPBACK,RUNNING> mtu 65536
inet 127.0.0.1 netmask 255.0.0.0
inet6 ::1 prefixlen 128 scopeid 0x10<host>
loop txqueuelen 0 (Local Loopback)
RX packets 13406577 bytes 4201274223 (3.9 GiB)
RX errors 0 dropped 0 overruns 0 frame 0
TX packets 13406577 bytes 4201274223 (3.9 GiB)
TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
```

5. Examine the output, find the interface that uses the old IP address, and note its name.

6. Use the vi editor to edit the settings for the interface. To do this, enter the following at the command line:

```
sudo vi /etc/sysconfig/network-scripts/ifcfg-interface name you noted in step #5
```

For example, from our output, we could enter:

sudo vi /etc/sysconfig/network-scripts/ifcfg-ens32

7. The ifcfg file will look like this:

```
TYPE=Ethernet
BOOTPROTO=none
DNS1=10.64.20.33
DEFROUTE=yes
IPV4 FAILURE FATAL=no
IPV6INIT=yes
IPV6 AUTOCONF=yes
IPV6_DEFROUTE=yes
IPV6_FAILURE_FATAL=no
NAME=ens32
UUID=d471435d-9adf-47c9-b3f3-32f61dccbad8
DEVICE=ens32
ONBOOT=yes
IPADDR=10.64.68.20
PREFIX=24
GATEWAY=10.64.68.1
IPV6 PEERDNS=yes
IPV6 PEERROUTES=yes
```

- 8. You can edit one or more of the following settings:
 - DNS1=IP address of the DNS server that will be used by the SL1 appliance.
 - IPADDR=New IP address of the SL1 appliance.
 - **PREFIX**=netmask for the SL1 appliance.
 - GATEWAY=IP address of the network gateway that will be used by the SL1 appliance.
- 9. Save your changes and exit the file (:wq)
- 10. At the command line, enter the following:

```
sudo service network restart
```

Step 5. Update the IP Address in the MySQL Database

In this step, you must set the new IP address in the master.system_settings_licenses table so that when SL1 is restarted, the new IP address is recognized as licensed.

- 1. Either go to the console of the SL1 appliance or use SSH to access the server.
- 2. Login as user **em7admin** with the appropriate password.
- 3. Enter the following at the command line:

silo_mysql

4. At the mysql prompt, enter the following query:

```
UPDATE master.system_settings_licenses SET ip="[new IP address]" WHERE ip="[old
IP address] LIMIT 1"
For example:
  [em7admin@hostname ~]$ silo_mysql
MariaDB [(none)]> UPDATE master.system_settings_licenses SET ip="192.168.10.22"
WHERE ip="10.1.1.240";
Query OK, 1 row affected (0.01 sec)
Rows matched: 1 Changed: 1 Warnings: 0
MariaDB[(none)]>
```

5. Enter "exit" to exit the MySQL session.

Step 6. Reboot the Appliance

Reboot the appliance to apply all of the changes you made.

The system will boot up and will start the interface with the new IP address. SL1 will start up and will learn from the database that the new IP address matches its configuration file and the value in the database table. Therefore, SL1 will keep the current license for the appliance.

Changing the IP Address on a Database Server

Changing the primary IP address of a Database Server requires additional steps if

- the Database Server resides in a High Availability configuration or a Disaster Recovery configuration
- the Database Server might connect to Data Collectors configured for PhoneHome

In addition, when you change the primary IP address of a Database Server, you must update the configurations for any Data Collectors, Message Collectors and Administration Portals that communicate with that Database Server.

To change the IP address of a Database Server:

Step 1. Stop the EM7 Service

Before changing the IP address, you must stop the EM7 service. To stop the EM7 service:

- 1. Either go to the console of the Database Server or use SSH to access the server.
- 2. Login as user em7admin with the appropriate password.
- 3. Enter the following at the command line:

sudo systemctl stop em7

Step 2. Change the IP Address in the Configuration Files

You must change the ipaddress value in the configuration files.

- 1. Either go to the console of the SL1 appliance or use SSH to access the server.
- 2. Enter the following at the command line:

sudo vi /etc/siteconfig/siloconf.siteconfig

- Change the following line in the [LOCAL] section of the file to specify the new IP address: ipaddress = new_IP_address
- 4. Save and quit the file (:wq).
- 5. Do steps 2-4 to change the IP address in the /etc/silo.conf file.

Step 3. Change the IP Address in the /etc/hosts File

If the /etc/hosts file contains an entry for the appliance, update the entry with the new IP address.

- 1. Either go to the console of the SL1 appliance or use SSH to access the server.
- 2. Enter the following at the command line:

sudo vi /etc/hosts

3. If you see an IP address for the Database Server, change the IP address to the new IP address.

Step 4. Change the IP Address in the Network Interface Configuration File

NOTE: Be sure to set the IPADDR, PREFIX, GATEWAY and DNS# variables to the appropriate values for the new network. The PREFIX is the subnet mask in CIDR notation.

To change the IP address, Netmask, Gateway address, and DNS Server for an appliance in the ifconfig file:

- 1. Either go to the console of the Database Server or use SSH to access the server.
- 2. Login as user em7admin with the appropriate password.
- 3. Enter the following at the command line:

sudo ifconfig

4. Your output will look like this:

```
ens32: flags=4163<UP, BROADCAST, RUNNING, MULTICAST> mtu 1500
inet 10.64.68.20 netmask 255.255.255.0 broadcast 10.64.68.255
inet6 fe80::250:56ff:fe84:455f prefixlen 64 scopeid 0x20<link>
ether 00:50:56:84:45:5f txqueuelen 1000 (Ethernet)
RX packets 1774927 bytes 161985469 (154.4 MiB)
RX errors 0 dropped 861 overruns 0 frame 0
TX packets 1586042 bytes 158898786 (151.5 MiB)
TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
lo: flags=73<UP,LOOPBACK,RUNNING> mtu 65536
inet 127.0.0.1 netmask 255.0.0.0
inet6 ::1 prefixlen 128 scopeid 0x10<host>
loop txqueuelen 0 (Local Loopback)
RX packets 13406577 bytes 4201274223 (3.9 GiB)
RX errors 0 dropped 0 overruns 0 frame 0
TX packets 13406577 bytes 4201274223 (3.9 GiB)
TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
```

- 5. Examine the output, find the interface that uses the old IP address, and note its name.
- 6. Use the vi editor to edit the settings for the interface. To do this, enter the following at the command line:

```
sudo vi /etc/sysconfig/network-scripts/ifcfg-interface name you noted in step #5
```

For example, from our output, we could enter:

```
sudo vi /etc/sysconfig/network-scripts/ifcfg-ens32
```

7. The ifcfg file will look like this:

```
TYPE=Ethernet
BOOTPROTO=none
DNS1=10.64.20.33
DEFROUTE=yes
IPV4 FAILURE FATAL=no
IPV6INIT=yes
IPV6 AUTOCONF=yes
IPV6 DEFROUTE=yes
IPV6 FAILURE FATAL=no
NAME=ens32
UUID=d471435d-9adf-47c9-b3f3-32f61dccbad8
DEVICE=ens32
ONBOOT=yes
IPADDR=10.64.68.20
PREFIX=24
GATEWAY=10.64.68.1
IPV6 PEERDNS=yes
IPV6 PEERROUTES=yes
```

- 8. You can edit one or more of the following settings:
 - DNS1=IP address of the DNS server that will be used by the Database Server.
 - **IPADDR**=New IP address of the Database Server.
 - **PREFIX**=netmask for the Database Server.
 - GATEWAY=IP address of the network gateway that will be used by the Database Server.
- 9. Save your changes and exit the file (:wq)
- 10. At the command line, enter the following:

sudo service network restart

Step 5. Update the IP Address in the MySQL Database

In this step, you must set the new IP address in the master.system_settings_licenses table so that when the Database Server is restarted, SL1 recognizes the new IP address as licensed.

- 1. Either go to the console of the SL1 appliance or use SSH to access the server.
- 2. Login as user em7admin with the appropriate password.
- 3. Enter the following at the command line:

silo_mysql

4. At the mysql prompt, enter the following query:

```
UPDATE master.system_settings_licenses SET ip="[new IP address]" WHERE ip="[old IP address] LIMIT 1"
```

For example:

```
[em7admin@hostname ~]$ silo_mysql
```

```
MariaDB [(none)]> UPDATE master.system_settings_licenses SET ip="192.168.10.22"
WHERE ip="10.1.1.240";
Query OK, 1 row affected (0.01 sec)
Rows matched: 1 Changed: 1 Warnings: 0
```

MariaDB[(none)]>

5. Enter "exit" to exit the MySQL session.

Step 5a: For Database Servers Configured with PhoneHome

If your Database Server is configured with PhoneHome, perform the following additional steps to change the IP address of the :Database Server

- 1. Either go to the console of the Database Server or use SSH to access the server.
- 2. Enter the following at the command line:

NOTE: If you are planning to change the IP address of multiple Database Servers, you will want to update all of the relevant IP addresses in PhoneHome in this step.

phonehome status

3. The output will look like the following:

```
Phone Home Client configuration:
 Config Revisions: Device: 2 Destinations: 7 Global: 9
            State Status Forwards Name
Device Id Type
_____
    collector Enabled forwarded
                           Phone Home collector 15
15
Device Id Type
            State Host/Ip Port Name
_____
    database Enabled 192.168.2.2 7705 Phone Home database 11
11
    database Enabled 192.168.2.4 7705 Phone Home database 12
12
13
    database Enabled 192.168.2.6 7705 Phone Home database 13
```

- 4. Note the Device ID for the Database Server. .
- Run the phonehome set command to change the IP address for the device ID that corresponds to the Database Server. To do this, enter the following:

```
phonehome set [device ID] ip="[new IP address]"
```

where:

- device id is the device ID you noted in step #4.
- new ip address is the new IP address.

For example

```
[root@database_hostname username] # phonehome set 11 ip="[new_ip_address]"
Reloading sshd configurations
```

6. For each Database Server that you want to change the IP address, perform step #5.

Step 5b For Clustered Database Appliances (using HA, DR, or HA+DR)

If your Database Servers are clustered for High Availability (HA), Disaster Recovery (DR), or both (HA+DR), to change the IP address of the Database Servers, you must also modify the clustering software configuration files, as described in this step.

1. Either go to the console of the Database Server or use SSH to access the server.

NOTE: Changes to the running Cluster Resource Manager (CRM) configuration take effect immediately. ScienceLogic recommends that you wait to wait to change the virtual IP address until the Database Server has been moved to its new location, if applicable. 2. You must edit the settings for the virtual IP for the cluster. At the command line, enter the following:

```
crm resource stop virtual_ip
crm resource param virtual_ip set ip [new IP address]
crm resource param virtual_ip set cidr_netmask [new subnet mask in CIDR
notation]
crm resource start virtual_ip
```

- 3. In a High Availability configuration, the two Database Servers use two rings:
 - ringO defines the private interfaces that are connected directly to one another via crossover cable.
 - ring1 defines the public interfaces that host the virtual IP and conduct the SL1 related tasks.

To update these values in a High Availability configuration, you must edit the file /etc/corosync/corosync.conf..

- 4. Use a file editor like vi to edit /etc/corosync/corosync.conf.
- 5. You will see something like this:

```
nodelist {
   node {
    ring0_addr: 192.168.25.200
    ring1_addr: 10.1.20.25
   name: hardb1
   nodeid: 1
   }
   node {
    ring0_addr: 192.168.25.201
    ring1_addr: 10.1.20.26
    name: hardb2
    nodeid:2
   }
}
```

For the Database Server with the new IP address, edit the value for ring0_addr to match the new IP address. Save the file.

- 6. DRBD is the service that synchronizes the Database Servers in a High Availability or Disaster Recovery configuration. The DRBD file /etc/drbd.d/r0.res defines how data (on resource 0) is synchronized.
 - In SL1 configured for High Availability , DRBD uses the private IPs to synchronize high-availability data.
 - In SL1 configured for High Availability plus Disaster Recovery, DRBD uses the private interface to synchronize high-availability data and the virtual IP and the public IP addresses to synchronize data for disaster recovery.
 - In SL1 configured for Disaster Recovery, DRBD uses the virtual IP and the public IP addresses to synchronize data.

Use a file editor like vi to edit /etc/drbd.d/r0.res. It will look something like this:

```
resource r0 {
 protocol A;
 device /dev/drdb1;
 stacked-on-top-of r0-L {
  address 127.0.0.1:7789;
  proxy on hadrdb1 hadrdb2 {
   inside 127.0.0.1:7790;
   outside 192.168.25.200:7788;
  }
 }
on hadrdb2
  disk /dev/mapper/em7vg-db;
  address 127.0.0.1:7789;
  meta-disk internal;
  proxy on hadrdb3 {
  inside 127.0.0.1:7790;
   outside 192.168.25.201:7788;
  }
 }
```

Replace instances of the old IP address with the new IP address and save the file.

Shut down the Database Server .

.

7. Upon reboot of the Database Server, run a discovery session to rediscover the Database Server with its new IP address.

Step 6. Reboot the Appliance

Reboot the Database Server to apply all of the changes you made.

CAUTION: If you are migrating a High Availability cluster, shut down the secondary first, then the primary, so that SL1 does not perform a failover. Restart up the primary first, and after it is up and running, restart on the secondary.

The system will boot up and will start the interface with the new IP address. SL1 will start up and will learn from the database that the new IP address matches its configuration file and the value in the database table. Therefore, SL1 will keep the current license for the appliance.

Step 7. Change the Database Appliance IP Address in the Administration Portals, Data Collectors, and Message Collectors

You must edit the configuration for each SL1 node that communicates with the Database Server. To do so, perform the following steps on each Administration Portal, Data Collector, and Message Collector in your SL1 system.


Perform the following steps to log in to the Web Configuration Utility:

1. You can log in to the Web Configuration Utility using any web browser supported by SL1. The address of the Web Configuration Utility is in the following format:

https://ip-address-of-appliance:7700

NOTE: For AWS instances, *ip-address-of-appliance* is the public IP for the AWS instance. To locate the public IP address for an AWS instance, go to AWS, go to the **Instances** page, and highlight an instance. The **Description** tab in the lower pane will display the public IP.

2. When prompted to enter your user name and password, log in as the "em7admin" user with either the default password of **em7admin** or the password you configured.



3. After logging in, the main **Configuration Utility** page appears:

Scier	nceLogic™ Web Configuration Uti	lity 🚜 H	ome ≪ Licensing	Device Settings	CPhoneHome DeLogout
	С	Configura	tion Utiliti	es	
		-	ng your ScienceLogic™ sof		es.
	≮ Licensing	≓ Interfaces	Device Settings	C.	PhoneHome
		Licens	e Information		
	Capacity :	7000	Expiration : N	lon, 05 Mar 2018 05:00:00) GMT
	License Type	e : Trial	Or	ganization : silotest	
		Sci	nceLogic™		

4. Click the **[Device Settings]** button in the upper-right of the page. The **Settings** page appears.

ScienceLogic™ Web Configuration Utility	# Home ≮ Licensing ≓ Interfaces & Device Settings ∿PhoneHome @
	Settings
Web Configuration Username em7admin	Configure your appliance. Web Config Password (change only) Confirm Web Config Password
Appliance Type Administration Portal	Database IP Address 10.2.3.16
Database Username	Database Password (change only) Confirm Database Password
GUI Username root	GUI Password (change only) Confirm GUI Password
Edit Files	Save
chrony.conf silo.conf chrony.d/servers.conf	

5. In the **Settings** page, enter the following:

- Database IP Address. The new IP address of the Database Server.
- **Database Username**. Username for the database account that the Administration Portal will use to communicate with the Database Server.
- Accept the default values in all other fields.
- 6. Click the [Save] button. You may now log out of the Web Configuration Utility.

Changing the IP Address on a Data Collector or Message Collector

You can change the IP address of a Data Collector or Message Collector in two ways:

- In the Web Configuration Utility
- From the command line of the Data Collector or Message Collector

Regardless of the method you choose, SL1 will automatically update the IP address of the Data Collector or Message Collector in:

- /etc.sillo.conf
- /etc/sysconfig/network-scripts/ifcfg-ens160
- /etc/hosts
- the master.system_settings_licenses table, in the ip column

The following sections explain the necessary steps.

Using the Web Configuration Utility to Change the IP Address of a Data Collector or Message Collector

Perform the following steps to log in to the Web Configuration Utility:

1. You can log in to the Web Configuration Utility using any web browser supported by SL1. The address of the Web Configuration Utility is in the following format:

```
https://ip-address-of-appliance:7700
```

NOTE: For AWS instances, *ip-address-of-appliance* is the public IP for the AWS instance. To locate the public IP address for an AWS instance, go to AWS, go to the **Instances** page, and highlight an instance. The **Description** tab in the lower pane will display the public IP.

2. When prompted to enter your user name and password, log in as the "em7admin" user with either the default password of **em7admin** or the password you configured.

ScienceLogic Configuration Utility

3. After logging in, the main **Configuration Utility** page appears:

	ScienceLogic™ Web Configuration Utili	ity	🖀 Home 🛛 🔦 Licensi	ng ≓ Interfaces	Device Settings	C PhoneHome	⊡ Logout	
	•	C 1						
Configuration Utilities								
	This interface provides helpers for registering your ScienceLogic™ software and interfaces.							
	Licensing	≓ Interfaces	•	Device Settings		C PhoneHome		
	License Information							
	Capacity : 7	000		Expiration : M	lon, 05 Mar 2018 05:00	:00 GMT		
	License Type	: Trial		Or	ganization : silotest			
			ScienceLogic™					

- 4. Select the Interfaces tab.
- 5. In the Interfaces page, select the interface that you want to edit.

ScienceLogic [™] Web Cor	nfiguration Utility	A Home < Licensing ≓ Interface	s 🏟 Device Settings 📞 Phone Home	€►Logo
	Interfa	ace Details : ens32		
Name		Interface IP Address		
ens32		10.64.166.24		
Netmask IP Address		Gateway IP Address		
IPv6 Address				
valid ipv6 format				
		Save		
		Non-editable properties		
bootproto	browser_only	defroute	device	
static	no	yes	ens32	
id	ipaddr	ipv4_failure_fatal	ipv6_addr_gen_mode	
ens32	10.64.166.24	no	stable-privacy	
ipv6_autoconf	ipv6_defroute	ipv6_failure_fatal	ipv6addr	
yes	yes	no		
			ipv6init	
			yes	
onboot	prefix	proxy_method	type	
yes	23	none	Ethernet	
uuid				
00000600 0000 4000 0005				
		ScienceLogic™		

- 6. Enter values in the following fields:
 - Interface IP Address. Required. Enter the IP address for the bonded interface in standard IPv4, dotted-octet format.
- 7. The IP address for the Data Collector or Message Collector will be automatically updated in all the necessary configuration file and database tables.

Using the Command Line to Change the IP Address of a Data Collector or Message Collector

- 1. Either go to the console of the Data Collector or Message Collector or use SSH to access the server.
- 2. At the shell prompt, enter:

```
update_ip <interface_ID> <new_IP>
where:
```

- interface_ID is the name of the interface, usually ensn32 or ens160.
- *new_IP* is the new IP address to assign to the interface.
- 3. The IP address for the Data Collector or Message Collector will be automatically updated in all the necessary configuration file and database tables.

Chapter **10**

Changing Name Servers on an SL1 Appliance

Overview

This chapter describes how to change domain name servers (DNS) on an SL1 appliance.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon (三).
- To view a page containing all the menu options, click the Advanced menu icon (…).

This chapter includes the following topics:

Changing Name Servers on an SL1 Appliance	246
Installing Additional RPMs on an SL1 Appliance	248

Changing Name Servers on an SL1 Appliance

Domain Name Server (DNS) server settings are configured at installation. You cannot adjust the DNS settings later through the Web Configurator. Instead, you must use the command line interface (CLI) to change the DNS server information. This action requires no downtime.

To change the DNS settings:

- 1. Edit the /etc/resolv.conf file by entering the following command: sudo vi /etc/resolv.conf
- 2. Change the *nameserver* entry to the IP address of the new DNS or add new DNS entries to the file.

3. Save and quit to commit the changes.

This change immediately causes the OS to use the new DNS, with no reboot or service restarts required. If you have multiple nameservers listed in the file, the system will try each entry in the list until it gets a response or runs out of nameservers.

Next, add the DNS to the interface configuration file so that the change will persist if the network service is restarted or the appliance is rebooted.

To add one or more domain name servers to the interface configuration file:

- 1. Either go to the console of the SL1 appliance or use SSH to access the server.
- 2. Log in as user **em7admin** with the appropriate password. The default password is **em7admin**.
- 3. Determine the name of your primary interface (not the "lo" interface) by running the following command: ip addr
- 4. Edit the corresponding interface configuration file in the /etc/sysconfig/network-scripts directory: sudo vi /etc/sysconfig/network-scripts/ifcfg-{interface name}
- 5. Find the "DNS1" entry and change the IP address to the IP address of the new DNS.

NOTE: You can enter additional DNS servers and define them as DNS2, DNS3, and so on.

6. Save and quit to commit the changes.

Installing Additional RPMs on an SL1 Appliance

For certain patch releases, ScienceLogic might require additional RPMs to be installed on specific appliance types. If an RPM install is required, the release notes will indicate the additional RPMs to install on each specific appliance type.

To install additional RPMs on an appliance, perform the following steps:

- 1. Download the RPM files provided by ScienceLogic to your local machine.
- 2. Log in as root at the appliance console.
- 3. Copy each of the downloaded RPM files to the appliance. To copy the downloaded files, perform the following command as root at the console of the appliance:

```
scp <username-on-local-machine>@<ip-address-of-your-local-machine>:<full-path-
to-rpm-on-your-local-machine> <full-path-on-appliance-to-copy-to>
```

4. Use the following command to run the RPM installer for each of the RPM files:

```
rpm -U <name-of-rpm-file>.rpm
```

5. If you have not yet done so, apply the latest patch to your SL1 system.

Chapter **1**1

Backup Management

Overview

This chapter describes how to prepare to back up your SL1 system, to define and run your backups, and to restore from different backup types.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon (=).
- To view a page containing all the menu options, click the Advanced menu icon (…).

This chapter includes the following topics:


Types of SL1 Backups	. 250
Preparing for SL1 Backups	251
Creating a Backup Credential	252
Configuration Backups	253
Restoring a Configuration Backup	257
Full Backup	259
Restoring a Full Backup	261
Retaining Full Backups	263
Additional Configuration for Solaris NFS Remote Shares	264
DR Backup	264
Restoring a DR Backup	267
Retaining DR Backups	267

Types of SL1 Backups

SL1 allows you to define three types of backups for your system:

- Configuration Backup. Includes the core database tables and files required to restore an SL1 system. A configuration backup includes scope and policy information, but not performance data, data collected using configuration Dynamic Applications, events, or logs.
- *Full Backup*. Includes all SL1 databases and tables but does not include the configuration files specified in /etc/backup. These files are backed up in each configuration backup.
- **Disaster Recovery Backup**. Includes a full backup of the disaster-recovery database for SL1 systems configured for disaster recovery (DR). The Disaster Recovery backup is similar to the Full Backup.

The **Backup Management** page (System > Settings > Backup), shown below, lets you define your backups and run them on demand.



CAUTION: ScienceLogic does not support vmotion or VMware Snapshots for backups of data. For backup purposes, ScienceLogic supports only ScienceLogic backups to remote storage. vmotion and VMware Snapshots can cause SL1 outages.

Preparing for SL1 Backups

Before creating a backup of your system, you must complete the following steps:

Identify the external system (NFS or SMB mount) and a directory to which you want to write the backups. You
will need to specify the hostname or IP address of this system and the directory when configuring your
backups.

NOTE: It is the responsibility of the system administrator for the remote NFS or SMB share to create any necessary entries in /etc/fstab required to allow the SL1 system to access the share as root.

- 2. Create a credential in SL1 that allows SL1 to write to the external system (NFS or SMB share) where you will store the backups.
- 3. Define the configuration backup, full backup, or DR backup in SL1.

Creating a Backup Credential

To configure a backup, you must create a **Basic/Snippet** Credential that allows SL1 to write to the external systems where you will store the backups. To create a backup credential:

- 1. Go to the Credential Management page (System > Manage > Credentials).
- 2. In the **Credential Management** page, click the **[Actions]** button in the upper right corner of the page. Select **Create Basic/Snippet Credential**.
- 3. The **Credential Editor** page appears, where you can define values in the following fields:

Credential Editor			×
Create New Basic/Snippet Credential			Reset
Basic Settings			
	Credential Name		I
MyBackupCredential			
Hostname/IP	Port	Timeout(ms)	
	ername	Password	
someuser		••••••	
	Save		

- Credential Name. Name of the credential. Can be any combination of alphanumeric characters.
- Hostname/IP. The hostname or IP address.
- Port. This field is deprecated. Backups will not use this field.
- Timeout (ms). This field is deprecated. Backups will not use this field.
- Username. Username to use when connecting to the external system. If you are backing up to NFSremote, this field is not required.
- **Password**. Password to use when connecting to the external system. If you are backing up to NFSremote, this field is not required.
- 4. Click the **[Save]** button.

Configuration Backups

A configuration backup stores a copy of the core database tables that are required to restore an SL1 system. Configuration backups use the "MySQL dump" tool to create backups.

You must store configuration backups on an external system (not the Database Server or All-In-One Appliance). You can specify that configuration backups be stored on an NFS mount or SMB mount on an external system.

NOTE: SL1 Systems prior to 8.12 allow you to store backups locally. New SL1 systems later than 8.12 require you to store backups on an external system.

NOTE: If you have a large system and very large backup files, you can use an alternative method to perform backups that reduces performance issues during backup. For more information, see the section *Performing Config Backups and Full Backups on a Disaster Recovery Database Server*.

Note the following information about configuration backups:

- SL1 can launch configuration backups automatically at the interval you specify.
- During configuration backup, the ScienceLogic database remains online.
- When the configuration backup starts, SL1 creates a temporary mount point to your remote share in /data.local/backup/remote<unix_timestamp>.

What Does a Configuration Backup Include?

A configuration backup includes:

- Scope and policy information, but not performance data, data collected using configuration Dynamic Applications, or events.
- By default, the following files are backed up during a configuration backup:
 - /etc/backup.conf
 - /etc/corosync/corosync.conf
 - /etc/drbd.d/r0.res
 - /etc/drbd-proxy.license
 - /etc/hosts
 - /etc/my.cnf.d/silo_mysql.cnf
 - /etc/nginx/*
 - /etc/phonehome/*
 - /etc/php-fpm.d/*.conf

- /etc/postfix/main.cf
- /etc/silo.conf
- /etc/siteconfig/*
- /etc/ssh/*.key
- /etc/ssh/*.pub
- /etc/sysconfig/network-scripts/ifcfg-*
- /etc/sysctl.d/*
- /etc/systemd/system/mariadb.service.d/*.conf
- /opt/em7/nextui/nextui.conf
- /usr/libexec/postfix/main.cf
- /var/log/em7/*
- All files and folders specified in /etc/backup.conf. If you have additional files that you want to include in configuration backups, you can include them in the file /etc/backup.conf
- The following databases:
 - *master*. Includes system-level settings for SL1, Dynamic Application definitions and alignments, run book automation and action policies, monitoring policy definitions, and credentials.
 - *master_access*. Includes user account information, access keys, and access hooks.
 - *master_ap2*. Includes files from the new UI, including files from Business Services.
 - master_biz. Includes asset information, dashboards, distribution lists, document templates, IT Service policy information, knowledge base information, organization information, product SKU information, RSS feeds, ticketing information, and user preferences. By default, configuration backups do not include the *ticket external requests table* from the master biz database.
 - *master_custom*. Includes GUI customizations, dashboard widget definitions, PowerPack files, and custom attributes for the Integration Server.
 - *master_dev*. Includes information associated with device records, excluding performance data, data collected using configuration Dynamic Applications, events, or logs.
 - *master_dns*. Includes DNS information.
 - *master_events*. The configuration backup includes only the event_suppressions table from this database. This table stores event suppression settings.
 - **master_filestore**. Includes information about files, PowerPacks, and notes. By default, configuration backups do not include the tables metadata_system_package, metadata_system_patch, storage_system_package, and storage_system_patch.

NOTE: In SL1 versions prior to 8.14, configuration backups contained RPM update and package files. In version 8.14 and higher, configuration backups no longer contain these files, making the backup process complete faster and making the backup file smaller.

- master_platform. Includes information about ScienceLogic appliances.
- *master_reports*. Includes custom report definitions.
- *mysql*. Contains the configuration settings for the MariaDB database.
- scheduler. Includes all instances of scheduled items: reports, discovery sessions, etc.
- **sysinfo**. Contains the configuration settings for High Availability, Disaster Recovery, and PhoneHome Collectors.

Viewing the Databases and Tables Included or Excluded from a Configuration Backup

To see which databases and tables are included in configuration backups in your environment:

- 1. Navigate to the **Database Tool** page (System > Tools > DB Tool)
- 2. In the Select Database field, select Master.
- 3. In the "SQL Query" field, enter this query:

```
SELECT backup_db_list FROM `system_settings_backup` WHERE id = 1
```

To see which databases and tables are excluded in configuration backups in your environment:


- 1. Navigate to the **Database Tool** page (System > Tools > DB Tool)
- 2. In the Select Database field, select Master.
- 3. In the "SQL Query" field, enter this query:

SELECT backup_cb_table_exclude FROM `system_settings_backup` WHERE id = 1

Defining a Configuration Backup

To define and schedule a configuration backup:

- 1. Go to the **Backup Management** page (System > Settings > Backup).
- 2. In the **Configuration Backup** pane, provide values in the following fields:



- Every. Together with the Interval field, specifies the frequency of the backup.
- Interval. Together with the *Every* field, you must specify how frequently SL1 should automatically execute a configuration backup. Your choices are:
 - Disabled. Configuration backups are disabled. If you want to run on-demand configuration backups only, you do not need to change this setting.
 - Day. SL1 will execute configuration backups daily as specified (for example, every 2 days).
 - Week. SL1 will execute configuration backups weekly as specified (for example, every 2 weeks).
 - Month. SL1 will execute configuration backups monthly as specified (for example, every 1 month).

- Start Time / Date. If you enabled configuration backups, you must specify the start time. You must specify the date on which you want configuration backups to begin, as well as the time of day you want the backups to run. For example, you might want to run configuration backups during a maintenance window late at night. Click the field to open a calendar and time selector.
- *Timezone*. Optional. Specify the timezone to use when running a backup. The default is UTC. Use the drop-down list to select the timezone.
- **Configuration Credentials**. Select the credential you created for SL1 to use to connect to your external system (NFS or SMB). For more information, see **Creating a Backup Credential**.
- **Configuration Protocol**. Specify the type of external system where the configuration backup will be stored. Choices are:
 - NFS-Remote. When you select this option, SL1 stores the configuration backup on an NFS share.

NOTE: If you select the NFS-remote option, and your NFS share is hosted on a Solaris system, you must perform the steps listed in the Additional Configuration for Solaris NFS Mounts section.

- SMB-Remote. When you select this option, SL1 stores the configuration backup on an SMB share.
- **Configuration Subdirectory**. Specify a directory on the NFS or SMB share in which you would like to store the configuration backup. On the remote share, the current Unix time will be appended to the directory name to ensure the directory name is unique each time the backup runs.
- 3. Click the **[Save]** button to save your settings. SL1 will execute the configuration backup at the specified interval, starting on the date you specified in the **Start Time / Date** field and using the time you specified in the **Start Time / Date** field.
- 4. To run the backup immediately, click the [Backup Now] button under Configuration Backup in the Immediate Backup section of the Backup Management page. SL1 will run the backup immediately, as well as running the scheduled backup you configured in this procedure.

Restoring a Configuration Backup

If you have performed configuration backups, you can restore your system from a configuration backup in the event of data corruption or other failure. The configuration backup file contains one SQL (.sql) file for each database that was included in the configuration backup.

NOTE: These steps assume that the Database Server has not been previously configured.

NOTE: To complete these steps, you must be familiar with how to edit a file using the vi text editor. If you need assistance with these steps, please contact ScienceLogic Support.

To restore a database using the backup file:

1. Either go to the console of the Database Server or use SSH to access the server.

NOTE: The Database Server to which you are restoring the backup must be at the same revision number as the Database Server that created the backup file.

2. Log in as user **em7admin** and assume root user privileges by using the following command:

\$ sudo -s

3. Execute the following commands at the command line to uncompress the backup file, where <new_ subdirectory> is a directory you create that will be the destination for your uncompressed files, and where <full path and filename for backup.tgz> is the location and name of your backup file.:

```
# mkdir /data.local/db/<new_subdirectory>
# cd /data.local/db/<new_subdirectory>
# pigz -dc <full path and file name for backup.tgz> | tar xv
```

For example:

```
# mkdir /data.local/db/my_backups
# cd /data.local/db/my_backups
# pigz -dc /mnt/db1_config_2021-02-01_21-00-00.tgz | tar xv
```

4. Your target directory will now contain one SQL file for each database included in the backup. Copy the configuration backup files to their original locations. For example:

```
# cp -r opt /
# cp -r var /
# cp -r etc /
# cp -r usr /
```

5. To restore a database, execute the following command using the username of a user that has administrative privileges in MySQL (by default, the user is **root** and the password is **em7admin**):

```
silo_mysql <name_of_database> -u <username> -p<password> < <name_of_
database>.sql
```

NOTE: Do not include a space between "-p" and the password.

For example, to restore the database "master" as the user "root" with the default password of "em7admin", perform the following command:

silo_mysql master -u root -pem7admin < master.sql</pre>

- 6. To restore all the databases that are included in the backup file, repeat step 5 for each .sql file.
- 7. Re-license the Database Server using the standard licensing procedure. For details, see the section on *Licensing and Configuring an Appliance* in the *Installation and Initial Configuration* manual.

Full Backup

Running a full backup creates a complete backup of the ScienceLogic database. Full backups use a built-in tool call MariaBackup.

You must store full backups on an external system (not the Database Server or All-In-One Appliance). You can specify that full backups be stored on an NFS mount or SMB mount on an external system.

NOTE: SL1 Systems prior to 8.12 allow you to store backups locally. New SL1 systems later than 8.12 require you to store backups on an external system.

NOTE: If you have a large system and very large backup files, you can use an alternative method to perform backups that reduces performance issues during backup. For more information, see the section *Performing Config Backups and Full Backups on a Disaster Recovery Database Server*.

Note the following information about full backups:

- SL1 can launch full backups automatically at the interval you specify.
- During a full backup, the ScienceLogic database remains online.

What Does a Full Backup Include?

A full backup does the following:

- A full backup includes all databases and tables.
- A full backup does not back up the files in /etc/backup.conf.

NOTE: For very large SL1 systems, ScienceLogic recommends you use a SAN with snapshot technology to backup and restore data.

NOTE: If your SL1 System uses AWS RDS (remote database), the Full Backup option is disabled.


Defining a Full Backup

Full backups include all databases and tables. SL1 automatically launches this backup at the frequency and time you specify.

To define and schedule a full backup:

1. Go to the **Backup Management** page (System > Settings > Backup).

2. In the **Full Backup** pane, provide values in the following fields:



- Every. Together with the Interval field, specifies the frequency of the backup.
- Interval. Together with the Every field, specifies how frequently SL1 should automatically execute a full backup. Your choices are:
 - Disabled. Full backups are disabled.
 - Day. SL1 will execute full backups daily as specified (for example, every 2 days).
 - Week. SL1 will execute full backups weekly as specified (for example, every 2 weeks).
 - Month. SL1 will execute full backups monthly as specified (for example, every 1 month).
- Start Time / Date. If you enabled full backups, you must specify the start time. You must specify the date on which you want configuration backups to begin, as well as the time of day you want the backups to run. For example, you might want to run configuration backups during a maintenance window late at night. Click the field to open a calendar and time selector.
- **Timezone**. Optional. Specify the timezone to use when running a backup. The default is UTC. Use the drop-down list to select the timezone.

- **Full Credentials**. Select the credential you created for SL1 to use to connect to your external system (NFS or SMB). For more information, see **Creating a Backup Credential**.
- Full Protocol. Specify the type of external system where the full backup will be stored. Choices are:
 - NFS-Remote. When you select this option, SL1 stores the configuration backup on an NFS share.

NOTE: If you select the NFS-remote option, and your NFS share is hosted on a Solaris system, you must perform the steps listed in the Additional Configuration for Solaris NFS Mounts section.

- SMB-Remote. When you select this option, SL1 stores the configuration backup on an SMB share.
- **Custom mariabackup Options**. Specify one or more custom backup options. For details on these options, see https://mariadb.com/kb/en/mariabackup-options/.
- 3. Select the **[Save]** button to save your settings. SL1 will execute the full backup at the frequency and time you specified in the **Every**, **Interval**, and **Start Time/Date** fields.
- To run the backup immediately, click the [Backup Now] button under Full Backup. SL1 will immediately run the backup and will still run the backup at the frequency and time you specified in the Backup Frequency and Start Time fields.

Restoring a Full Backup

To restore a SL1 system using a full backup file, perform the following steps:

NOTE: These steps assume that the Database Server has not been previously configured.

NOTE: To complete these steps, you must be familiar with how to edit a file using the vi text editor. If you need assistance with these steps, please contact ScienceLogic Support.

1. Either go to the console of the Database Server where you want to restore the backup, or use SSH to log in to the Database Server.

NOTE: The Database Server to which you are restoring the backup must be at the same revision number as the Database Server that created the backup file.

2. Log in as user **em7admin** and then assume root privileges:

\$ sudo -s

4. Execute the following commands:

WARNING: Executing this command will stop the database. SL1 will not be operational until you complete the restore procedure.

```
# systemctl stop em7
# systemctl stop mariadb
# rm -rf /data.local/db/*
```

5. Go to a local directory or a directory on a mounted server that has sufficient space for your data to be extracted. This must be a directory **other than /data.local/db**:

```
# cd <directory for data extraction>
# pigz -dc <full_path_and_name_of_backup_file.gz> | mbstream -x -C .
```

Where <new_subdirectory> is a directory you create that will be the destination for your uncompressed files, and where <full path and filename for backup.tgz> is the location and name of your backup file. For example:

```
# cd /backups/full
# pigz -dc /mnt/db1 full 2021-02-01 21-00-00.gz | mbstream -x -C .
```

6. Execute the following command, where *<subdirectory>* is the directory you created in the previous step:

more /<directory for data extraction>/backup_my.conf

- 7. Locate the line that looks like the following. Copy or write down the exact text that appears, such as:
- innodb_data_file_path=ibdata1:354M;ibdata2:500M:autoextend:max:8925M 8. Execute the following command to edit the /etc/my.cnf.d/silo mysql.cnf file:
 - vi /etc/siteconfig/mysql.siteconfig
- 9. Add the line you copied in Step 7 to the mysql.siteconfig file, such as:

innodb data file path=ibdata1:354M;ibdata2:500M:autoextend:max:8925M

- 10. Save the file and exit the vi editor. To do this, enter :wq.
- 11. Execute the following command to build the updated configuration file:

/opt/em7/share/scripts/generate-my-conf.py -o /etc/my.cnf.d/silo_mysql.cnf

12. Execute the following commands:

```
# mariabackup --prepare --target-dir=
# mariabackup --datadir=/data.local/db --copy-back --target-dir=
# chown -R mysql:mysql /data.local/db/*
# systemctl start mariadb
# systemctl start em7
```

NOTE: Note that these commands assume you have changed directories to the directory that contains the extracted backup files. If you want to run these commands from a location other than the location of the extracted backup files, then you must enter a value after "target-dir=" to point to the directory where the extracted files are located. To learn more about MariaBackup, see https://mariadb.com/kb/en/full-backup-and-restore-with-mariabackup/.

NOTE: Depending on the size of the backup, the mariabackup command might take a long time to complete.

13. Re-license the Database Server using the standard licensing procedure. For details, see the section on *Licensing and Configuring an Appliance* in the *Installation and Initial Configuration* manual.

Retaining Full Backups

SL1 can automatically delete backups to save space on the external system where you store your backup files.

You can specify a retention value. SL1 will keep the retention value plus one additional backup.

To specify the number of full backups to retain, perform the following:

1. Go to the **Database Tool** page (System > Tools > DB Tool).

Databa	ase Tool Database Support	Interface	Actions	Reset	Guide
	Select Database	SQL Query		7	
mast mast mast mast mast		SELECT FROM system_messages;	Go	I	
id s	ev date_edit module	r message			*
1 2	2012-02-22 20:19:32 1	1: proc_mgr received a close signal and is shutting itself down.			E
2 1	2012-02-22 21:43:20 1	11: Alert 395 returned true, but not firing: alert simulation mode is enabled			
3 1	2012-02-22 23:59:54 1	11: Alert 367 returned true, but not firing: alert simulation mode is enabled			
4 1	2012-02-23 01:04:47 1	11: Alert 370 returned true, but not firing: alert simulation mode is enabled			
5 1	2012-02-23 01:22:51 1	11: Alert 1 returned true, but not firing: alert simulation mode is enabled			
6 1	2012-02-23 01:22:51 1	11: Alert 1 returned true, but not firing: alert simulation mode is enabled			
71	2012-02-25 20:00:35 1	82: Something unexpected happened during normalization for Dynamic App Raw Freq 20: izip argument #1 must support iteration			
8 4	2012-02-26 00:00:58 1	143: Unhandled exception during collection, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo	_common/misc.p	/", line 433, i	n new_f File
94	2012-02-26 00:00:58 1	143: Unhandled exception on appliance: 1, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_	common/misc.py	', line 433, in	new_f File
10 4	2012-02-26 02:00:38 1	143: Unhandled exception during collection, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo	_common/misc.p	/", line 433, i	n new_f File
11 4	2012-02-26 02:00:38 1	143: Unhandled exception on appliance: 1, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_	common/misc.py	', line 433, in	new_f File
12 1	2012-02-27 07:00:38 1	82: Something unexpected happened during normalization for Dynamic App Raw Freq 20: izip argument #1 must support iteration			
13 4	2012-02-27 14:00:50 1	143: Unhandled exception during collection, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo	_common/misc.p	/", line 433, i	n new_f File
14 4	2012-02-27 14:00:50 1	143: Unhandled exception on appliance: 1, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_	common/misc.py	', line 433, in	new_f File
15 4	2012-02-27 22:00:38 1	143: Unhandled exception during collection, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo	_common/misc.p	/", line 433, i	n new_f File
16 4	2012-02-27 22:00:39 1	143: Unhandled exception on appliance: 1, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_	common/misc.py	, line 433, in	new_f File
17 4	2012-02-28 04:00:58 1	143: Unhandled exception during collection, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo	_common/misc.p	/", line 433, i	n new_f File
<	2012 02 20 04:00:00 4	2 4 M. Haba and a marked and a subscript of the star o		1 Kara 400 Ka	* ***** }

2. In the SQL Query field, enter the following:

```
UPDATE master.system_settings_backup SET backup_retention = <number of backups
to retain> WHERE id = 2
```

- 3. For example, the following command would retain five full backups, the last four plus the current backup: UPDATE master.system settings backup SET backup retention = 4 WHERE id = 2
- 4. Select the [Go] button to execute the query.
- 5. SL1 will create an entry in /var/log/em7/silo.log when a backup is deleted.

Additional Configuration for Solaris NFS Remote Shares

To use the NFS-remote backup protocol with an NFS share hosted on a Solaris system, you must configure the Solaris system to allow the backup process to change file ownership permissions. To do this:

• In /etc/dfs/dfstab on the Solaris system, you must specify that the fully-qualified domain name of the Database Server or All-In-One Appliance can access the NFS file system as root. For example:

```
share -F nfs -o sec=sys,root=database.sciencelogic.local -d "ScienceLogic
Backup Share" /export/home/backup
```

• In /etc/defaults/nfs on the Solaris system, include the line "NFSMAPID_DOMAIN=<domain of Database Server or All-In-One Appliance>. For example:

NFSMAPID_DOMAIN=ScienceLogic.local

You can test this configuration by mounting the NFS file system from the console of your SL1 appliance, creating a new file on the file system using the "touch" command, and then executing the command "Is -Ia". If the Solaris system is configured correctly, the output of the Is command will indicate that the new file was created and is owned by the "root" user.

DR Backup

For SL1 systems configured for disaster recovery, DR Backup temporarily stops replication, mounts the database, and runs a full backup of the disaster-recovery database. The process then re-enables replication and performs a partial resynchronization from the primary.

You must store DR backups on an external system (not the Database Server or All-In-One Appliance). You can specify that DR backups be stored on a remote NFS mount or SMB mount.

Disaster Recovery Backups use 'tar' to create a copy and compress the /data.local/db directory.

DR backup includes all configuration data, performance data, and log data. During DR backup, the primary ScienceLogic database remains online.

NOTE: The **DR Backup** fields appear only for systems configured for Disaster Recovery. DR Backup is not available for the two-node High Availability cluster.

NOTE: If your SL1 System uses AWS RDS (remote database), the DR Backup option is disabled.

Defining a DR Backup

To define and schedule a DR backup:

1. Go to the **Backup Management** page (System > Settings > Backup).

DR Backup
Every Interval Image: Every Interval Image: Imag
Start Time / Date 2011-01-01 00:00:00
Timezone
DR Credentials
DR Protocol [NFS-Remote]
DR Subdirectory /nfsshare

- 2. In the **DR Backup** pane, provide values in the following fields:
 - **Every**. Together with the **Interval** field, specifies the frequency of the backup.
 - Interval. Together with the **Every** field, you must specify how frequently SL1 should automatically execute a configuration backup. Your choices are:
 - *Disabled*. DR backups are disabled. If you want to run on-demand DR backups only, you do not need to change this setting.
 - Day. SL1 will execute DR backups daily as specified (for example, every 2 days).
 - Week. SL1 will execute DR backups weekly as specified (for example, every 2 weeks).
 - Month. SL1 will execute DR backups monthly as specified (for example, every 1 month).
 - Start Time/Date. If you enabled DR backups, you must specify the start time. You must specify the date on which you want DR backups to begin, as well as the time of day you want the backups to run. For example, you might want to run DR backups during a maintenance window late at night. Click the field to open a calendar and time selector.
 - *Timezone*. Optional. Specify the timezone to use when running a backup. The default is UTC. Use the drop-down list to select the timezone.
 - **DR Credentials**. Select the credential you created for SL1 to use to connect to your external system (NFS or SMB). For more information, see **Creating a Backup Credential**.

NOTE: Your organization membership(s) might affect the list of credentials you can see in the DR Credentials field. For details, see the Discovery and Credentials manual.

- DR Protocol. Specifies where SL1 should store the full backups. Choices are:
 - *NFS-Remote*. When you select this option, SL1 stores the DR backup on an NFS share.

NOTE: If you select the *NFS*-remote option, and your NFS mount is hosted on a Solaris system, you must perform the steps listed in the *Additional Configuration for Solaris NFS Mounts* section of this chapter.

- SMB-Remote. When you select this option, SL1 stores the DR backup on an SMB share.
- **DR Subdirectory**. Specify a directory on the NFS or SMB share in which you would like to store the DR backup. On the remote share, the current Unix time will be appended to the directory name to ensure the directory name is unique each time the backup runs.
- 3. Click the **[Save]** button to save your settings. SL1 will execute the DR backup at the frequency and time you specified in the **Backup Frequency** and **Start Time** fields.
- To run the backup immediately, click the [Backup Now] button under DR Backup. SL1 will immediately run the backup and will still run the backup at the frequency and time you specified in the Backup Frequency and Start Time fields.

Restoring a DR Backup

To restore a Database Server using a DR backup file, perform the following steps:

NOTE: These steps assume that the Database Server has not been previously configured.

- 1. The Database Server to which you are restoring the backup must be at the same revision number as the Database Server that created the backup file.
- 2. Either go to the console of the Database Server where you want to restore the backup or use SSH to access the Database Server.
- 3. Log in as user **em7admin** and sudo to the root account:

```
sudo -s
```

4. Execute the following commands:

WARNING: Executing this command will stop the database. SL1 will not be operational until you complete the restore procedure.

```
systemctl stop em7
systemctl stop mariadb
rm -rf /data/db/*
```

5. Execute the following commands, substituting the full pathname of your backup file:

```
cd /data/db
pigz -dc <full path and name to backup file.tgz> | tar xvf -
mv /data/db/data/db/* .
rm -rf /data/db/data
cp /data/db/etc/my.cnf.d/silo_mysql.cnf /root/silo_mysql.bak
rm -rf /data/db/etc
chown -R mysql:mysql /data/db/*
```

6. Execute the following commands to restart SL1 and the database:

```
systemctl start em7
systemctl start mariadb
```

Retaining DR Backups

SL1 can automatically delete backups to save space on the external system where you store your backup files.

You can specify a retention value. SL1 will keep the retention value plus one additional backup.

To specify the number of DR backups to retain, perform the following:

1. Go to the **Database Tool** page (System > Tools > DB Tool).

tabase Tool Database Suppo	Actions Reset Guide
Select Database	SQL Query
aster_access aster_biz aster_biz aster_custom aster_debug asster_dev asster_dev asster_dev master_ges]	SELECT * FROM system_messages;
sev date_edit moo	ule message
2 2012-02-22 20:19:32 1	1: proc. mgr received a close signal and is shutting itself down.
1 2012-02-22 21:43:20 1	11: Alert 395 returned true, but not firing: alert simulation mode is enabled
1 2012-02-22 23:59:54 1	11: Alert 367 returned true, but not firing: alert simulation mode is enabled
1 2012-02-23 01:04:47 1	11: Alert 370 returned true, but not firing; alert simulation mode is enabled
1 2012-02-23 01:22:51 1	11: Alert 1 returned true, but not firing: alert simulation mode is enabled
1 2012-02-23 01:22:51 1	11: Alert 1 returned true, but not fining; alert simulation mode is enabled
1 2012-02-25 20:00:35 1	82: Something unexpected happened during normalization for Dynamic App Raw Freq 20; izip argument #1 must support iteration
4 2012-02-26 00:00:58 1	143; Unhandled exception during collection, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_1 F
4 2012-02-26 00:00:58 1	143: Unhandled exception on appliance: 1, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_f Fil
4 2012-02-26 02:00:38 1	143: Unhandled exception during collection, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_1 F
4 2012-02-26 02:00:38 1	143: Unhandled exception on appliance: 1, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_f Fil
1 2012-02-27 07:00:38 1	82: Something unexpected happened during normalization for Dynamic App Raw Freq 20: izip argument #1 must support iteration
4 2012-02-27 14:00:50 1	143: Unhandled exception during collection, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_f F
4 2012-02-27 14:00:50 1	143: Unhandled exception on appliance: 1, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_f Fil
4 2012-02-27 22:00:38 1	143: Unhandled exception during collection, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_1 F
4 2012-02-27 22:00:39 1	143: Unhandled exception on appliance: 1, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_f Fil
4 2012-02-28 04:00:58 1	143; Unhandled exception during collection, process IT Service; Service Management Engine; Traceback (most recent call last); File "/usr/local/silo/proc/silo common/misc.pv", line 433, in new 1F
4 0040 00 00 04:00:00 4	

2. In the SQL Query field, enter the following:

```
UPDATE master.system_settings_backup SET backup_retention = <number of backups to retain> WHERE id = 3
```

3. For example:

UPDATE master.system_settings_backup SET backup_retention = 4 WHERE id = 3

would retain five DR backups, the last four and the current backup.

- 4. Select the [Go] button.
- 5. SL1 will created an entry in /var/log/em7/silo.log when a backup is deleted.

Performing Configuration Backups and Full Backups on the Disaster Recovery Database Server

Users with large systems and very large backup files can use an alternative method to back up SL1. This alternative method, performing backups from the Disaster Recovery Database Server, reduces performance issues during backup.

DR Backup is a method for *backing up the Disaster Recovery system*. Performing standard configuration backups or full backups on the Disaster Recovery Database Server is an alternative method to *backup SL1*.

Unlike the DR Backup, which uses tar to make a compressed copy of the /data/db directory, performing a configuration backup from a Disaster Recovery Database Server uses the MySQL Dump tool and backs up the same data as described in the section on **Configuration Backups**.

Unlike the DR Backup, which uses tar to make a compressed copy of the /data/db directory, performing a full backup from a Disaster Recovery Database Server uses the MariaBackup tool and backs up the same data as described in the section on *Full Backups*.

During a configuration backup or full backup from a Disaster Recovery Database Server:

- The Disaster Recovery Database Server does not appear active to any other SL1 appliances.
- No applications or services can connect to the Disaster Recovery Database Server.

NOTE: After you define configuration backups on the Disaster Recovery Database Server, you should disable any other existing configuration backups. However, you can continue to use standard DR Backup to backup your Disaster Recovery system.

NOTE: After you define full backups on the Disaster Recovery Database Server, you should disable any other existing full backups. However, you can continue to use standard DR Backup to backup your Disaster Recovery system.

Configuration Backup on a Disaster Recovery Database Server

To perform a configuration backup on the Disaster Recovery Database Server:

1. Go to the **Database Tool** page (System > Tools > DB Tool).

abase Tool Database Suppor	t Interface Actions Reset Guide
Select Database	SQL Query
aster_access ^ aster_biz aster_custom aster_debug aster_dev aster_dev aster_dev aster_vents master_logs] ~	SELECT FROM system_messages;
sev date_edit modu	le message
2 2012-02-22 20:19:32 1	1: proc_mgr received a close signal and is shutting itself down.
1 2012-02-22 21:43:20 1	11: Alert 395 returned true, but not firing: alert simulation mode is enabled
1 2012-02-22 23:59:54 1	11: Alert 367 returned true, but not firing: alert simulation mode is enabled
1 2012-02-23 01:04:47 1	11: Alert 370 returned true, but not firing: alert simulation mode is enabled
1 2012-02-23 01:22:51 1	11: Alert 1 returned true, but not firing: alert simulation mode is enabled
1 2012-02-23 01:22:51 1	11: Alert 1 returned true, but not firing: alert simulation mode is enabled
1 2012-02-25 20:00:35 1	82: Something unexpected happened during normalization for Dynamic App Raw Freq 20: izip argument #1 must support iteration
4 2012-02-26 00:00:58 1	143: Unhandled exception during collection, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_f F
4 2012-02-26 00:00:58 1	- 143: Unhandled exception on appliance: 1, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_f Fil
4 2012-02-26 02:00:38 1	143: Unhandled exception during collection, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_f F
4 2012-02-26 02:00:38 1	143: Unhandled exception on appliance: 1, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_f Fil
1 2012-02-27 07:00:38 1	82: Something unexpected happened during normalization for Dynamic App Raw Freq 20: izip argument #1 must support iteration
4 2012-02-27 14:00:50 1	143: Unhandled exception during collection, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_f F
4 2012-02-27 14:00:50 1	143: Unhandled exception on appliance: 1, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_f Fil
4 2012-02-27 22:00:38 1	143: Unhandled exception during collection, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_f F
4 2012-02-27 22:00:39 1	143: Unhandled exception on appliance: 1, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_f Fil
4 2012-02-28 04:00:58 1	143: Unhandled exception during collection, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/silo_common/misc.py", line 433, in new_f F
4 0040 00 00 04/00/00 4	4 40. Habba da anticidade da a

2. In the SQL Query field, enter the following:

```
UPDATE master.system_settings_backup SET backup_on_dr = 1 WHERE id = 1
```

- 3. Select the **[Go]** button.
- 4. Follow the instructions in the section on Creating a Credential.

- 5. Following the instructions in the section on **Defining a Configuration Backup**.
- 6. To restore the backup, follow the steps in the section **Restoring a Configuration Backup**.

NOTE: If you enabled configuration backups on the Disaster Recovery Database Server, you should disable standard configuration backups.

Full Backup on a Disaster Recovery Database Server

To perform a full backup on the Disaster Recovery Database Server:

1. Go to the **Database Tool** page (System > Tools > DB Tool).

Databa	ase Tool Database Support	Interface	Actions	Reset	Guide
	Select Database	SQL Query		7	
maste maste maste maste maste	er_access er_biz er_custom er_debug er_dev er_dev er_dev er_des er_events ter_logs]	SELECT FROM system_messages;	Go		
id se	ev date edit moduk	e messaoe			*
1 2	2012-02-22 20:19:32 1	1: proc. mgr received a close signal and is shutting itself down.			E
2 1	2012-02-22 21:43:20 1	11: Alert 395 returned true, but not firing: alert simulation mode is enabled			
3 1	2012-02-22 23:59:54 1	11: Alert 367 returned true, but not firing: alert simulation mode is enabled			
4 1	2012-02-23 01:04:47 1	11: Alert 370 returned true, but not firing: alert simulation mode is enabled			
5 1	2012-02-23 01:22:51 1	11: Alert 1 returned true, but not firing: alert simulation mode is enabled			
6 1	2012-02-23 01:22:51 1	11: Alert 1 returned true, but not firing: alert simulation mode is enabled			
7 1	2012-02-25 20:00:35 1	82: Something unexpected happened during normalization for Dynamic App Raw Freq 20: izip argument #1 must support iteration			
8 4	2012-02-26 00:00:58 1	143: Unhandled exception during collection, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc	/silo_common/misc.p	y", line 433,	in new_f File
9 4	2012-02-26 00:00:58 1	143: Unhandled exception on appliance: 1, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/	silo_common/misc.py	", line 433, i	n new_f File
10 4	2012-02-26 02:00:38 1	- 143: Unhandled exception during collection, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc	/silo_common/misc.p	y", line 433,	in new_f File
11 4	2012-02-26 02:00:38 1	143: Unhandled exception on appliance: 1, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/	silo_common/misc.py	", line 433, i	n new_f File
12 1	2012-02-27 07:00:38 1	82: Something unexpected happened during normalization for Dynamic App Raw Freq 20: izip argument #1 must support iteration			
13 4	2012-02-27 14:00:50 1	143: Unhandled exception during collection, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc			
14 4	2012-02-27 14:00:50 1	-143: Unhandled exception on appliance: 1, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/	silo_common/misc.py	", line 433, i	n new_f File
15 4	2012-02-27 22:00:38 1	143: Unhandled exception during collection, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc			
16 4	2012-02-27 22:00:39 1	143: Unhandled exception on appliance: 1, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc/			
17 4	2012-02-28 04:00:58 1	143: Unhandled exception during collection, process IT Service: Service Management Engine: Traceback (most recent call last): File "/usr/local/silo/proc			
<		4 49. Habaadhad aanaadhaa aa aabaan 4 aanaaa 19 Paadaa Paadaa Haanaada Paalaa Taanabaah / maabaadha Haabh 19 Haadhaaffadaaa /			

2. In the SQL Query field, enter the following:

UPDATE master.system_settings_backup SET backup_on_dr = 1 WHERE id = 2

- 3. Select the **[Go]** button.
- 4. Follow the instructions in the section on Creating a Credential.
- 5. Following the instructions in the section on **Defining a Full Backup**.
- 6. To restore the backup, follow the steps in the section **Restoring a Full Backup** to restore a configuration backup.

NOTE: If you enabled full backups on the Disaster Recovery Database Server, you should disable standard full backups.

Chapter

12

Viewing License Data

Overview

This chapter describes license data for SL1.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon (=).
- To view a page containing all the menu options, click the Advanced menu icon (…).

This chapter includes the following topics:

wing License Information

Viewing License Information

The License Information modal enables you to:

- View a list of all third-party licenses that are aligned with SL1
- Search for specific licenses
- View the full text of each license

To view license information:

1. Click the Toolbox button in the upper-right of the ScienceLogic browser session and then select *License Information*.

C I			Ľ	TRIAL LICENSE: 62 DAYS REMAINING						≜	Logged in as emi	7adm ³
ScienceL	.ogic											
	ds Views Events Ticket	a Knowledge	Reports Re	gistry System Preferences						Bookmarks (Cl		
	os views Events Licket	a <u>K</u> nowneoge	Rep <u>o</u> ra <u>R</u> e	grany System Preterences						Create a Ticke		
4	Device Manager Devices Found [671]									Finder (Ctrl+Al		
vice Manager												
nished Device Manager			Device				Current	Collection	Collection	Home (Ctrl+Al		
vice Components	Device Name *	IP Address	Category	Device Class Sub-class	DID	Organization	State	Group	State			
vice Groups	W						>=Healthy T					(+0)
rdware	1. P 1 5. 10.0.13.20-CTIManager		UC.Service	Cisco Systems CTI Manager Service	1106	System	Healthy 🔬	CUG	Unavailable	My Preference	s (Ctrl+Alt+P)	
rviors	2. 🤌 🚮 🏯 🏯 10.0.13.20-Extension Mobility		UC.Service	Cisco Systems Extension Mobility Service	1109	System	Healthy 🕰	CUG	Unavailable	My Tickets (Ctr		
tware	3. 🕐 🚮 🚉 🚑 10.0.13.20-Tftp		UC.Service	Cisco Systems TFTP Service	1105	System	Healthy 🔬	CUG	Unavailable	Regular Expre	ssion Tester	
mplates	4. A 1 5 5 10.0.13.20-Tomcat		UC.Service	Cisco Systems Torncat	1107	System	Healthy 🕰	CUG	Unavailable	Clear EM7 Sys	tem Cache	
inplates	5. A 10.0.13.20-WebDialer Web Service		UC.Service	Cisco Systems Cisco WebDialer Service	1108	System	Healthy A	CUG	Unavailable	olear Enri oys		
ors	6. 2.1 5. 5. 10.0.13.21-CTIManager		UC.Service	Cisco Systems CTI Manager Service	1115	System	Healthy A	CUG	Unavailable	Auto-Discover	(Ctrl+Alt+A)	
orks	7. A 1 5 5 10.0.13.21-Extension Mobility	. 🦻	UC.Service	Cisco Systems Extension Mobility Service	1118	System	Healthy A	CUG	Unavailable	Organizational		
vices	8. 9 /1 5. 5 10.0.13.21-Tfp		UC.Service	Cisco Systems TFTP Service	1114	System	Healthy A	CUG	Unavailable	Device Manao	ement (Ctrl+Alt+1	
nts	9. 9 1 5 5 10.0.13.21-Torncat		UC.Service	Cisco Systems Torncat	1117	System		CUG	Unavailable		ment (Ctrl+Alt+2)	
	10. A the second		UC.Service	Cisco Systems Cisco WebDialer Service	1116	System		CUG	Unavailable			
	11. 2 1 3 4 10.0.13.22 CTIManager		UC.Service	Cisco Systems CTI Manager Service	1122			CUG	Unavailable	Network IP Ma	nagement (Ctri+A	Mt+3
ess Services	12 P A A 10.0.13.22-Extension Mobility		UC.Service	Cisco Systems Extension Mobility Service	1125	System		CUG	Unavailable	User Accounts	(Ctrl+Alt+4)	
	13. 2 1 2 1 10.13.22-Thp		UC.Service	Cisco Systems TFTP Service	1121	System		CUG	Unavailable	Vendor Manag	ement (Ctrl+Alt+5	
look	14. 2 1 5. 5 10.13.22.Tomcat		UC.Service	Cisco Systems Tomcat	1123	System		CUG	Unavailable	External Conta	Ict Management (I	
ng	15. A 10.13.22-YebDialer Web Service		UC.Service	Cisco Systems Cisco WebDialer Service	1124	System		CUG	Unavailable		_	
Proxies			UC.Device.Trunk	Cisco Systems H323 Trunk	1141	System		CUG	Unavailable	License Inform	ation	
	16. 17. 17. 10.168.37.35 17. 10.168.37.35 17. 10.168.37.35		UC.Device.Trunk	Cisco Systems (H323 Trunk	1152			CUG		EM7 Version In	formation	
						System			Unavailable			
	18. 2 10.7.78.19.415		Network Application		1560	System		CUG	User-Disabled	LOG OFF		
	19. 🤌 🚮 173.36.219.46	9 173.36.219.46	Network.USilty	Cisco Systems ACI	2	ACI		CUG	User-Disabled			
	20. <u>9.前去去</u> access			Cisco Systems ACI Application Network Profile	16	ACI		CUG	Unavailable		- 🖷 😂 🗞	
	21. ACI Fabric 1.: common			Cisco Systems ACI Tenant	12	ACI		CUG	Active			
	22. 🤌 👔 ACI Fabric 1 tinfra			Cisco Systems ACI Tenant	14	ACI		CUG	Active		- 🖷 😳 🗞	
	23. ACI Fabric 1: LeoSimple	9		Cisco Systems ACI Tenant	13	ACI		CUG	User-Disabled			
	24. ACI Fabric 1:mgmt			Cisco Systems ACI Tenant	11	ACI		cug	User-Disabled	-	- 🖷 😳 🗞	
	25. 🤌 🚮 Amazon Cloud		Cloud.Service	Service AWS Service	1651	System		CUG	Active		- 📾 👯 🗞	
	26. P 1 4 4 ANN			Cisco Systems ANN Container	1112	System		CUG	Unavailable	Cisco SNMPv2 - Ex		
	27. 🤌 🚮 🏯 🏯 ANN		UC.MediaResource	Cisco Systems ANN Container	1850	System	Healthy 🕰	CUG	Unavailable	Cisco SNMPv2 - Ex	1 V2 🗎 🕄 🖏	
	28. 🔑 🚮 🚉 🚉 ANN_2		UC.MediaResource	Cisco Systems ANN	1135	System	Healthy 🔬	CUG	Unavailable	Cisco SNMPv2 - Ex	: V2 😸 🖏 🗞	
	29. 🤌 🛔 🛔 ANN_3	- 10	UC.MediaResource	Cisco Systems ANN	1134	System	Healthy A	CUG	Unavailable	Cisco SNMPv2 - Ex	: V2 📑 💆 🗞	1
	30. 🤌 🚮 🤹 👙 ANN_4		UC.MediaResource	Cisco Systems ANN	1136	System	Healthy 🖄	CUG	Unavailable	Cisco SNMPv2 - Ex	: V2 📾 👯 🗞	
	31. 🤌 🚮 🚊 🚑 apic 1		Network Application	Cisco Systems ACI APIC Controller	8	ACI	Major 🛆	CUG	User-Disabled		- 10 10 10	
	32. 9 m A. A. apic2		Network Application	Cisco Systems ACI APIC Controller	6	ACI	Major 🗥	CUG	User-Disabled		- 1829	
	33. A at 5 apic3		Network Application	Cisco Systems ACI APIC Controller	7	ACI	Critical 🗛	CUG	User-Disabled		- 10120	
	34. P 1 + + auto2container1		Cloud Storage	Microsoft Azure Storage Container	891	Azure	Healthy 🕰	CUG	Unavailable			
	35. 9 at A AutoCloud		Cloud.Compute	Microsoft Azure Cloud Service	812	Azure	Major (1)	CUG	Unavailable			
	36. 9 A A automationstore2		Cloud Account	Microsoft Azure Storage Account	777	Azure	Major (1)	CUG	Unavailable		- 00 22 80	
	37. 9 M A A AutoNetwork		Cloud Network	Microsoft Azure Virtual Network	860	Azure		CUG	Unavailable			
	38. 9 A Azure Cloud		Cloud Service	Microsoft Azure Services	680	Azure		CUG	Active		- 1029	
	39. A state course		Cloud Storage	Microsoft Azure SQL Database	1026	Azure		cug	Unavailable		- 1000	
	40.		Cloud Account	Microsoft Azure Account	681	Azure		CUG	Active		- 1020	
	41. P 1 5 5 BIG-IP LTM Service			F5 Networks, Inc. BIG-IP Local Traffic Manager		System		CUG	Active	SNMP Public V2	V2 m 10 %	
	Verving Page: 1]		recorder opportunit	i o monoria, mar j anorar bocar manager	1220	3731011	meany A		Photo Contraction of the second secon	Stear Public V2	·· · · · · · · · · · · · · · · · · · ·	

The License Information modal appears. All of the licenses that are aligned with SL1 are listed.

2. On the License Information modal, you can do the following:

d Ali Collapse Ali	search for name of software or license
Adobe Flex Software Development Kit v3.0 Software Flex SDK	e License
Adobe Font Metrics File Format Specification License AFMParse - Parse Adobe Font Metrics Files	
Apache License 2.0	
ncclient, cordova-plugin-dialogs, fakeworker-js, cordova-plugin-dialogs, cordova-plugin-file, Libr-mobile, xmltopdf, habitrpg-mobile, Apache Cas cordova-mobile-spec, OnlineLecturerAppointmentSystem, phonegap-st quickstarts, OpenOffice	ssandra, excanvas, jQuery Impromptu, Apache-HTTP Server, Cordova
quickstarts, openonice	
Apache License, Version 2.0 Apache License Version 2.0, January 2004 http://www.apache.org/licenses/	
Apache License, Version 2.0 Apache License Version 2.0, January 2004	
Apache License, Version 2.0 Apache License Version 2.0, January 2004 http://www.apache.org/licenses/	
Apache License, Version 2.0 Apache License Version 2.0, January 2004 http://www.apache.org/licenses/ TERMS AND CONDITIONS FOR USE, REPRODUCTION, AND DISTRIBUTION	bution as defined by Sections 1 through 9 of this document.
Apache License, Version 2.0 Apache License Version 2.0, January 2004 http://www.apache.org/licenses/ TERMS AND CONDITIONS FOR USE, REPRODUCTION, AND DISTRIBUTION 1. Definitions.	,
Apache License, Version 2.0 Apache License Version 2.0, January 2004 http://www.apache.org/licenses/ TERMS AND CONDITIONS FOR USE, REPRODUCTION, AND DISTRIBUTION 1. Definitions. "License" shall mean the terms and conditions for use, reproduction, and distrib	t owner that is granting the License. nat control, are controlled by, or are under common control with that or indirect, to cause the direction or management of such entity,

- To view any license in its entirety, click its right-arrow icon. When you do, the icon becomes a downarrow, and the full license information appears.
- To view all of the licenses in their entirety, click the **Expand All** link.
- To view only the condensed information for each license, click the Collapse All link.
- To search for a specific license, type part or all of its name in the search box in the upper-right of the page and then press the **Enter** key.

Chapter

13

Subscription Licenses

Overview

If you have a subscription license, you can use the **Subscription Usage** page (Manage > Subscription Usage) to:

- View current or historical subscription license usage graphs
- Download subscription license usage data for manual upload to the ScienceLogic billing server
- Upload a receipt from the ScienceLogic billing server

If your SL1 system is configured to communicate with the ScienceLogic billing server, usage data will be sent automatically from your SL1 system to the ScienceLogic billing server once a day. After the ScienceLogic billing server receives the usage data, SL1 will automatically mark the license usage file as delivered.

If your SL1 system is not configured to communicate with the ScienceLogic billing server or if the connection to the ScienceLogic billing server fails, you can manually upload usage data to the ScienceLogic billing server.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon (三).
- To view a page containing all the menu options, click the Advanced menu icon (…).

This chapter includes the following topics:

Viewing the Subscription License Usage	275
Viewing Delivery Status	.275
Manually Uploading License Usage to ScienceLogic	276
Downloading the Daily License Usage File	277
Manually Uploading the Daily License Usage File to ScienceLogic	.278

Uploading the ScienceLogic Receipt	
Data Retention Settings for Licensing	

Viewing the Subscription License Usage

If you have a subscription license, you can view a dashboard on license usage for your SL1 system. To view the dashboard containing the license usage for your SL1 system:

1. Go to the **System Usage** page (Manage > Subscription Usage). The **Subscription Usage** page appears.

Subscription Usage				Activity Jude.Evans-Mccarthy	v 👽 ScienceLogie
Current License Usage Totals		Historical License Usage Totals			Last Quarter 👻
10		1000		1	1
5		500		host hassast	W
Infrastructure Non-Billable	: Ratio Storage n-Billable 🔵 Ratio 🔵 Storage	Jul 20	Aug '20 🔶 Non-Billable	Sep '20 Ratio Storage Inactive	
Current License Usage by Device	e to search device licenses			≡ ✿ License Da	ta Delivery Status
DEVICE NAME	ORGANIZATION	CLASS	CATEGORY	LICENSE TYPE	
Restorepoint Appliance	Network	Restorepoint Appliance	Servers	Infrastructure	
AIDAIHXVQSNXTUJBFOWYE	System	AWS Account	Cloud.Account	Infrastructure	
rstlsvcsa6u2a01	VMware	VMWare vCenter Server Appliance	Servers.VMware	Infrastructure	
10.2.5.72	VMware	VMWare vCenter Server Appliance	Servers.VMware	Infrastructure	
cscol26	System	ScienceLogic, Inc. EM7 Data Collector	System.EM7	Non-Billable	
cscol27	System	ScienceLogic, Inc. EM7 Data Collector	System.EM7	Non-Billable	
bl-db	System	ScienceLogic, Inc. EM7 Database	System.EM7	Non-Billable	

- 2. The dashboard displays three reports:
 - Current License Usage Totals
 - Historical License Usage Totals
 - Current License Usage by Device or Current License Counts by Device Class, depending on your selection

Device categories depend upon your specific license agreement with ScienceLogic. The types of license categories that appear in the dashboard reports will reflect your license agreement with ScienceLogic.

Viewing Delivery Status

The License Data Delivery Status page displays the status of one or more daily license usage files. To view the License Data Delivery Status page:

- 1. Go to the **Subscription Usage** page (Manage > Subscription Usage).
- 2. Click the [License Data Delivery Status] button.
- 4. The License Data Delivery Status modal appears and displays a list of daily license usage files. For each daily license usage file, the License Data Delivery Status page displays the following:
 - Summary Date. Date associated with the daily license-usage file.
 - Delivery Status. Possible values are:
 - "0" (zero). File has not been uploaded to the ScienceLogic billing server.
 - "1" (one). File has been uploaded to the ScienceLogic billing server and may be deleted from the SL1 system by the automated maintenance process.
 - Summary Size. Size of the daily license usage file.

icense Da				Reset Down	
All	Summary Date *	v]	Delivery Status	Summary Size (kB)	[
1.	2020-10-04 00:00:00		0	10948.4	
2.	2020-10-03 00:00:00		0	10948.4	(
3.	2020-10-02 00:00:00		0	10948.4	
4.	2020-10-01 00:00:00		0	10948.4	[
5.	2020-09-30 00:00:00		0	10948.4	
6.	2020-09-29 00:00:00		0	10948.4	(
7.	2020-09-28 00:00:00		0	10948.4	
8.	2020-09-27 00:00:00		0	10948.4	(
9.	2020-09-26 00:00:00		0	10948.4	
10.	2020-09-25 00:00:00		0	10948.4	[
11.	2020-09-24 00:00:00		0	10948.4	

Manually Uploading License Usage to ScienceLogic

If your SL1 system is configured to communicate with ScienceLogic, usage data will automatically be sent to the ScienceLogic billing server once a day. After the ScienceLogic billing server receives the usage data, SL1 will automatically mark the license usage file as delivered.

If your SL1 system is not configured to communicate with ScienceLogic or if the connection to the ScienceLogic billing server fails:

- You can use the License Data Delivery Status page to manually download the daily license-usage file.
- You can then log in to the ScienceLogic billing server and manually upload the daily license-usage file.
- You can then use the License Data Delivery Status page to upload the ScienceLogic "receipt" to your SL1 system, allowing SL1 to mark the license usage file as delivered.
- License usage files will not be deleted from your system until they are delivered.

Downloading the Daily License Usage File

If your SL1 system is not configured to communicate with ScienceLogic or if the connection to the ScienceLogic billing server fails, you can use the **License Data Delivery Status** page to manually download the daily license usage file. You can then log in to the ScienceLogic Licensing and Billing server and manually upload the daily license usage file.

To download the daily license-usage file using the License Data Delivery Status page:

- 1. Go to the **Subscription Usage** page (Manage > Subscription Usage).
- 2. Click [License Data Delivery Status].

3. Select one or more daily license usage files to download to your local computer, and then click the **[Download]** button.

	Summary Date +		Delivery Status	Summary Size (kB)	
All		► A		▼	
1.	2020-10-04 00:00:00		0	10948.4	
2.	2020-10-03 00:00:00		0	10948.4	
3.	2020-10-02 00:00:00		0	10948.4	
4.	2020-10-01 00:00:00		0	10948.4	
5.	2020-09-30 00:00:00		0	10948.4	
6.	2020-09-29 00:00:00		0	10948.4	
7.	2020-09-28 00:00:00		0	10948.4	
8.	2020-09-27 00:00:00		0	10948.4	
9.	2020-09-26 00:00:00		0	10948.4	
10.	2020-09-25 00:00:00		0	10948.4	
11.	2020-09-24 00:00:00		0	10948.4	

NOTE: If the download size exceeds 50MB, the [Download] button is disabled.

4. The daily license usage file is saved to your local computer. The downloaded file is usually named "license_ data.json.gz".

Manually Uploading the Daily License Usage File to ScienceLogic

After downloading the daily license usage file to your local computer, you can manually upload the file to the ScienceLogic billing server. To do this:

- 1. Log in to the ScienceLogic billing system.
- 2. Go to the **Subscription Data** page (Preferences > Account > Subscription Billing).
- 3. In the **Subscription Data** page, go to the **Subscription Data Update** pane. Use the **[Browse]** button to find the daily license-usage file that you downloaded to your local computer.

4. Click the **[Get Update]** button to upload the daily license-usage file to the ScienceLogic server.

bscription Data For [System Administrator] Organization: System	Rest Guide
ubscription Data Update	License Dala File Choose File No file chosen Get Update
ubscription Data Receipt Status	From (07/11/2015 To (10/11/2015 Get Status
evice Count by License Type	
	- No Data -

5. The ScienceLogic server will provide a "receipt" file for you to download. This file is usually called "status_ updated.json.gz". You must upload this receipt to your SL1 system.

Uploading the ScienceLogic Receipt

After uploading the daily license usage file to the ScienceLogic Billing server, the ScienceLogic server will provide a "receipt" file for you to download. This file is usually called "status_updated.json.gz".

You must upload this "receipt" file to your SL1 system to inform your SL1 system that the upload was successful and that the SL1 system may delete the daily license usage file.

To upload the "receipt" file:

- 1. Go to the **Subscription Usage** page (Manage > Subscription Usage).
- 2. Click [License Data Delivery Status].
- 3. In the Status Update File field, click [Choose File] and browse to locate the "receipt" file.

4. Click the [Upload] button to upload the "receipt" file to your SL1 system.

	Summary Date •		Delivery Status	Summary Size (kB)	v
All		▼ All		▼	
1.	2020-10-04 00:00:00		0	10948.4	
2.	2020-10-03 00:00:00		0	10948.4	
3.	2020-10-02 00:00:00		0	10948.4	
4.	2020-10-01 00:00:00		0	10948.4	C
5.	2020-09-30 00:00:00		0	10948.4	
6.	2020-09-29 00:00:00		0	10948.4	
7.	2020-09-28 00:00:00		0	10948.4	
8.	2020-09-27 00:00:00		0	10948.4	
9.	2020-09-26 00:00:00		0	10948.4	
10.	2020-09-25 00:00:00		0	10948.4	C
11.	2020-09-24 00:00:00		0	10948.4	
8. 9. 10.	2020-09-27 00:00:00 2020-09-26 00:00:00 2020-09-25 00:00:00		0 0 0	10948.4 10948.4 10948.4	

Data Retention Settings for Licensing

The Data Retention Settings page contains settings for subscribers.

To adjust these settings:

- 1. Go to the **Data Retention Settings** page (System > Settings > Data Retention).
- 2. The following sliders appear under the **Subscription Data Retention** heading:
 - **Subscriber Device Configuration Data**. For users with a subscriber license. Number of months to retain the files and database tables that contain configuration information for a device. Default value is twelve months.
 - **Subscriber Device Usage Data**. For users with a subscriber license. Number of months to retain information on total number of events and total number of tickets. Default value is six months.
 - Subscriber System Configuration Data. For users with a subscriber license. Number of months to retain the files and database tables that contain configuration information for the SL1 system. Default value is twelve months.

- **Subscriber System Usage Data**. For users with a subscriber license. Number of months to retain information on total number of events and total number of tickets. Default value is six months.
- **Subscriber Device Type Data**. For users with a subscriber license. Number of months to retain the files and database tables that map each device to a device category, as per your subscriber license. Default value is six months.
- Subscriber Daily Delivery Data. For users with a subscriber license. Number of months to retain the "crunched" license usage data that is calculated each day using the Subscriber Device Configuration Data, Subscriber System Configuration Data, Subscriber System Usage Data, and Subscriber Device Type Data. SL1 will not prune data that has not yet been delivered to the ScienceLogic Licensing and Billing server.

Chapter

14

CAC Authentication

Overview

SL1 supports CAC authentication. The **Client Certificate & CAC Authentication** page allows you to define a check for SSL certificate that controls whether the login page is displayed to the end user. This feature is primarily used to authenticate Common Access Card (CAC) users against a Department of Defense (DoD) issued serverside certificate; however, based on your business needs, this feature can also be used with your own client/server certificates.

The CAC is a United States DoD smartcard issued as standard identification for active duty military personnel, reserve personnel, civilian employees, and eligible contractor personnel.

Each CAC contains a client-side security certificate from the DoD certificate authority (DoD Root CA). This clientside certificate allows the CAC to authenticate with web servers that include the server-side security certificate from the DoD certificate authority. Web servers with the server-side security certificate are deemed secure for DoD use.

SL1 allows you to configure appliances that provide the user interface (Administration Portal, All-In-One Appliance, or the Database Server) for use with DoD certificates or your own certificates. You can install serverside certificates on the user interface appliances and then authenticate access to those web servers with a CAC or a client-side certificate associated with a user's web browser.

When authentication of the client-side certificate against the server-side certificate is successful, the CAC is used as the user's authentication to SL1. If the Authentication Profile contains both the "CAC/Client Cert" and "EM7 Login Page" credential sources *and* a CAC is not presented or is invalid, then the ScienceLogic login page is presented to the end user.

NOTE: Currently, SL1 does not support client-side certificate authentication for login to the console, either through SSH or through a keyboard connected to the appliance.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon (=).
- To view a page containing all the menu options, click the Advanced menu icon (…).

This chapter includes the following topics:

Prerequisites	.283
Importing SSL Certificates	. 284
Extracting the Common Name from a Certificate for Authentication	.286
Defining the Client Certificate Chain	.287
Verifying SSL Certificate File Import and Resolving Issues	288
Clear the SL1 Cache and Restart NGINX	. 289
Testing the Configuration	
Special Circumstance: Multiple Levels of Intermediate Certificates	. 292
Accessing the Appliance without CAC Authentication	.292

Prerequisites

To use client certificate authentication with SL1, you must first meet the following requirements:

- 1. Organizations must be configured. For more information, see "Creating and Editing Organizations" in the **Organizations and Users** manual.
- (Optional) Configure User Policies if you will use EM7 authentication. You do not need to configure user policies if you are using Active Directory (AD) or LDAP. For more information, see "Creating a User Policity" in the Organizations and Users manual.
- 3. If you are using LDAP or Active Directory as your user store, you must configure this as your Authentication Resource before setting up your Authentication Profile. For more information, see Authentication Resources.
- 4. Configure an Authentication Profile for CAC authentication. When setting up your Authentication Profile for CAC, align the "CAC/Client Cert" credential with the profile as the first credential source. Align the EM7 Login Page as a secondary credential source for administrator access. For more information, see Creating an Authentication Profile.
- 5. Your users must have either:
 - Valid CACs with valid client-side certificates already loaded onto the cards, or
 - Valid client-side certificates installed in their web browser.

- If CACs are used, the browser through which the user logs on to the user interface must be able to read security certificates from the cards. For Mozilla Firefox, users can install <u>http://www.forge.mil/Resources-Firefox.html</u>. For Internet Explorer, users must purchase and install commercial software for reading security certificates.
- 6. Enable the Force Secure HTTPS setting. In the **Behavior Settings** page (System > Settings > Behavior), enable this setting by selecting the checkbox. Only when the Administration Portal, All-In-One Appliance, or the Database Server uses HTTPS will the appliance request a security certificate from the CAC or client web browser.
- 7. In the SSL Certificates page (System > Settings > Authentication > Admin SSL Certificates), you must install the server-side certificate on the Administration Portal, All-In-One Appliance, or the Database Server in PEM format. For CAC authentication, the server-side certificate is issued by the DoD. To learn more about importing a certificate, see the section Importing an SSL Certificate.

```
NOTE: If you want to extract part of the Common Name to customize the username that is displayed
in SL1 after CAC authentication, you can edit the ScienceLogic configuration file to customize
the displayed username. You do not need to do this if you are using the msUPN. For more
information, see Extracting the Common Name from a Certificate for Authentication.
```

 In the Client Certificate & CAC Authentication page (System > Settings > Authentication > CAC Client Cert Auth), you must configure the server-side certificate and test it against your client-side certificate. For more information, see Defining the Client Certificate Chain.

Importing SSL Certificates

Secure Sockets Layer, or SSL, is a protocol for securely transmitting data via the Internet. SSL uses a private key to encrypt data to be transferred over an Internet connection. In SL1, you can import server-side SSL certificate files, including DoD certificate files used in CAC authentication, to the Administration Portal, All-In-One Appliance, or the Database Server.

Note the following:

- You must have one root certificate and one certificate for each intermediate authority in the client certificate chain. If you have users with CACs issued by different intermediate authorities, you must import SSL certificates for all possible client authentication chains into SL1.
- All SSL certificates must be in PEM format.
- You can test your SSL certificate files by using the following command, where <certificate_file_name> is the full name of the certificate file:

```
openssl x509 -text -noout -in <certificate_file_name>
```

TIP: It is a best practice to check each certificate file before attempting to import the file. If you encounter an error, resolve that error before you continue.

To import an SSL certificate for CAC authentication:

- 1. Go to the SSL Certificates page (System > Settings > Authentication > SSL Certificates).
- 2. In the SSL Certificates page, click the [Actions] menu. Select Import PEM Certificate File. The Import Certificate File (PEM format) modal appears.

SSL Certificate	×
Import Certificate File (PEM format)	Reset
Description	
CA File Browse for file Browse	e
Save	

- 3. In the Import Certificate File (PEM format) modal, enter the following:
 - **Description**. Description of the certificate.
 - CA File. Browse for the server-side certificate file on your local computer.
- 4. Click the **[Save]** button to load the certificate to the Administration Portal, All-In-One Appliance, or the Database Server.
- Repeat these steps for each certificate file you want to import. When finished, verify that all of your certificates appear in the listing shown on the SSL Certificates page (System > Settings > Authentication > SSL Certificates).

TIP: A best practice is to make note of the value in the Hash field shown for each certificate and verify that the hash values match the symlink files in the /var/lib/em7/certs directory on the appliance after completing the configuration of your client certificate chain. You will use these hash values in *Verifying SSL Certificate File Import and Resolving Issues*.

Extracting the Common Name from a Certificate for Authentication

By default, the certificate configuration file (em7_certificate.conf) is configured to display the full common name (CN) of the CAC user as the username in SL1 after authentication. If this meets your requirements, then you do not need to update the configuration file and can skip this section.

NOTE: If you are using the Microsoft User Principal Name (MS UPN) in your certificates, you do not need to make any edits in the configuration file.

However, if you require that SL1 use only a portion of the CN, then you can edit the certificate configuration file to parse out a username from the CN in the certificate.

For example, in some instances you might want to use an employee's ID number as the username. To do that, you must edit the Nginx configuration file.

To do so:

- 1. Log in to the console of the ScienceLogic appliance as the root user.
- 2. Navigate to the directory /etc/ngnix/conf.d/:

```
cd /etc/ngnix/conf.d/
```

3. Open the file em7_certificate.conf with a text editor like vi:

vi em7_certificate.conf

4. Modify the file to extract the CN from the full Distinguished Name (DN) found in the certificate based on how you want to map the username to an LDAP system or how you want the usernames to look if you are using SL1 internal as the backend of your authentication configuration.

This is the default configuration of the file:

```
# Create the Username for EM7 to use from the Certificate
# Default: Pull the Common Name from the DN.
map $ssl_client_s_dn $ssl_client_username {
    ~/?CN=(?<CN>[^/,]+) $CN;
}
```

Modify the string to extract the name. The following is a regular expression that extracts the CN from the full DN) found in the certificate:

```
map $ssl_client_s_dn $ssl_client_username { ~/CN=[A-Z\.]+(?<num>[0-9]+)
$num; }
```

5. Save and quit (:wq) the file.

Defining the Client Certificate Chain

When you define a CAC or client-side certificate on a web browser, you are actually selecting a server-side certificate on the SL1 appliance and testing the client-side certificate (on your browser or your CAC) against the certificate on the appliance.

You can also define some custom settings for client-side certificate authentication. You can define error messages that are displayed to the end user if authentication fails. Optionally, you can also define IP addresses in this modal for which the user interface will not perform certificate authentication, if you have not already created an Authentication Profile for this purpose. See Accessing the Appliance without CAC Authentication for more information.

When authentication is successful, the user interface displays the **ScienceLogic Login** page to the user.

To define the authentication settings:

- 1. Access the user interface with your CAC or a browser with your client-side certificate installed.
- 2. Go to the **Client Certificate & CAC Authentication** page (System > Settings > Authentication > CAC Client Cert Auth).

Certificate & CAC Authentication Feature disabled	
	Root CA Certificates
	Auth Failure Message
₿ ~	A TI* ● ¶ * ブ = 亘 □ □ □ □ ● □ Ø ●
Start t	(ping
	Save

- 3. Supply a value in each of the following fields:
 - **Root CA Certificates**. Select all root and intermediate certificates that make up the chain from a list of certificates installed on the **SSL Certificates** page (System > Settings > Authentication > Admin SSL Certificates). Your client-side certificate will be authenticated against the selected server-side root and intermediate certificates.
 - Auth Failure Message. Enter text for the error message that appears to users if authentication fails.

CAUTION: Do not leave the default text in the "Auth Failure Message" field.

- Ignore Networks. In this field, you can enter a list of networks and hosts from which certificate authentication is not required. During each login, the platform will compare the client's IP address to the list entered in this field. If the client's IP address is included in this field, SL1 will not require certificate authentication from that client.
 - **NOTE:** If you are using Authentication Profiles to configure access from specific resources from which certificate authentication is not required, you do not need to use the *Ignore Networks* field. For more information, see Accessing the Appliance without CAC Authentication.
 - In the *Ignore Networks* field, you can enter one or more IP addresses, each separated by a newline character (press the [**<Enter>**] key).
 - In the list of IPs to ignore, you can enter only the first octet, only the first and second octet, only the first, second, and third octet, or all four octets. SL1 will interpret the entry as if the rightmost octet is followed by * (asterisk).

For example:

- 192.168.10.142 will allow a single host to log in to the user interface without certificate authentication
- 192 behaves the same as entering 192*. This will allow all hosts included in 192.0.0.1 through 192.254.254.254 to log in to the user interface without certificate authentication
- 192.168.10.24 behaves the same as entering 192.168.10.24*. This will allow all hosts 192.168.10.24, 192.168.10.240, 192.168.10.241, 192.168.10.242, 192.168.10.243, 192.168.10.244, 192.168.10.245, 192.168.10.246, 192.168.10.247, 192.168.10.248, and 192.168.10.249
- 4. Click the **[Save]** button to save your settings. The user interface displays the message:

Settings Saved Successfully. Configuration must be tested in order to take effect.

CAUTION: Do not click the Test link at this time.

Verifying SSL Certificate File Import and Resolving Issues

After you have imported your SSL certificates and configured your client certificate chain, it is important to verify the your certificate files were imported correctly and are valid in SL1.

To verify that your SSL certificate files were imported correctly:

- 1. Either go to the console of the SL1 appliance where you imported the SSL certificates, or use SSH to log in.
- 2. Navigate to the /var/lib/em7/certs directory.

3. Review the list of hash symlink files in the directory and compare them to the list of certificates on the SSL Certificates page. Ensure that the hash values shown in SL1 match the hash symlink files. Note that the hash symlink in the /var/lib/em7/certs directory (in blue text) for a certificate file is appended with ".0", as shown in the image below.

	in]# ll /vai	r/lib/e	em7/o	cert	cs/	
total 140						
lrwxrwxrwx. 1 s-em7-http	s-em7-core	21	Jun	25	03:41	4f5db21f.0 -> DoDpem
lrwxrwxrwx. 1 s-em7-http	s-em7-core	21	Jun	25	03:41	60085f15.0 -> DoD .pem
lrwxrwxrwx. 1 s-em7-http	s-em7-core	21	Jun	25	03:41	9cf5f371.0 -> DoD .pem
lrwxrwxrwx. 1 s-em7-http	s-em7-core	21	Jun	25	03:41	d7fc5635.0 -> DoD .pem
-rw-rr 1 s-em7-http	s-em7-core	1716	Jun	25	03:35	pem
-rw-rr 1 s-em7-http	s-em7-core	1716	Jun	25	03:36	pem
-rw-rr 1 s-em7-http	s-em7-core	1753	Jun	25	03:36	pem
-rw-rr 1 s-em7-http	s-em7-core	1753	Jun	25	03:37	pem
-rw-rr 1 s-em7-http	s-em7-core	1753	Jun	25	03:37	pem
-rw-rr 1 s-em7-http	s-em7-core	1269	Jun	25	03:35	.pem
lrwxrwxrwx. 1 s-em7-http	s-em7-core	22	Jun	25	03:41	ebe73690.0 -> DoD 3.pem
lrwxrwxrwx. 1 s-em7-http	s-em7-core	21	Jun	25	03:41	ec465775.0 -> DoDpem
-rw-rw-r 1 s-em7-core	s-em7-core	9960	Jun	25	03:41	em7_combined.crt
-rw-rw-r 1 s-em7-core	s-em7-core	1489	Jun	2	00:35	em7_default.crt
-rw-rw-r 1 s-em7-core	s-em7-core	11972	Jun	2	00:35	<pre>em7_import_dodeca2.cac</pre>
-rw-rw-r 1 s-em7-core	s-em7-core	10485	Jun	2	00:35	em7_import_dodeca.cac
-rw-rw-r 1 s-em7-core	s-em7-core	5302	Jun	2	00:35	<pre>em7_import_rel3_dodroot_1024.cac</pre>
-rw-rw-r 1 s-em7-core	s-em7-core	66452	Jun	2	00:35	<pre>em7_import_rel3_dodroot_2048.cac</pre>
-rw-rr 1 s-em7-http	s-em7-core		Jun	25	03:41	f9b9dee864d0b27dda9dde4bbdfb9cf7.sync
[root@aio-169-161 em7adm:	in]#					

All of the following must be true. If any of these are not true, then the certificate file was not imported and saved correctly in SL1:

- One hash symlink file should exist in the directory for each of the imported certificate files.
- The file size of the "em7_combined.crt" file is equal to the combined file sizes of all of the certificate (.pem) files. (The file "em7_combined.crt" *is not* equal to the "em7_default.crt" file.)
- When you view the contents of the "em7_combined.crt" file using cat or similar command, the file is the concatenation of all of the certificate (.pem) files. NGINX references the "em7_combined.crt" file as the file containing the client certificate chain.
- 4. If any of the conditions listed above are not true, then the certificate file was not imported and saved correctly in SL1. To resolve the problem:
 - a. Log in to the SL1 appliance user interface.
 - b. Go to the Client Certificate & CAC Authentication page ().
 - c. Edit the Auth Failure Message field. Make a change to the section.
 - d. Click [Save].
 - e. Repeat steps 1-3 to verify your certificate files.

Clear the SL1 Cache and Restart NGINX

Before you proceed to testing the configuration, you must clear the SL1 cache, restart NGINX, and close any browsers you have open. This will ensure the best outcome when testing.


- 1. Log in to the user interface on the given SL1 appliance.
- 2. Click on the **[Toolbox]** button () and choose Clear SL1 System Cache.
- 3. Log out of the SL1 appliance.
- 4. Either go to the console of the SL1 appliance where you imported the SSL certificates, or use SSH to log in.
- 5. Run the following command to restart NGINX: sudo systemctl restart nginx
- 6. Log out of the SL1 appliance completely. Close any open browsers that have been used to access the appliance

Testing the Configuration

After you define the certificate authentication settings, you must test your client-side certificate against the serverside certificate you selected in the **Root CA Certificates** field. Testing your configuration is required to prevent an incorrect configuration from preventing administrator access to the user interface. If the test is successful, the certificate authentication settings will be applied. If the test is unsuccessful, the certificate authentication settings will not be applied.

To test certificate authentication settings:

- 1. With your CAC inserted in the reader, access the user interface of your SL1 appliance, and log in with an administrator account.
- 2. Go to the **Client Certificate & CAC Authentication** page (System > Settings > Authentication > CAC Client Cert Auth).



4. After defining the certificate, you will see the following message at the top of the pane:

Configuration must be tested in order to take effect: TEST.

5. Click the **TEST** link. SL1 will attempt to authenticate your client-side certificate against the selected serverside certificate. 6. If the test authentication is successful, SL1 will display the following message at the top of the pane and end users with the appropriate client certificate or CAC can now access the user interface using client certificate authentication:

Configuration verified and enabled.

- 7. A new field, *Client Cert / CAC Auth*, appears with a default value of *Allowed*. You can select one of the following values for this field:
 - Allowed. This is the default value. Users with CAC and a corresponding account in the platform are
 automatically logged in to the platform when the user enters the URL of the Administration Portal or
 the All-In-One. If a CAC user does not have an account defined in the platform, the login screen is
 displayed. When a non-CAC user enters the URL of the Administration Portal or the All-In-One, they
 will see the message defined in the Auth Failure Message field (defined in the previous section).
 - Locked. Users with CAC and an aligned account in the platform are automatically logged in to the platform when the user enters the URL of the Administration Portal or the All-In-One. If a CAC user does not have an account defined in the platform, or a user does not have a CAC, when that user enters the URL of the Administration Portal or the All-In-One, they will see the message defined in the **Auth Failure Message** field (defined in the certificate authentication settings).

NOTE: ScienceLogic recommends that you set this field to *Locked* unless your implementation specifically requires one of the other options.

- Disabled. When a user enters the URL of the Administration Portal or the All-In-One Appliance, the platform displays the login screen.
- 8. Set the Certificate User Field to "Common Name" (default) or "MS UPN".

NOTE: If you are using LDAP or Active Directory (AD) for user authentication, set this field to "MS UPN".

- 9. Select the [Save] button to save the setting in the Client Cert / CAC Auth field.
- 10. If the test authentication is unsuccessful, the user interface will display the following message at the top of the pane. The settings will not be applied, and client certificate authentication will not be used until the problem is corrected:

 $\ensuremath{\mathsf{ERROR}}$: configuration was not successfully tested with CAC or Client Certificate.

Special Circumstance: Multiple Levels of Intermediate Certificates

By default, SL1 is configured to handle the typical certificate hierarchy, which comprises three levels: root, intermediate, and client certificates. This represents a depth of 2 from the root to the client certificate. If your organization will use CAC authentication in which you have multiple levels of intermediate certificates in the hierarchy, you will need to change this setting (ssl verify depth) as described in the procedure below.

To update the value of ssl_verify_depth:

- 1. Log in to the console of the ScienceLogic appliance as the root user.
- 2. Navigate to the directory /etc/ngnix/conf.d/:

cd /etc/ngnix/conf.d/

3. Open the file em7ngx_web_ui.conf with a text editor like vi:

vi em7ngx_web_ui.conf

4. Edit the ssl_verify_depth value to be the depth from client certificate to the root certificate (for example, 3):

ssl_verify_depth 3;

5. Save and quit (:wq) the file.

Accessing the Appliance without CAC Authentication

In certain circumstances, you might need to access your SL1 Appliance without using CAC authentication. For example, the following are some reasons you might want to use another authentication type:

- For use during initial setup
- For appliance access when a certificate has expired
- For maintenance or administrator accounts
- For certain internal networks that will not require certificate authentication

You can configure the appliance to accept a login in these cases in two ways:

- By configuring an Authentication Profile to use an alternative authentication resource (for example, EM7 Internal) for certain networks or hosts. For more information, see Authentication Profiles.
- By using the Ignore Networks field on the Client Certificate & CAC Authentication page (System
 > Settings > Authentication > CAC/ClientCert Auth). For more information, see Defining the Client
 Certificate Chain.

Chapter **15**

Authentication Profiles and Resources

Overview

This chapter describes the following topics:

- Authentication Profiles. Policies that align user accounts with one or more types of authentication.
- Authentication Resources. Configuration policies that describe how SL1 should communicate with a user store.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon (\equiv) .
- To view a page containing all the menu options, click the Advanced menu icon (…).

This chapter includes the following topics:

Authentication Profiles	294
Viewing the List of Authentication Profiles	294
Filtering the List of Authentication Profiles	295
The "default" Authentication Profile	297
Creating an Authentication Profile	298
Editing an Authentication Profile	301
Deleting One or More Authentication Profiles	301
Authentication Resources	301
Viewing the List of Authentication Resources	302
Filtering the List of Authentication Resources	303
The "EM7 Internal" Resource	304

Creating an LDAP/AD Authentication Resource	305
Creating an SSO Authentication Resource	310
Editing an Authentication Resource	315
Deleting an Authentication Resource	315

Authentication Profiles

Authentication profiles are policies that align user accounts with one or more types of authentication:

- Alignment by pattern matching. SL1 examines the URL or IP address that a user enters in a browser to connect to an Administration Portal, Database Server, or All-In-One Appliance. If the URL or IP address matches the criteria specified in an authentication profile, SL1 will automatically use the matching profile to perform user authentication.
- Credential Source. Specifies from where SL1 should extract the username and password or certificate to be authenticated. These credentials are passed to SL1 through HTTP. SL1 then passes the credentials to each authentication resource specified in the authentication profile (for example, CAC/ Client Cert). The authentication resources communicate with user stores that can authenticate the credentials entered by a user.
- Authentication Resource. Specifies the connector to use to communicate with the user store, the credential to use to connect to the user store (if applicable), such as your Active Directory server, and the URLs to examine during authentication. Authentication Resource also maps attributes from the user's account in the user store to fields in the ScienceLogic user account. For details on creating an authentication resource, see the section on Authentication Resources.

Viewing the List of Authentication Profiles

To view a list of all authentication profiles in SL1:

1. Go to the Authentication Profiles page (System > Settings > Authentication > Profiles).

	Profiles Authentication Profi				Create	Reset Guide
	Profile Name •		Hostname Pattern	Priority Order	Edited By	Last Edited
ACAC_Users	3	4 testing		0		2021-07-09 11:29:12
🤌 default		1	-	em7a	ıdmin	
					[Select Action]	✔ Go

- 2. The following information is displayed about each authentication profile:
- Profile Name. Name of the authentication profile.
- *ID*. Unique numeric ID, automatically assigned by SL1 to each authentication profile.
- Hostname Pattern. This field is used to match the URL or IP address that a user enters in a browser to connect to an Administration Portal, Database Server, or All-In-One Appliance. If the URL or IP address matches the value in this field, SL1 applies the authentication profile to the user for the current session.
- **Priority Order**. If your SL1 System includes multiple authentication profiles, SL1 evaluates the authentication profiles in priority order, ascending. This column displays the priority order value for the authentication profiles, where 0 (zero) is the highest priority.
- Edited By. The user who created or last edited the authentication profile.
- Last Edited. Date and time the authentication profile was created or last edited.
- TIP: To sort the list of authentication profiles, click on a column heading. The list will be sorted by the column value, in ascending order. To sort by descending order, click the column heading again. The Last Edited column sorts by descending order on the first click; to sort by ascending order, click the column heading again.

Filtering the List of Authentication Profiles

You can filter the list of authentication profiles on the **Authentication Profiles** page by one or more of the following parameters: **Profile Name**, **ID**, **Hostname Pattern**, **Priority Order**, **Edited By**, and **Last Edited**. The list of authentication profiles is dynamically updated as you select each filter.

For each filter, except **Last Edited**, you must enter text to match against. SL1 will search for authentication profiles that match the text, including partial matches, and will filter while you type. Text matches are not case-sensitive. You can use the following special characters in each filter except **Last Edited**:

• , (comma). Specifies an "or" operation. For example:

"dell, micro" would match all values that contain the string "dell" OR the string "micro".

• & (ampersand). Specifies an "and" operation. For example:

"dell & micro" would match all values that contain the string "dell" AND the string "micro".

• ! (exclamation mark). Specifies a "not" operation. For example:

"!dell" would match all values that do not contain the string "dell".

- ^ (caret mark). Specifies "starts with". For example:
 - "^ micro" would match all strings that start with "micro", like "microsoft".
 - "^" will include all rows that have a value in the column.
 - "! ^ " will include all rows that have no value in the column.
- \$ (dollar sign). Specifies "ends with". For example:

"\$ware" would match all strings that end with "ware", like "VMware".

- "\$" will include all rows that have a value in the column.
- "!\$" will include all rows that have no value in the column.

By default, the cursor is placed in the first Filter-While-You-Type field. You can use the <Tab> key or your mouse to move your cursor through the fields.

Only authentication profiles that meet all the following filter criteria will be displayed in the **Authentication Profiles** page:

- **Profile Name**. Name of the authentication profile. You can enter text to match, including special characters, and the **Authentication Profiles** page will display only authentication profiles that have a matching name.
- *ID*. Unique numeric ID, automatically assigned by SL1 to each authentication profile. You can enter text to match, including special characters, and the **Authentication Profiles** page will display only authentication profiles that have a matching ID.
- Hostname Pattern. This field is used to match the URL or IP address that a user enters in a browser to connect to an Administration Portal, Database Server, or All-In-One Appliance. If the URL or IP address matches the value in this field, SL1 applies the authentication profile to the user for the current session. You can enter text to match, including special characters, and the Authentication Profiles page will display only authentication profiles that have a matching hostname pattern.

- **Priority Order**. You can enter text to match, including special characters, and the **Authentication Profiles** page will display only authentication profiles that have a matching priority number.
- *Edited By*. The user who created or last edited the authentication profile. You can enter text to match, including special characters, and the **Authentication Profiles** page will display only authentication profiles that have been created or edited by a matching username.
- Last Edited. Date and time the authentication profiles was created or last edited. You can select from a list of time periods. The Authentication Profiles page will display only authentication profiles that have been created or edited within that time period.

The "default" Authentication Profile

SL1 includes a *default* authentication profile, for which the following rules apply:

- You cannot delete the *default* profile.
- If an **AP Hostname Pattern** fails to match all the other authentication profiles, SL1 applies the *default* authentication profile.
- For users running version 7.7 or earlier of SL1 who apply one or more patches to upgrade to version 7.8, the **default** profile allows ScienceLogic authentication to perform as it did prior to version 7.8.
 - On patched systems, the default profile is included in the patch.
 - On patched systems, the default profile is pre-configured to allow ScienceLogic administrators to log in via the ScienceLogic login page and the authentication resource EM7 Internal.
 - On patched systems, the default profile is pre-configured to allow credentials via CAC/Client Certificate, HTTP Auth, or the EM7 Login Page.
 - On patched systems, the default profile is pre-configured to use all legacy authentication resources: SSO (legacy), LDAP/AD (legacy), and EM7 Internal.

NOTE: Administrators can edit the default profile and use the new, non-legacy authentication resources but are not required to do so.

- For users who installed version 7.8 or later of SL1 using an ISO, initially the default profile is pre-configured to allow ScienceLogic administrators to log in via CAC/Client Certificate, HTTP Auth, or the EM7 Login Page and the authentication resource EM7 Internal. This allows administrators to log in and perform initial configuration on the SL1 system.
 - On ISO systems, the default profile is included in the patch.
 - On ISO systems, the default profile is pre-configured to allow credentials via CAC/Client Certificate, HTTP Auth, or the EM7 Login Page.
 - On ISO systems, the default profile is pre-configured to use only the authentication resource EM7 Internal.

NOTE: After initial configuration, administrators can edit the *default* profile as best fits their organization.

Creating an Authentication Profile

To create a new authentication profile:

1. Go to the Authentication Profiles page (System > Settings > Authentication > Profiles).

	files Authentication Profiles F	ound (2)				Create	Reset Gui
	Profile Name •)[Hostname Pattern	Priority Order	Edited By	Last Edited
AC_Users		4	testing		0		2021-07-09 11:29:12
🤌 default		1				em7admin	
						[Select Action]	✔ Go

2. Click the [Create] button. The Authentication Profile Editor modal page appears.

Create Authentication Profile	×
Authentication Profile Editor Creating New Authentication P	rofile Reset
Name	Priority Order
Pattern Type	AP Hostname Pattern
	▼
Available Credential Sources	Aligned Credential Sources
CAC/Client Cert EM7 Login Page HTTP Auth	» ≪
Available Authentication Resources	Aligned Authentication Resources
asdfasdf asdfasdf EM7 Internal	» «
	Save

- 3. Enter values in the following fields:
 - Name. Name of the authentication profile.
 - **Priority Order**. If your SL1 System includes multiple authentication profiles, SL1 evaluates the authentication profiles in ascending priority order. SL1 will apply the authentication profile that matches the hostname or IP in the current URL AND has the lowest value in the **Priority Order** field.
 - Pattern Type. Specifies how SL1 will evaluate the value in the AP Hostname Pattern field. Choices are:
 - Wildcard. SL1 will perform a text match, with wildcard characters (asterisks).
 - Regex. SL1 will use regular expressions to compare the **AP Hostname Pattern** to the current session information.

- AP Hostname Pattern. This field is used to match the URL or IP address that a user enters in a browser to connect to an Administration Portal, Database Server, or All-In-One Appliance. If the URL or IP address matches the value in this field, SL1 applies the authentication profile to the user for the current session.
 - For example, if you specify "*" (asterisk), any IP address or URL will match. SL1 will then apply this authentication profile to every session on an Administration Portal, Database Server, or All-In-One Appliance.
 - If you enter "192.168.38.235", SL1 will apply the authentication profile to each session on an Administration Portal, Database Server, or All-In-One Appliance where the user enters "192.168.38.235" into the browser.
 - If you enter "*.sciencelogic.local", SL1 will apply the authentication profile to each session on an Administration Portal, Database Server, or All-In-One Appliance where the user enters a URL ending with ".sciencelogic.local" into the browser.
- Available Credential Sources. This field tells SL1 how to retrieve the user's credentials from the HTTP request to SL1. To align a credential source with the authentication profile, highlight the credential source and click the right-arrow button. You can select zero, one, or multiple credential sources for the authentication profile. Initially, this pane displays a list of all the credential sources:

NOTE: If you will be using CAC authentication, align the CAC/Client Cert credential source. If this is your primary method of logging in to SL1, align CAC/Client Cert as the number one credential source. ScienceLogic recommends having EM7 Login Page aligned, as well, for administrator or maintenance access.

- CAC/Client Cert. SL1 will retrieve a certificate from the HTTP request.
- *EM7 Login Page*. SL1 will retrieve a user name and password from the ScienceLogic login page fields.
- HTTP Auth. SL1 will retrieve a user name and password from the HTTP request.

NOTE: If you are using Single Sign-On (SSO) authentication, the **Available Credential Sources** field is ignored. You do not have to align a credential source because credentials are submitted directly to an Identity Provider (IdP) instead of SL1.

- Aligned Credentials Sources. This field displays the list of credential sources that have been aligned with the authentication profile. The authentication profile will examine each credential source in the order in which it appears in this list. When the authentication profile find the user's credential, the authentication profile stops examining any remaining credential sources in the list.
- Available Authentication Resources. This field tells SL1 which authentication resources to use to authenticate the retrieved credentials. To align an authentication resource with the authentication profile, highlight the authentication resource and click the right-arrow button. You must select at least one authentication resource (but can select more than one). For details on creating an authentication resource, see the section on Authentication Resources.

- Aligned Authentication Resources. This field displays the list of authentication resources that have been aligned with the authentication profile. The authentication profile will examine each authentication resource in the order in which it appears in this list. When an authentication resource successfully authenticates the user, the authentication profile stops executing any remaining authentication resources in the list.
- 4. Click the [Save] button to save your changes to the new authentication profile.

Editing an Authentication Profile

The Authentication Profiles page allows you to edit an existing authentication profile. To do so:

- 1. Go to the Authentication Profiles page (System > Settings > Authentication > Profiles).
- 2. Find the authentication profile that you want to edit. Click its wrench icon (\mathscr{P}) .
- 3. The Authentication Profile Editor modal page appears. In this page, you can edit the value of one or more fields.
- 4. Click the [Save] button to save your changes to the authentication profile.

Deleting One or More Authentication Profiles

The Authentication Profiles page allows you to delete one or more authentication profiles from SL1. To do so:

- 1. Go to the Authentication Profiles page (System > Settings > Authentication > Profiles).
- 2. Select the checkbox of each authentication profile that you want to delete.
- 3. Click the **Select Actions** menu (in the lower right), select *DELETE Authentication Profile*, and then click the **[Go]** button. The selected authentication profiles will be deleted.

NOTE: You cannot delete the *default* authentication profile.

Authentication Resources

An authentication resource is a configuration policy that describes how SL1 should communicate with a user store. An authentication resource specifies the connector to use to communicate with the user store, the credential to use to connect to the user store (if applicable), and the URLs to examine during authentication. An authentication resource also maps attributes from the user's account in the user store to fields in the ScienceLogic user account.

Viewing the List of Authentication Resources

The Authentication Resource Manager page displays a list of all authentication resources in the SL1 System.

To view the list of authentication resources :

1. Go to the Authentication Resource Manager page (System > Settings > Authentication > Resources).

Resource Nar	ne •	ID	Туре	Connector	Edited By	Last Edited
						Al
🖗 asdfasdf			SSO	OneLogin	em7admin	2016-02-14 19:53:37
asdfasdfasdf			LDAP/AD	LDAP/AD	em7admin	2016-02-14 19:53:26
P EM7 Internal		1	em7account	EM7 Internal	em7admin	2016-01-14 19:57:22

2. The following information is displayed about each authentication resource:

TIP: To sort the list of authentication resources, click on a column heading. The list will be sorted by the column value, in ascending order. To sort by descending order, click the column heading again. The *Last Edited* column sorts by descending order on the first click; to sort by ascending order, click the column heading again

- Resource Name. Name of the authentication resource.
- ID. Unique numeric ID, automatically assigned by SL1 to each authentication resource.
- Type. Specifies the user store that is associated with the resource. Possible types are:
 - *EM7 Internal*. The authentication resource communicates and passes information to and from the ScienceLogic Database.
 - LDAP/AD. The authentication resource communicates and passes information to and from an LDAP server or Active Directory server.
 - SSO. The authentication resource communicates and passes information to and from a SAML Identity Provider (IdP) or Service Provider (SP).

- **Connector**. The software that allows communication between the authentication resource and the user store. Possible connectors are:
 - EM7 Internal. Software that communicates with the ScienceLogic Database.
 - LDAP/AD. Software that communicates with an LDAP server or Active Directory server.
 - LDAP/AD Legacy. Software that communicates with an LDAP server or Active Directory server for ScienceLogic servers that were configured prior to version 7.8 of SL1. SL1 Systems that were upgraded to version 7.8 using patches can continue to use the same authentication methods without making changes to user accounts or the LDAP server or Active Directory server.
 - OneLogin. Software that communicates with a SAML Identity Provider (IdP).
 - SimpleSAML Legacy. Software that communicates with a SAML Identity Provider (IdP) and Service Provider (SP) for ScienceLogic servers that were configured prior to version 7.8 of SL1. SL1 Systems that were upgraded to version 7.8 using patches can continue to use the same authentication methods without making changes to user accounts, the SAML configuration, or the SSO provider.
- Edited By. The user who created or last edited the authentication resource.
- Last Edited. Date the time the authentication resource was created or last edited.

Filtering the List of Authentication Resources

You can filter the list of authentication resources on the **Authentication Resource Manager** page by one or more of the following parameters: **Resource Name**, **ID**, **Type**, **Connector**, **Edited By**, and **Last Edited**. The list of authentication resources is dynamically updated as you select each filter. For each filter except **Last Edited**, you must enter text to match against. SL1 will search for authentication resources that match the text, including partial matches. Text matches are not case-sensitive. You can use the following special characters in each filter except Last Edited:

• , (comma). Specifies an "or" operation. For example:

"dell, micro" would match all values that contain the string "dell" OR the string "micro".

• & (ampersand). Specifies an "and" operation. For example:

"dell & micro" would match all values that contain the string "dell" AND the string "micro".

• ! (exclamation mark). Specifies a "not" operation. For example:

"!dell" would match all values that do not contain the string "dell".

- ^ (caret mark). Specifies "starts with". For example:
 - "^ micro" would match all strings that start with "micro", like "microsoft".
 - "^" will include all rows that have a value in the column.
 - "! ^ " will include all rows that have no value in the column.

• \$ (dollar sign). Specifies "ends with". For example:

"\$ware" would match all strings that end with "ware", like "VMware".

"\$" will include all rows that have a value in the column.

"!\$" will include all rows that have no value in the column.

By default, the cursor is placed in the first Filter-While-You-Type field. You can use the **<Tab>** key or your mouse to move your cursor through the fields.

Only authentication resources that meet all the following filter criteria will be displayed in the **Authentication Resource Manager** page:

- **Resource Name**. Name of the authentication resource. You can enter text to match, including special characters, and the **Authentication Resource Manager** page will display only authentication resources that have a matching name.
- *ID*. Unique numeric ID, automatically assigned by SL1 to each authentication resource. You can enter text to match, including special characters, and the **Authentication Resource Manager** page will display only authentication resources that have a matching ID.
- **Type**. Specifies the user store that is associated with the resource. You can enter text to match, including special characters, and the **Authentication Resource Manager** page will display only authentication resources that have a matching type.
- Connector. The specific software that allows communication between the authentication resource and the user store. You can enter text to match, including special characters, and the Authentication Resource Manager page will display only authentication resources that have a matching connector.
- Last Edited. Date and time the authentication resources was created or last edited. You can select from a list of time periods. The Authentication Resource Manager page will display only authentication resources that have been created or edited within that time period.
- *Edited By*. ScienceLogic user who created or last edited the authentication resource. You can enter text to match, including special characters, and the **Authentication Resource Manager** page will display only authentication resources that have been created or edited by a matching username.

The "EM7 Internal" Resource

The EM7 Internal resource allows you to access the user store in the ScienceLogic database.

- By default, each SL1 System, whether upgraded to version 7.8 or built from a 7.8 ISO, includes the EM7 Internal authentication resource.
- You cannot create an EM7 Internal authentication resource.
- You cannot edit or delete the EM7 Internal authentication resource included with your SL1 System.
- Each SL1 System can include only one the EM7 Internal authentication resource.

Creating an LDAP/AD Authentication Resource

h ohThe **LDAP/AD Auth Resource Editor** page allows you to define an authentication resource for use with an LDAP/AD user store. An LDAP/AD authentication resource specifies the connector (communication software) to use to communicate with the LDAP/AD user store and the credential to use to connect to the user store. An LDAP/AD authentication resource can also map attributes from the user's LDAP/AD account to fields in the ScienceLogic user account.

ScienceLogic administrators can use LDAP or Active Directory to authenticate ScienceLogic users. There are two ways to use LDAP or Active Directory authentication with SL1:

- You can configure SL1 to automatically create user accounts for existing LDAP or Active Directory users and then always use LDAP or Active Directory to authenticate those users when they log in to SL1.
- You can use LDAP or Active Directory to authenticate one or more ScienceLogic users when they log in to SL1.

To create an LDAP/AD authentication resource:

- 1. Go to the Authentication Resource Manager page (System > Settings > Authentication > Resources).
- 2. Click the [Actions] menu and then select Create LDAP/AD Resource. The LDAP/AD Auth Resource Editor modal page appears.

internication r	Resource Editor Editing LDAP/AD	Resource [2]			New	Reset
Read Credential	[SiLO-AD (]QA-Silo AD] •) [[None (disable)] •)	User Name Suffix Search Filter	(sAMAccountName=%u %Su = email prefx / EMT username %e = email address	Sync directory values to EM7 on login [[enable]] Sync EM7 values to directory on save [[disable]]	∨	
tribute Mapping				User Policy Alignment		
EM7 Field	Directory Attribute	EM7 Field	Directory Attribute	Type [Static policy alignment]	~	
First Name	givenname	Primary Email	mail	Policy [SILO]	~	
Last Name	sn	Secondary Email				
Title		Street Address	streetaddress)		
Department	department	Suite / Building)		
Phone	telephonenumber	City	1)		
Fax	facsimiletelephonenumber	State	st)		
Mobile	mobile	Postal Code	postalcode)		
Pager	pager	Country	C)		
MFA User			specifies organization ID]			

3. Enter values in the following fields:

Basic Settings

• Name. Name of the LDAP/AD authentication resource.

- **Read Credential**. Credential that allows SL1 to read data from an LDAP or Active Directory server. Select from a list of all LDAP and Active Directory credentials to which you have access. If this field has been set to a credential to which you do not have access, this field will display the value *Restricted Credential*. If you set this field to a different credential, the entry for *Restricted Credential* will be removed from the field; you will not be able to re-align the field with the *Restricted Credential*.
- Write Credential. Credential that allows SL1 to write data to an LDAP or Active Directory server. Select from a list of all LDAP and Active Directory credentials to which you have access. If this field has been set to a credential to which you do not have access, this field will display the value Restricted Credential. If you set this field to a different credential, the entry for Restricted Credential will be removed from the field; you will not be able to re-align the field with the Restricted Credential.

NOTE: Your organization membership(s) might affect the list of credentials you can see in the **Read** Credential field and the Write Credential field. For details, see the Discovery & Credentials manual.

- User Name Suffix. Optional field. Because SL1 can authenticate against multiple LDAP or Active Directory servers, there is a risk of collision among user names. In this field, you can enter a string to append to the user name to minimize the risk of collision. For example:
 - Suppose we entered @ad.local in this field.
 - Suppose the next LDAP/AD user logs in to SL1 with the user name **bishopbrennan**.
 - SL1 will log that user in as **bishopbrennan@ad.local**.

NOTE: A best practice to avoid collisions is to use email addresses as user names.

• Search Filter. Specifies where to find the user's account information in LDAP or Active Directory. You must tell SL1 where to find the LDAP or AD attribute that maps to the user's account name in SL1.

For example, an LDAP user might use his/her uid value to log in to SL1. In the ScienceLogic account, that uid value will then become the user's **Account Login Name**.

You can use the following variables in the search filter:

- %u. ScienceLogic login name.
- %e. Email address.
- An example search filter for LDAP might be:

```
(&(objectClass=person)(uid=%u))
```

This says to search in the object class called "person" for the uid that matches the ScienceLogic login name (entered when the user logs in to SL1 and then stored in the variable %u).

• An example search filter for Active Directory might be:

```
(sAMAccountName=%u)
```

This says to search for the samaccountname attribute that matches the ScienceLogic login name (entered when the user logs in to SL1 and then stored in the variable %u).

- For more information on the syntax of LDAP and AD search filters, see <u>RFC 4515</u>.
- Sync directory values to EM7 on login. If an LDAP or AD administrator makes changes to an LDAP or AD account, SL1 will automatically retrieve those updates and apply them to the user's account in SL1 (in the Account Properties page) the next time the user logs in to SL1. (For more information about user account properties, see the Organizations & Users manual.)
- Sync EM7 values to directory on save. If a ScienceLogic administrator made changes to the ScienceLogic account, SL1 will automatically write those changes to the user's account in LDAP or Active Directory.

NOTE: The Sync EM7 values to directory on save option requires a write credential.

Attribute Mapping

If you have configured SL1 to automatically create ScienceLogic accounts for LDAP or AD users, these fields specify the LDAP or AD attribute value that will be automatically inserted into each field in each user's **Account Properties** page. (For more information about user account properties, see the **Organizations** & **Users** manual.)

SL1 automatically populates as many of these fields as possible. You can edit or delete the default values provided by SL1. For example, SL1 automatically inserts the value of the LDAP/AD attribute "sn" (surname) into the *Last Name* field in each user's **Account Properties** page.

NOTE: SL1 requires that the LDAP or AD attribute name that you specify in each field uses **all lower-case characters**.

- First Name. Specifies the LDAP or AD attribute value that will be automatically inserted into the First Name field in each user's Account Properties page. By default, SL1 inserts the value of the LDAP/AD attribute "givenname" into this field.
- Last Name. Specifies the LDAP or AD attribute value that will be automatically inserted into the Last Name field in each user's Account Properties page. By default, SL1 inserts the value of the LDAP/AD attribute "sn" into this field.
- *Title*. Specifies the LDAP or AD attribute value that will be automatically inserted into the *Title* field in each user's **Account Properties** page.
- **Department**. Specifies the LDAP or AD attribute value that will be automatically inserted into the **Department** field in each user's **Account Properties** page.
- **Phone**. Specifies the LDAP or AD attribute value that will be automatically inserted into the **Phone** field in each user's **Account Properties** page. By default, SL1 inserts the value of the LDAP/AD attribute "telephonenumber" into this field.

- Fax. Specifies the LDAP or AD attribute value that will be automatically inserted into the Fax field in each user's Account Properties page.
- **Mobile**. Specifies the LDAP or AD attribute value that will be automatically inserted into the **Mobile** field in each user's **Account Properties** page. By default, SL1 inserts the value of the LDAP/AD attribute "mobile" into this field.
- **Pager**. Specifies the LDAP or AD attribute value that will be automatically inserted into the **Pager** field in each user's **Account Properties** page.
- **Primary Email**. Specifies the LDAP or AD attribute value that will be automatically inserted into the **Primary Email** field in each user's **Account Properties** page. By default, SL1 inserts the value of the LDAP/AD attribute "mail" into this field.
- Secondary Email. Specifies the LDAP or AD attribute value that will be automatically inserted into the Secondary Email field in each user's Account Properties page.
- Street Address. Specifies the LDAP or AD attribute value that will be automatically inserted into the Street Address field in each user's Account Properties page. By default, SL1 inserts the value of the LDAP/AD attribute "streetaddress" into this field.
- Suite/Building. Specifies the LDAP or AD attribute value that will be automatically inserted into the Suite/Building field in each user's Account Properties page.
- *City*. Specifies the LDAP or AD attribute value that will be automatically inserted into the *City* field in each user's *Account Properties* page. By default, SL1 inserts the value of the LDAP/AD attribute "l" into this field.
- **State**. Specifies the LDAP or AD attribute value that will be automatically inserted into the **State** field in each user's **Account Properties** page. By default, SL1 inserts the value of the LDAP/AD attribute "st" into this field.
- **Postal Code**. Specifies the LDAP or AD attribute value that will be automatically inserted into the **Postal Code** field in each user's **Account Properties** page. By default, SL1 inserts the value of the LDAP/AD attribute "postalcode" into this field.
- Country. Specifies the LDAP or AD attribute value that will be automatically inserted into the Country field in each user's Account Properties page.
- Organization. Specifies the LDAP or AD attribute value that will be used to automatically define the *Primary Organization* field in each user's **Account Permissions** page. You must also specify one of the following:
 - directory attribute specifies organization ID. If selected, the attribute in the **Organization** field specifies an organization ID.
 - directory attribute specifies organization name. If selected, the attribute in the **Organization** field specifies an organization name.
 - directory attribute specifies organization CRM ID. If selected, the attribute in the **Organization** field specifies the CRM ID of an organization.

NOTE: To use Attribute Mapping for **Organization**, your LDAP/AD schema must include an attribute that maps to ScienceLogic Organization names, Organization IDs, or Organization CRM IDs.

NOTE: When you create a new LDAP/AD user, you must align a user policy with that user. If the aligned user policy specifies an organization for the user, the value from the user policy will overwrite the value from Attribute Mapping.

User Policy Alignment

- **Type**. Specifies whether SL1 should automatically create ScienceLogic accounts for each LDAP or Active Directory user in the search base (which is specified in the credential), whether SL1 should simply use LDAP or Active Directory to authenticate one or more users, or whether SL1 will refuse to authenticate specific users. Choices are:
 - Do not authenticate new users from directory. Only those users who have an account already created in SL1 can log in to SL1. However, if one or more users' Account Permissions page specifies LDAP /Active Directory in the Authentication Method field, SL1 will authenticate those users with either LDAP or Active Directory, using the settings and credentials specified in this page.
 - Static policy alignment. If an LDAP or AD user logs in to SL1 using the LDAP or AD attribute specified in the Search Filter field, SL1 will automatically create an account for that user. SL1 will use one user policy (specified in the Policy field) to create all imported LDAP or AD user accounts. SL1 will also use the settings and credentials specified in this page when creating the account.
 - Dynamic policy alignment. If an LDAP or AD user logs in to SL1 using the LDAP or AD attribute specified in the Search Filter field, SL1 will automatically create an account for that user. SL1 will choose from among multiple user policies to create imported LDAP or AD user accounts. For example, some imported user accounts might use "user policy A"; other imported user accounts might use "user policy B". SL1 will also use the settings and credentials specified in this page when creating the account.

NOTE: If you selected Static policy alignment in the Type field, you must supply a value in the Policy field:

• **Policy**. Specifies the user policy to use to automatically create a ScienceLogic account for each LDAP or AD user. Select from a list of all user policies that specify LDAP /Active Directory in the **Authentication Method** field.

NOTE: If you selected Dynamic policy alignment in the **Type** field, you must supply values in the **Attribute**, **Value**, and **Policy** fields.

• Attribute. Specifies the LDAP or AD attribute you want to use to differentiate imported user accounts. For example, you could select the attribute "department" and then assign different user policies to import user accounts from different departments. You can also use this field to exclude LDAP or AD accounts for which you do not want to create a ScienceLogic account.

- Value. Specifies the LDAP or AD attribute value. That is, you specify one of the possible values for the attribute (specified in the Attribute field). SL1 will compare the value in this field to the retrieved value for the Attribute.
- **Policy**. Choose one of the following:
 - Do Not Authenticate. If selected, if the retrieved value of the specified **Attribute** matches the value in the **Value** field, the user is not authenticated. This setting applies to new users for whom LDAP or Active Directory would have to create a new account in SL1 and for users who already have an account in SL1.
 - the policy you want to associate with that value. Select from a list of all user policies that specify LDAP /Active Directory in the **Authentication Method** field.
 - For example, suppose you specified "department" in the Attribute field. Suppose that the "department" attribute could have two possible values: "Sales" or "NOC".
 - Suppose you created two user policies. One user policy, called "Sales User Policy", includes the appropriate ticket queues and access keys for Sales personnel. Another user policy, called "NOC User Policy", include the appropriate ticket queues and access keys for NOC personnel.
 - In one of the Value fields, you could specify "Sales". In the corresponding Policy field, you could then specify "Sales User Policy".
 - In the next Value field, you could specify "NOC". In the corresponding Policy field, you could specify "NOC User Policy.
 - After defining these two Value fields and corresponding Policy fields, user accounts from the Sales department would be imported into SL1 using the Sales User Policy. User accounts from the NOC department would be imported into SL1 using the NOC User Policy.
- To define additional **Value** and **Policy** fields, click on the green plus-sign (📌) icon.
- 4. Click the [Save] button to save your changes to the new authentication resource.

Creating an SSO Authentication Resource

The **SSO Auth Resource Editor** page allows you to define an authentication resource for use with a SAML IdP. An SSO authentication resource specifies the connector (communication software) to use to communicate with the SAML IdP and the URLs to use to send and retrieve information from the SAML IdP. An SSO authentication resource can also maps attributes from the user's SSO account to fields in the ScienceLogic user account.

ScienceLogic administrators can use SSO to authenticate ScienceLogic users. There are two ways to use SSO authentication with SL1:

- You can configure SL1 to automatically create user accounts for existing SSO users and then always use SSO to authenticate those users when they log in to SL1.
- You can use SSO to authenticate one or more ScienceLogic users when they log in to SL1.

To create an SSO authentication resource:

1. Go to the Authentication Resource Manager page (System > Settings > Authentication > Resources).

2. Click the **[Actions]** menu and then select Create SSO Resource. The **SSO Auth Resource Editor** page appears.

thentication Resou	rce Editor Creating New SSO Auth	hentication R	esource		Rese
isic Settings					
Name	User 1	Name Suffix		Sync directory values to EM7 on login	enable
IdP Entity ID	k	MP SSO URL		Signing Options	disable
dP Cert Fingerprint	k	MP SLS URL		Strict Mode	disable 🗸
IdP Certificate				Integrated Windows Auth	disable 🗸
tribute Mapping				User Policy Alignment	
EM7 Field	Directory Attribute EMI	17 Field	Directory Attribute	Type Do not import new users or s	vnc user polic V
First Name	P	Primary Email			
Last Name	Seco	ondary Email			
Title	Stre	eet Address			
Department	Sui	uite / Building			
Phone		City			
Fax		State			
Mobile		Postal Code			
Pager		Country			
MFA User		~			
Organization	director	ory attribute specifie	s organization ID		

3. Enter values in the following fields:

Basic Settings

- Name. Name of the SSO authentication resource.
- *IdP Entity ID*. Globally unique name for the identity provider or service provider, in the format of an absolute URL.
- *IdP Cert Fingerprint*. The SHA1 certificate fingerprint, provided by the identity provider or service provider.
- User Name Suffix. Optional field. Because a user can authenticate against multiple SSO servers, there is a risk of collision among user names. In this field, you can enter a string to append to the ScienceLogic user name to minimize risk of collision. For example:
 - Suppose we entered @ad.local in this field.
 - Suppose the next LDAP/AD user logs in to SL1 with the user name **bishopbrennan**.
 - SL1 will log in that user as **bishopbrennan@ad.local**.

NOTE: A best practice to avoid collisions is to use email addresses as user names.

• IdP SSO URL. The URL to which SL1 will send login requests to the IdP. This field must contain an absolute URL.

- *IdP SLS URL*. Optional field. If you want each user to be automatically logged out of the IdP when that user logs out of SL1, enter the URL to which SL1 will post the logout request to the IdP. If you leave this field blank, a user can log out of SL1 without automatically logging out of the IdP.
- Sync directory values to EM7 on login. If an SSO administrator makes changes to an SSO account, SL1 will automatically retrieve those updates and apply them to the user's account in SL1 (in the Account Properties page) the next time the user logs in to SL1. (For more information about user account properties, see the Organizations & Users manual.)

Attribute Mapping

If you have configured SL1 to automatically create ScienceLogic accounts for SSO users, these fields specify the SAML attribute value that will be automatically inserted into each field in each user's **Account Properties** page. (For more information about user account properties, see the **Organizations & Users** manual.)

SL1 automatically populates as many of these fields as possible. You can edit or delete the default values provided by SL1. For example, SL1 automatically inserts the value of the SAML attribute "sn" (surname) into the *Last Name* field in each user's **Account Properties** page.

NOTE: SL1 requires that the SAML attribute name that you specify in each field uses all lowercase characters.

- First Name. Specifies the SAML attribute value that will be automatically inserted into the First Name field in each user's Account Properties page. By default, SL1 inserts the value of the SAML attribute "givenname" into this field.
- Last Name. Specifies the SAML attribute value that will be automatically inserted into the Last Name field in each user's Account Properties page. By default, SL1 inserts the value of the SAML attribute "sn" into this field.
- *Title*. Specifies the SAML attribute value that will be automatically inserted into the *Title* field in each user's **Account Properties** page.
- **Department**. Specifies the SAML attribute value that will be automatically inserted into the **Department** field in each user's **Account Properties** page.
- **Phone**. Specifies the SAML attribute value that will be automatically inserted into the **Phone** field in each user's **Account Properties** page. By default, SL1 inserts the value of the SAML attribute "telephonenumber" into this field.
- Fax. Specifies the SAML attribute value that will be automatically inserted into the Fax field in each user's Account Properties page.
- Mobile. Specifies the SAML attribute value that will be automatically inserted into the Mobile field in
 each user's Account Properties page. By default, SL1 inserts the value of the SAML attribute "mobile"
 into this field.
- **Pager**. Specifies the SAML attribute value that will be automatically inserted into the **Pager** field in each user's **Account Properties** page.

- **Primary Email**. Specifies the SAML attribute value that will be automatically inserted into the **Primary Email** field in each user's **Account Properties** page. By default, SL1 inserts the value of the SAML attribute "mail" into this field.
- Secondary Email. Specifies the SAML attribute value that will be automatically inserted into the Secondary Email field in each user's Account Properties page.
- Street Address. Specifies the SAML attribute value that will be automatically inserted into the Street Address field in each user's Account Properties page. By default, SL1 inserts the value of the SAML attribute "streetaddress" into this field.
- Suite/Building. Specifies the SAML attribute value that will be automatically inserted into the Suite/Building field in each user's Account Properties page.
- City. Specifies the SAML attribute value that will be automatically inserted into the City field in each user's Account Properties page. By default, SL1 inserts the value of the SAML attribute "l" into this field.
- State. Specifies the SAML attribute value that will be automatically inserted into the State field in each user's Account Properties page. By default, SL1 inserts the value of the SAML attribute "st" into this field.
- **Postal Code**. Specifies the SAML attribute value that will be automatically inserted into the **Postal Code** field in each user's **Account Properties** page. By default, SL1 inserts the value of the SAML attribute "postalcode" into this field.
- Country. Specifies the SAML attribute value that will be automatically inserted into the Country field in each user's Account Properties page.
- Organization. Specifies the SAML attribute value that will be used to automatically define the *Primary Organization* field in each user's **Account Permissions** page. You must also specify one of the following:
 - directory attribute specifies organization ID. The attribute in the **Organization** field specifies an organization ID.
 - directory attribute specifies organization name. The attribute in the **Organization** field specifies an organization name.
 - directory attribute specifies organization CRM ID. The attribute in the **Organization** field specifies the CRM ID of an organization.

NOTE: To use Attribute Mapping for **Organization**, your SAML schema must include an attribute that maps to All-In-One Appliance Organization names, Organization IDs, or Organization CRM IDs.

NOTE: When you create a new SSO user, you must align a user policy with that user. If the aligned user policy specifies an organization for the user, the value from the user policy will overwrite the value from Attribute Mapping.

User Policy Alignment

- **Type**. Specifies whether SL1 should automatically create ScienceLogic accounts for each SSO user, whether SL1 should simply use SSO to authenticate one or more users, or whether SL1 will refuse to authenticate specific users. Choices are:
 - Do not authenticate new users. Only those users who have an account already created in SL1 can log in to SL1, which will authenticate those users with SSO using the settings specified in this page.
 - Static policy alignment. If an SSO user tries to access SL1, SL1 will automatically create an account for that user. SL1 will use **one user policy** (specified in the **Policy** field) to create the imported SSO user accounts for this authentication resource. SL1 will also use the settings specified in this page when creating the account.
 - Dynamic policy alignment. If an SSO users tries to access SL1, SL1 will automatically create an account for that user. SL1 will choose from among multiple user policies to create imported SSO user accounts for this authentication resource. For example, some imported user accounts might use "user policy A"; other imported user accounts might use "user policy B". SL1 will also use the settings specified in this page when creating the account.

NOTE: If you selected Static policy alignment in the Type field, you must supply a value in the Policy field.

• **Policy**. Specifies the user policy to use to automatically create a ScienceLogic account for each SSO user. Select from a list of all user policies.

NOTE: If you selected Dynamic policy alignment in the **Type** field, you must supply values in the **Attribute**, **Value**, and **Policy** fields.

- Attribute. Specifies the SAML attribute you want to use to differentiate imported user accounts. For example, you could select the attribute *department* and then assign different user policies to import user accounts from different departments. You can also use this field to exclude SSO accounts for which you **do not want to allow authentication**.
- Value. Specifies the SAML attribute value. That is, you specify one of the possible values for the attribute (specified in the **Attribute** field). SL1 will compare the value in this field to the retrieved value for the **Attribute**.
- **Policy**. Choose one of the following:
 - Do Not Authenticate. If the retrieved value of the specified **Attribute** matches the value in the **Value** field, the user is not authenticated. This setting applies to new users for whom SSO would have to create a new account in SL1 and for users who already have an account in SL1.
 - the policy you want to associate with that value. Select from a list of all user policies that specify SSO in the **Authentication Method** field.
 - For example, suppose you specified department in the **Attribute** field. Suppose that the department attribute could have two possible values: Sales or NOC.

- Suppose you created two user policies. One user policy, called Sales User Policy, includes the appropriate ticket queues and access keys for Sales personnel. Another user policy, called NOC User Policy, includes the appropriate ticket queues and access keys for NOC personnel.
- In one of the Value fields, you could specify Sales. In the corresponding Policy field, you could then specify Sales User Policy.
- You could then click on the plus-sign icon (*) and add another Value field and another Policy field.
- In the next Value field, you could specify NOC. In the corresponding Policy field, you could specify NOC User Policy.
- After defining these two Value fields and the corresponding Policy fields, user accounts from the Sales department would be imported into SL1 using the Sales User Policy.
- User accounts from the NOC department would be imported into SL1 using the NOC User *Policy*.
- To define additional Value and Policy fields, click on the green plus-sign icon (*).
- 4. Click the [Save] button to save your changes to the new authentication resource.

Editing an Authentication Resource

The Authentication Resource Manager page allows you to edit an existing authentication resource. To do so:

- 1. Go to the Authentication Resource Manager page (System > Settings > Authentication > Resources).
- 2. Find the authentication resource that you want to edit. Click its wrench icon (*P*).
 - For LDAP/AD Resources, the LDAP/AD Auth Resource Editor page appears. In this page, you can
 you can edit the values for one or more fields. For more information, see the Creating an LDAP/AD
 Authentication Resource section.
 - For SSO Resources, SSO Auth Resource Editor page appears. In this page, you can you can edit the values for one or more fields. For more information, see the Creating an SSO Authentication Resource section.
- 3. Click the [Save] button to save your changes to the authentication resource.

Deleting an Authentication Resource

The **Authentication Resource Manager** page allows you to delete one or more authentication resources from SL1. To do so:

- 1. Go to the Authentication Resource Manager page (System > Settings > Authentication > Resources).
- 2. Select the checkbox (\mathbb{Z}) of each authentication resource that you want to delete.
- 3. Click the **Select Actions** menu (in the lower right), select *DELETE Authentication Resource*, and then click the **[Go]** button. The selected authentication resources will be deleted.

NOTE: You cannot delete the EM7 Internal authentication resource.

Chapter **16**

Installing an SSL Certificate

Overview

SSL is an acronym for Secure Sockets Layer. SSL is a protocol for securely transmitting data via the internet. SSL uses a private key to encrypt data to be transferred over the Internet connection. Usually, URLs that include "HTTPS" are using SSL for security.

To implement SSL, an SSL certificate resides on the web server and is used to encrypt the data and to identify the website. The SSL certificate contains information about the certificate holder, the domain for which the certificate was issued, the name of the Certificate Authority who issued the certificate, and the root and the country in which the certificate was issued.

There are two ways to acquire an SSL certificate:

- You can purchase a certificate from a vendor (called a "certificate authority"), such as VeriSign or GeoTrust.
- You can "self-sign" your own certificate. Using available tools (both open source and proprietary), you can create and sign your own SSL certificate instead of purchasing from a certificate authority.

SL1 includes a self-signed certificate from ScienceLogic. Self-signed certificates can trigger a warning message in some browsers. For this reasons, some customers might prefer to purchase an SSL certificate from a certificate authority and install the certificate on one or more servers.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon (\equiv).
- To view a page containing all the menu options, click the Advanced menu icon (...).

This chapter includes the following topics:

Certificates for ScienceLogic Servers	18
Requesting a Commercial SSL Certificate	18

Creating Your Own Certificate	319
Installing the Certificate on an SL1 Appliance	321

Certificates for ScienceLogic Servers

Each SL1 appliance includes a self-signed certificate from ScienceLogic.

Each SL1 appliance uses the Nginx web server and OpenSSL.

If you want to use commercial SSL certificates with SL1, you must purchase certificates for the following SL1 appliances:

- For each Administration Portal, Database Server, or All-In-One Appliance you must purchase **two** certificates, one for the standard user interface and one for the Configuration Utility.
- For each Data Collector, you must purchase one certificate, for use with the Configuration Utility.
- For each Message Collector, you must purchase one certificate, for use with the Configuration Utility.

Requesting a Commercial SSL Certificate

To purchase a commercial SSL certificate, you must first create a private key and then use the private key to create a Certificate Signing Request (CSR). You must then send the CSR to a Certificate Authority (CA). Some wellknown CAs are VeriSign, GeoTrust, Thawte, GoDaddy, and Comodo. The CA will charge you a fee and send you a certificate for use with your private key.

To create a CSR, perform the following on each SL1 appliance.

- 1. Either go to the console of the SL1 appliance or use SSH to access the server. Open a shell session on the SL1 appliance. Log in as "em7admin".
- 2. First, you must generate a private key for the server. To do this, enter the following at the shell prompt:

```
sudo openssl genrsa -aes256 -out [keyname].key 4096
```

where:

• [keyname] is a name for the private key. For example, you might want to name the private key for an administration portal *adminport.key*.

NOTE: Make sure the file is **not** named **silossl.key**. This is the name of the pre-existing ScienceLogic, self-signed certificate file.

- 3. You will be prompted to enter a pass phrase for the key.
- 4. Best practice is to make a backup copy of the key file and the pass phrase and store both in a secure location.

5. You must remove the pass phrase from the key before generating a Certificate Signing Request (CSR). To do this, enter the following at the shell prompt, inserting the keyname you used where indicated:

sudo openssl rsa -in [keyname].key -out [keyname].key.insecure

6. Next, you must create a Certificate Signing Request (CSR) for the private key you created in the previous steps. To do this, enter the following at the shell prompt:

sudo openssl req -new -key [keyname].key.insecure -out [keyname].csr

where:

• [keyname] is a name for the CSR for the specific server. For example, you might want to name the private key for an administration portal adminport.key and name the CSR for that key adminport.csr.

NOTE: Make sure the keyname is **not** *silossl.key*. This is the name of the pre-existing ScienceLogic, selfsigned certificate file.

7. You will be prompted to enter the Common Name. Enter the fully qualified domain name of the server where the certificate will be used and SSL and https will be run.

For example, if the SL1 appliance is accessed at https://company.adminportal.com, you would enter "company.adminportal.com" as the Common Name.

8. You can now send the .csr file to a Certificate Authority. The Certificate Authority will provide details on how to send the .csr file. The Certificate Authority will send you a .crt file. The .crt file is the public key that matches your private key for the SL1 appliance. Some Certificate Authorities, e.g. GoDaddy, might use an intermediate certificate to sign the provided certificate. If an intermediate certificate is used, the Certificate Authority will provide a bundle of chained certificates in a second .crt file.

Creating Your Own Certificate

There are two ways to create your own SSL certificate:

- If your organization is a root Certificate Authority (for example, some departments of the US government), you can create your own private key and public key for each ScienceLogic server.
- If your security requirements allow a self-signed certificate, you can create your own private key and public key for each SL1 appliance.

Remember to create key pairs for all for each SL1 appliance in your SL1 system and also remember to create two key pairs for each Administration Portal in your SL1 system.

If your organization is a Certificate Authority, see your organization's internal documentation on creating a certificate for Nginx.

If you want to create a self-signed certificate, perform the following:

- 1. Either go to the console of the SL1 appliance or use SSH to access the server. Open a shell session on the SL1 appliance. Log in as "em7admin".
- 2. First, you must generate a private key for the server. To do this, enter the following at the shell prompt:

sudo openssl genrsa -aes256 -out [keyname].key 4096

where [keyname] is a name for the private key. For example, you might want to name the private key for an administration portal adminport.key.

NOTE: Make sure the file is **not** named **silossl.key**.. This is the name of the pre-existing ScienceLogic, self-signed certificate file.

- 3. You will be prompted to enter a pass phrase for the key. Best practice is to make a backup copy of the key file and the pass phrase and store both in a secure location.
- 5. Next, you must create a self-signed certificate based on the private key you generated in the previous steps.

To do this, enter the following at the shell prompt:

```
sudo openssl req -new -x509 -nodes -sha1 -days 365 -key [keyname].key -out
[keyname].crt
```

where:

- [keyname].key is the private key for the SL1 appliance .
- [keyname].crt is the public key (certificate) for the SL1 appliance.

For example, you might want to name the private key for an administration portal *adminport.key* and name the certificate file for that key *adminport.crt*. The resulting .crt file is the public key that matches your private key for the SL1 appliance.

NOTE: Make sure the files are **not** named **silossl.crt** and **silossl.key**. These are the names of the pre-existing ScienceLogic, self-signed certificate files.

- 6. Remove the private key pass phrase. To do this, enter the following at the shell prompt: sudo openssl rsa -in [keyname].key -out [keyname].key.insecure
- 7. Copy your private key and certificate files to /etc/nginx.
- On Collectors. Add the private key and certificate file to each Collector for the Configuration Utility. To do this, add the names of the new .key and .crt files to the following files: /etc/nginx/conf.d/em7ngx_web_ui.conf /etc/nginx/conf.d/em7ngx_em7proxy_web_ui.conf

9. On the Administration Portal, Database Server, or All-in-One Appliance. Add the private key and certificate file for the user interface. To do this, add the names of the new .key and .crt files to the following files:
(ats/csinu/csenf d/csm7asu, useb, ui csenf)

/etc/nginx/conf.d/em7ngx_web_ui.conf /etc/nginx/conf.d/em7ngx em7proxy web ui.conf

10. Restart the Web Configuration Utility and web server by entering the following command: sudo systemctl restart nginx

Installing the Certificate on an SL1 Appliance

ScienceLogic does not provide support for third party certificates. Be advised that installing a new SSL certificate can affect the operation of SSL services.

Most certificate authorities provide support and resources on installing and enabling their certificates in Nginx web servers. If you have questions, please refer to your Certificate Authority.

WARNING: The following steps will stop and restart the SL1 appliance and temporarily make the Administration Portal site unavailable. Confirm with your System Administrator that you are permitted to restart the ScienceLogic Web Service.

NOTE: These instructions assume that you are familiar with the Linux shell and the "vi" editor.

To install a commercial SSL certificate on a SL1 appliance, perform the following:

- 1. Purchase a certificate from a certificate authority.
- 2. Copy the certificate files (*.key and all *.crt files) to a server that can access the SL1 appliance via SFTP.

NOTE: Make sure the files are **not** named **silossl.crt** and **silossl.key**. These are the names of the pre-existing ScienceLogic, self-signed certificate files.

- 3. Use SFTP or SCP to copy the .crt file(s) and the .key file to the SL1 appliance in the /etc/nginx directory.
- 4. Either go to the console of the SL1 appliance or use SSH to access the server. Open a shell session on the SL1 appliance. Log in as "em7admin".

5. If an intermediate certificate has been used to sign the certificate file, execute the following commands to combine the server certificate and the bundle of chained certificates provided by the Certificate Authority, entering the server certificate name, bundle name, and combined certificate name where indicated:

```
cd /etc/nginx
cat [server certificate name].crt [bundle name].crt > [combined certificate
name].crt
```

Use the combined .crt file name when updating the nginx configuration.

- 6. For each appliance, edit the following files to configure the certificate for the Configuration Utility:
 - /etc/nginx/conf.d/em7webconfig.conf
 - /etc/nginx/conf.d/em7_sladmin.conf
 - Edit the following lines, removing references to silossl.crt and silossl.key and replacing with the names of the new .key and .crtfiles:

```
ssl_certificate /etc/nginx/[name of .crt file];
ssl certificate key /etc/nginx/[name of .key file];
```

- 7. In addition, for each Administration Portal, Database Server, and All-In-One Appliance, you must also edit the following files to configure the certificate for the user interface:
 - /etc/nginx/conf.d/em7ngx web ui.conf
 - /etc/nginx/conf.d/em7ngx_em7proxy_web_ui.conf
 - Edit the following lines, removing references to silossl.pem and silossl.key and replacing with the names of the new key files:

```
ssl_certificate /etc/nginx/[name of .crt file];
ssl certificate key /etc/nginx/[name of .key file];
```

- 8. Next, you will need to restart the webconfig and webserver. To do this, execute the following command:
 - For all appliances, enter:

sudo systemctl restart nginx

- 9. To test the SSL certificate, open a browser session and connect to the Administration Portal, Database Server, or All-In-One Appliance using https.
 - From the Administration Portal, go to System > Settings > Appliances.
 - In the **Appliance Manager** page, select the toolbox icon (^(a)) for each server. Notice that the URL for the Configuration Utility includes https.

Chapter 17

Managing Host Files

Overview

The **Host File Entry Manager** page allows you to edit and manage host files for all of the Data Collectors from a single page in the SL1 system. When you create or edit an entry in the **Host File Entry Manager** page, SL1 automatically sends an update to every Data Collector in the specified Collector Group.

The Host File Entry Manager page is helpful when:

- The SL1 system does not reside in the end-customer's domain
- The SL1 system does not have line-of-sight to an end-customer's DNS service
- A customer's DNS service cannot resolve a host name for a device that the SL1 system monitors

You can create host file entries for each device managed by the SL1 system. You can create duplicate host file entries, one for each Collection Group, to ensure that all Collection Groups can resolve all host names for monitored devices.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon (三).
- To view a page containing all the menu options, click the Advanced menu icon (…).

This chapter includes the following topics:

Viewing the List of Host Entries	324
Creating a New Host Entry	325
Editing a Host Entry	326
Using an Existing Host File Entry to Create a New Host File Entry (Save As)	328
Deleting One or More Host Entries	. 329

Viewing the List of Host Entries

To view the list of host entries, perform the following steps:

1. Go to the Host File Entry Manager page (System > Customize > Host Files).

IP Address •	Hostnames and Aliases	Description	Organization	CUG	Edited By	Last Edited
10.20.0.3	HQ-PT-Dell1720n	Dell Printer	System	CUG1	em7admin	2015-10-29 19:47
10.20.0.34	HQ-W2K3-JUMP01	windows server	System	CUG1	em7admin	2015-10-29 19:46

- 2. The Host File Entry Manager page displays the following about each host entry:
 - IP Address. The IP address to resolve with the host name.
 - Hostnames and Aliases. The host name to align with the specified IP address. You can also include a space-delimited list of aliases for the host name.
 - **Description**. Description of the host entry.
 - Organization. Organization associated with the host.
 - **CUG**. The Collector Group to which SL1 will send the host entry. The host entry will be added to the host file on each Data Collection Server in the Collector Group.
 - Edited By . User who created or last edited the host entry.
 - Last Edit. Date the host entry was created or last edited.

Creating a New Host Entry

To create a host file entry:

1. Go to the Host File Entry Manager page (System > Customize > Host Files).

IP Address •	Hostnames and Aliases	<u>D</u>	escription Organization	n <u>CUG</u>		Edited
10.20.0.3	HQ-PT-Dell1720n	Dell Printer	System	CUG1	em7admin 2015-1	10-29 19:47:1
10.20.0.34	HQ-W2K3-JUMP01	windows server	System	CUG1	em7admin 2015-1	10-29 19:46

2. Click the **[Action]** menu and choose **Create New Entry**. The **Create New Host File Entry** modal page appears.

Host File Entry Editor	×
Create New Host File Entry	Reset
IP Address	
Hostnames and Aliases	
Description	
Organization Coll [System] CUG1	ector
Save	

- 3. In the Create New Host File Entry modal page, supply values in the following fields:
 - IP Address. The IP address to resolve with the hostname.

NOTE: Server hostnames should be aligned to external IP addresses when supporting Network Address Translation (NAT) environments.

- Hostnames and Aliases. The hostname to align with the specified IP address. You can also include a space-delimited list of aliases for the host name.
- **Description**. Description of the host entry. This field is not written to the host file. This field is for administrators to use when managing host file entries.
- **Organization**. Organization associated with the host. You can select from a list of all existing organizations. This field is not written to the host file. This field is for administrators to use when managing host file entries. For example, a service provider could assign each customer its own organization and then use this field to manage host file entries for each customer.
- 4. Click the **[Save]** button to save the new host entry.

Editing a Host Entry

To edit a host entry, perform the following steps:

1. Go to the Host File Entry Manager page (System > Customize > Host Files).

0.20.0.2						
	HQ-PT-Dell1720n	Dell Printer	System	CUG1	em7admin	2015-10-29 19:47:12
10.20.0.3 10.20.0.34	HQ-W2K3-JUMP01	windows server	System	CUG1	em7admin	2015-10-29 19:46:08

2. Click the wrench icon (*P*) for the host file entry you want to edit. The **Editing Host File Entry** modal page appears, populated with values from the selected host file entry.

Host File Entry Editor		×
Editing Host File Entry	New	Reset
IP Address		
10.20.0.3		
Hostnames and Aliases		
HQ-PT-Dell1720n		
Description		
Dell Printer		
Organization	Collector	
[System] 🔽 [CUG1]		
Save Save As		

- 3. In the Editing Host File Entry modal page, you can edit one or more of the following fields:
 - *IP Address*. The IP address to resolve with the host name.
 - Hostnames and Aliases. The host name to align with the specified IP address. You can also include a space-delimited list of aliases for the host name.
 - **Description**. Description of the host entry. This field is not written to the host file. This field is for administrators to use when managing host file entries.
 - **Organization**. Organization associated with the host. You can select from a list of all existing organizations. This field is not written to the host file. This field is for administrators to use when managing host file entries. For example, a service provider could assign each customer its own organization and then use this field to manage host file entries for each customer.
- 4. Click the [Save] button to save your changes.

Using an Existing Host File Entry to Create a New Host File Entry (Save As)

To create a new host entry, using an existing host entry as the template:

1. Go to the Host File Entry Manager page (System > Customize > Host Files).

IP Address •	Hostnames and Aliases	Description	Organization	CUG Edited By Last Edited
0.20.0.3	HQ-PT-Dell1720n	Dell Printer	System CU0	G1 em7admin 2015-10-29 19;4
0.20.0.34	HQ-W2K3-JUMP01	windows server	System CUG	

2. Click the wrench icon (*P*) for the host file entry you want to edit. The **Editing Host File Entry** modal page appears, populated with values from the selected host file entry.

Host File Entry Editor		×
Editing Host File Entry	New	Reset
IP Address		
10.20.0.3		
Hostnames and Aliases		
HQ-PT-Dell1720n		
Description		
Dell Printer		
Organization	Collector	
[[System] [CUG1]		
Save Save As		

- 3. In the Editing Host File Entry modal page, you can edit one or more of the following fields:
 - IP Address. The IP address to resolve with the host name.

- Hostnames and Aliases. The host name to align with the specified IP address. You can also include a space-delimited list of aliases for the host name.
- **Description**. Description of the host entry. This field is not written to the host file. This field is for administrators to use when managing host file entries.
- **Organization**. Organization associated with the host. You can select from a list of all existing organizations. This field is not written to the host file. This field is for administrators to use when managing host file entries. For example, a service provider could assign each customer its own organization and then use this field to manage host file entries for each customer.
- 4. Click the **[Save As]** button to save your changes as a new host file entry. A pop-up message appears, asking if you want to save your edits as a new entry. Click the **[OK]** button.

Deleting One or More Host Entries

To delete one or more host entries, perform the following steps:

1. Go to the Host File Entry Manager page (System > Customize > Host Files).

IP Address •	Hostnames and Aliases	Description	Organization	CUG	Edited By	Last Edited	1
							_
P 10.20.0.3 P 10.20.0.34	HQ-PT-Dell1720n HQ-W2K3-JUMP01	Dell Printer windows server	System System		em7admin em7admin	2015-10-29 19:4	
					[Select Action]		

- 2. Select the checkbox (2) for each host file entry you want to delete.
- 3. Click the **Select Action** field in the lower right, then select DELETE Host File Entry. Click the **[Go]** button.

© 2003 - 2021, ScienceLogic, Inc.

All rights reserved.

LIMITATION OF LIABILITY AND GENERAL DISCLAIMER

ALL INFORMATION AVAILABLE IN THIS GUIDE IS PROVIDED "AS IS," WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED. SCIENCELOGIC[™] AND ITS SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT.

Although ScienceLogic[™] has attempted to provide accurate information on this Site, information on this Site may contain inadvertent technical inaccuracies or typographical errors, and ScienceLogic[™] assumes no responsibility for the accuracy of the information. Information may be changed or updated without notice. ScienceLogic[™] may also make improvements and / or changes in the products or services described in this Site at any time without notice.

Copyrights and Trademarks

ScienceLogic, the ScienceLogic logo, and EM7 are trademarks of ScienceLogic, Inc. in the United States, other countries, or both.

Below is a list of trademarks and service marks that should be credited to ScienceLogic, Inc. The ® and [™] symbols reflect the trademark registration status in the U.S. Patent and Trademark Office and may not be appropriate for materials to be distributed outside the United States.

- ScienceLogic[™]
- EM7[™] and em7[™]
- Simplify IT™
- Dynamic Application™
- Relational Infrastructure Management[™]

The absence of a product or service name, slogan or logo from this list does not constitute a waiver of ScienceLogic's trademark or other intellectual property rights concerning that name, slogan, or logo.

Please note that laws concerning use of trademarks or product names vary by country. Always consult a local attorney for additional guidance.

Other

If any provision of this agreement shall be unlawful, void, or for any reason unenforceable, then that provision shall be deemed severable from this agreement and shall not affect the validity and enforceability of any remaining provisions. This is the entire agreement between the parties relating to the matters contained herein.

In the U.S. and other jurisdictions, trademark owners have a duty to police the use of their marks. Therefore, if you become aware of any improper use of ScienceLogic Trademarks, including infringement or counterfeiting by third parties, report them to Science Logic's legal department immediately. Report as much detail as possible about the misuse, including the name of the party, contact information, and copies or photographs of the potential misuse to: legal@sciencelogic.com



800-SCI-LOGIC (1-800-724-5644)

International: +1-703-354-1010