

Monitoring VMware Systems

VMware: vSphere Base Pack PowerPack version 215, rev. 1

Table of Contents

Introduction	
What is VMware vSphere?	
What Does the VMware: vSphere Base Pack PowerPack Monitor?	
Installing the VMware: vSphere Base Pack PowerPack	
Version Requirements and Limitations	. 5
Configuration and Credentials	
Prerequisites for Monitoring VMware vCenter Servers	
Creating a Read-Only User Account for Monitoring	
Configuring a SOAP/XML Credential	.10
Testing the VMware Credential	
Testing the VMware Credential in the SL1 Classic User Interface	
Configuring a VMware Device Template	
Discovery	
Discovering a vCenter Server	
Discovering a vCenter Server in SL1	.17
Discovering a vCenter Server in the SL1 Classic User Interface	.19
Configuring the VMware Dynamic Applications	
Configuring the "VMware: Events" Dynamic Application	
Configuring the Polling Frequency for VMware Performance Dynamic Applications	.22
Configuring the "VMware: Remove Session Cookies" Dynamic Application	
Using Collector Affinity with VMware Dynamic Applications	
Configuring the "VMware: Tag Configuration" Dynamic Application	
Collecting Custom Performance Metrics	
vSphere Performance Collection	
VSAN Performance Collection	
Viewing Component Devices	
Viewing Component Devices in SL1	
Viewing Component Devices in the SL1 Classic User Interface	
Relationships with Other Types of Component Devices	
Determining Availability for Component Devices	
Dashboards	.40
Installing the VMware: vSphere Dashboards PowerPack	
VMware Host Performance Dashboard	
VMware vCenter Overview Dashboard	
VMware Device Dashboards	
VMware: Cluster	
VMware: Datastore	
VMware: Datastore Cluster	
VMware: Host	
VMware: Resource Pool	
VMware: Virtual App	
VMware: Virtual Machine	.53

Chapter

Introduction

Overview

This manual describes how to monitor VMware vCenter Servers in SL1 using the VMware: vSphere Base Pack PowerPack.

Use the following menu options to navigate the SL1 user interface:

• To view a pop-out list of menu options, click the menu icon (三).

The following sections provide an overview of VMware and the VMware: vSphere Base Pack PowerPack:

What is VMware vSphere?	4
What Does the VMware: vSphere Base Pack PowerPack Monitor?	4
Installing the VMware: vSphere Base Pack PowerPack	4
Version Requirements and Limitations	5

NOTE: ScienceLogic provides this documentation for the convenience of ScienceLogic customers. Some of the configuration information contained herein pertains to third-party vendor software that is subject to change without notice to ScienceLogic. ScienceLogic makes every attempt to maintain accurate technical information and cannot be held responsible for defects or changes in third-party vendor software. There is no written or implied guarantee that information contained herein will work for all third-party variants. See the End User License Agreement (EULA) for more information.

What is VMware vSphere?

vSphere is VMware's cloud virtualization platform that enables users to deploy and manage VMware cloud-based resources using a suite of components, including the vCenter Server centralized management application and ESX/ESXi host servers.

TIP: To familiarize yourself with VMware terminology, see the VMware Master Glossary: <u>http://www.vmware.com/pdf/master_glossary.pdf</u>.

What Does the VMware: vSphere Base Pack PowerPack Monitor?

To monitor VMware virtual infrastructure using SL1, you must install the VMware: vSphere Base Pack PowerPack. This PowerPack enables you to discover, model, and collect data about all aspects of VMware vSphere, including datacenters, clusters, virtual machines, and datastores.

The VMware: vSphere Base Pack PowerPack includes:

- Two example credentials you can use as templates to create SOAP/XML credentials to connect to the VMware devices you want to monitor
- Dynamic Applications to discover, model, and monitor performance metrics and/or collect configuration data for VMware devices.
- Device Classes for each of the VMware devices SL1 monitors
- A Device Template that enables you to easily align multiple Dynamic Applications to VMware devices
- Event Policies and corresponding alerts that are triggered when VMware devices meet certain status criteria
- Device dashboards for several of the discoverable VMware component devices

NOTE: The VMware: vSphere Dashboards PowerPack contains additional dashboards that display data collected from VMware systems. To view these dashboards, you must install the VMware: vSphere Dashboards PowerPack on your SL1 System. (For more information, see the section on VMware Dashboards.)

Installing the VMware: vSphere Base Pack PowerPack

Before completing the steps in this manual, you must import and install the latest version of the VMware: vSphere Base Pack PowerPack.

TIP: By default, installing a new version of a PowerPack overwrites all content from a previous version of that PowerPack that has already been installed on the target system. You can use the Enable Selective PowerPack Field Protection setting in the Behavior Settings page (System > Settings > Behavior) to prevent new PowerPacks from overwriting local changes for some commonly customized fields. (For more information, see the System Administration manual.)

To download and install a PowerPack:

- 1. Download the PowerPack from the <u>ScienceLogic Support Site</u>.
- 2. Go to the PowerPack Manager page (System > Manage > PowerPacks).
- 3. In the **PowerPack Manager** page, click the **[Actions]** button, then select Import PowerPack.
- 4. The Import PowerPack dialog box appears:

Import PowerPack™		×
Browse for file License:	Browse Import	

- 5. Click the [Browse] button and navigate to the PowerPack file.
- 6. When the PowerPack Installer modal appears, click the [Install] button to install the PowerPack.

NOTE: If you exit the **PowerPack Installer** modal without installing the imported PowerPack, the imported PowerPack will not appear in the **PowerPack Manager** page. However, the imported PowerPack will appear in the **Imported PowerPacks** modal. This page appears when you click the **[Actions]** menu and select *Install PowerPack*.

Version Requirements and Limitations

The following limitations and requirements apply to specific functionality in the VMware: vSphere Base Pack PowerPack:

- To collect I/O and latency metrics for datastores, you must enable Storage I/O Control. For information about Storage I/O Control, see the VMware knowledge base.
- Datastore Storage Performance Statistics are available only from vCenter systems running vSphere API 4.1.2 or later. SL1 will not collect Datastore Storage Performance Statistics if the Dynamic Applications that use Dynamic Component Mapping are used to monitor ESX or ESXi servers directly.
- Datastore Performance Statistics are unavailable for NFS datastores.
- If VMware Tools is not installed on a guest VM, SL1 cannot collect all performance statistics for that guest VM.

- Because no truly unique identifier is provided by the VMware vSphere API, it is possible that duplicate component devices could be created in SL1 when a virtual machine vMotions between separately monitored ESX/ESXi servers. (This issue does not affect vMotion events that occur within the same component tree, such as between two ESX/ESXi servers that are monitored through the same vCenter server.) Therefore, ScienceLogic recommends monitoring VMware servers through vCenter. In addition to accommodating vMotion events, monitoring through vCenter prevents performance issues on ESX/ESXi servers caused by API use.
- If you want to delete and reinstall version 203 or higher of the VMware: vSphere Base Pack PowerPack, you should first delete any existing copies of the Device Template included in the PowerPack and then create new versions of them after reinstalling the PowerPack. Doing so ensures that any copies of the Device Template included in the PowerPack will work properly after reinstallation. You should then assign the new Device Template(s) to any existing Discovery Sessions that were linked to the previous versions of the template(s).

Chapter

2

Configuration and Credentials

Overview

The following sections describe how to configure VMware vCenter resources for monitoring by SL1 using the VMware: vSphere Base Pack PowerPack:

Prerequisites for Monitoring VMware vCenter Servers	
Creating a Read-Only User Account for Monitoring	
Configuring a SOAP/XML Credential	
Testing the VMware Credential	
Testing the VMware Credential in the SL1 Classic User Interface	
Configuring a VMware Device Template	

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon (三).
- To view a page containing all the menu options, click the Advanced menu icon (***).

Prerequisites for Monitoring VMware vCenter Servers

Before performing the steps for configuring a vCenter server, you must:

- Have access to a VMware vCenter server that monitors your ESXi and ESX servers.
- Have access to the vCenter server using the vSphere web client.

If the Windows Server that hosts the vCenter server is SNMP-enabled, you must also configure your ESXi or ESX servers for communication using SNMP. To do so, you must:

 Configure SNMP community strings, traps, and polling on the ESXi or ESX server. Assign the server at least one SNMP community string. For more information, see VMware's documentation for <u>Configuring SNMP for</u> <u>ESXi 6.5</u> or <u>Configuring SNMP for ESXi 6.7</u>.

Creating a Read-Only User Account for Monitoring

Administrative users are the only default user type that have the level of access SL1 requires to collect data from the VMware vCenter web service. If you do not want to use the username and password of an administrative user in the SOAP/XML credential, you can set up a custom user role with the specific read-only access SL1 requires to the VMware vCenter web service.

To create a custom user role that grants the read-only access SL1 requires, perform the following steps:

- 1. Open your vCenter client at https://<vcenterservername>/ui
- 2. Select Menu > Administration from the drop-down.
- 3. In the menu at the left of the page, click Access Control > Roles. The **Roles** page appears:

vm vSphere Client	Menu 🗸	Q Search in all er	nvironments	C	?~
Administration - Access Control Roles	Roles				
Global Permissions	Roles provider	r:	rstlsvc6vsa	n01.eng.sciencelogic	.local ~
Licenses	+ 🗈 🧷 Administrator	×	1	DESCRIPTION Full access rights	USAGE
Client Plug-Ins vCenter Server Extens	Read-only No access				
 Deployment System Configuration 	Content library Datastore cons	administrator (sample) umer (sample)			
 Support Ubload File to Service 			16 items		

- 4. Click the plus sign (⁺) to add a new Role. The **New Role** page appears:
- 5. In the pane on the left, select **Storage views** and select the **View** checkbox. Click [Next].

Health update provider Host	All Storage views Privileges	All Selected Unselected
Host profile Network	Configure service	
Performance	View	
Permissions		
Profile-driven storage		
Resource		
Scheduled task		
Sessions		
Storage views		
Tasks		
Transfer service		
/Mware vCenter-Service		
Mware vSphere Updat		

6. In the next screen, enter a name for the role in the **Role name** field. Optionally, you can enter a description in the **Description** field.

New Role	
Role name	ScienceLogic
Description	Monitoring role for ScienceLogic
	CANCEL BACK FINISH

7. Click the **[Finish]** button.

To assign the custom role to a user account, perform the following steps:

1. In the vCenter client, select your vCenter server containing the hosts and clusters you are monitoring and click the **[Permissions]** tab.

Summ	Moni	Config	Permissi	Datacen	Н	osts & Clu
+ /	×					
User/Grou	ıp ↓				Ŧ	Role

- 2. Click the plus sign (+) to add permissions.
- 3. Enter values in the following fields:
 - User. Select your domain and add the user in the field below.
 - Role. Select the role that you just created.
 - Propagate to children. Select this checkbox.

User	vsphere.local	~
	Q em7admin	
Role	ScienceLogic	~
	Propagate to children	
		CANCEL

4. Click the **[OK]** button.

Configuring a SOAP/XML Credential

To use the Dynamic Applications in the VMware: vSphere Base Pack PowerPack, you must configure a SOAP/XML credential for the VMware web service. The VMware: vSphere Base Pack PowerPack includes the following templates for SOAP/XML credentials that you can edit for use with your vCenter server:

- VMware Server Example (for use with vCenter Server servers not requiring VSAN monitoring)
- VMware Server VSAN Example (for use with VSAN-enabled vCenter servers requiring VSAN monitoring)

To modify either of the VMware credential templates in the SL1 classic user interface, perform the following steps:

- 1. Go to the **Credential Management** page (System > Manage > Credentials).
- 2. Click the wrench icon (*P*) for the "VMware Server Example" credential. The **Credential Editor** modal page appears:

Credential Editor [18]							
Edit SOAP/XML Credential #18	New Reset						
Basic Settings Profile Name Content Encoding Method HTTP Version VMware Server Example [text/xml] V [POST] [HTTP/1.1] V URL [https://Host:Port/Path %D = Aligned Device Address %N = Aligned Device Host Name] [https://%D/sdk/vimService Image: Note that the second se	Soap Options Embedded Password [%P] Embed Value [%1] Embed Value [%2] VMWARE_USERNAME USERPWD_IN_EMBEC Embed Value [%3] Embed Value [%4]						
Proxy Settings Hostname/IP Port User	HTTP Headers + Add a header						
CURL Options CAINFO CAPATH CLOSEPOLICY CONNECTTIMEOUT COOKIEFILE COOKIELIST CRLF CUSTOMREOUEST DNSCACHETIMEOUT							
Save Save As							

- 3. Supply values in the following fields:
 - Profile Name. Enter a new name for the credential.
 - URL. In most cases, you can use the default setting. If you are a user that uses a domain account to log in to your vCenter, add <user/domain_name> to the URL.
 - Embed Value [%1]. Enter the username SL1 will use to connect to the VMware web service.
 - Embedded Password [%P]. Enter the password SL1 will use to connect to the VMware web service.
- 4. Click the [Save As] button to save your changes as a new credential.

CAUTION: Do not click the [Save] button, as it will save over the example credential, which you may need for future use.

Testing the VMware Credential

SL1 includes a Credential Test for VMware. Credential Tests define a series of steps that SL1 can execute on demand to validate whether a credential works as expected. For more information about creating and managing credential tests, see the **Discovery and Credentials** manual.

The VMware Credential Test can be used to test a SOAP/XML credential for monitoring VMware using the Dynamic Applications in the VMware: vSphere Base Pack PowerPack. The VMware Credential Test performs the following steps:

- Test Reachability. Attempts to reach the vCenter server using ICMP.
- Attempt VMware Connection. Attempts to connect to the VMware service using the account specified in the credential.

To test the VMware using the Credential Tester panel:

- 1. Go to the **Credentials** page (Manage > Credentials).
- 2. Locate the VMware credential that you created, click the Actions button (--), and then select Test.
- 3. The Credential Test Form modal page appears. Fill out the following fields on this page:
 - Select Credential Test. Select the "VMware Credential Test".
 - Collector. Select the All-In-One Appliance or Data Collector that will run the test.
 - IP or Hostname to Test. Type the IP address of the vCenter server.
- 4. Click [Run Test] button to run the credential test. The Testing Credential window appears.

The **Testing Credential** window displays a log entry for each step in the credential test. The steps performed are different for each credential test. The log entry for each step includes the following information:

- Step. The name of the step.
- **Description**. A description of the action performed during the step.
- Log Message. The result of the step for this execution of the credential test.
- **Status**. Whether the result of this step indicates the credential and/or the network environment is configured correctly (Passed) or incorrectly (Failed).
- Step Tip. Mouse over the question mark icon (?) to display the tip text. The tip text recommends what to do to change the credential and/or the network environment if the step has a status of "Failed".

Testing the VMware Credential in the SL1 Classic User Interface

SL1 includes a Credential Test for VMware. Credential Tests define a series of steps that SL1 can execute on demand to validate whether a credential works as expected.

The VMware Credential Test can be used to test a SOAP/XML credential for monitoring VMware using the Dynamic Applications in the VMware: vSphere Base Pack PowerPack. The VMware Credential Test performs the following steps:

- Test Reachability. Attempts to reach the vCenter server using ICMP.
- Attempt VMware Connection. Attempts to connect to the VMware service using the account specified in the credential.

To test the VMware credential:

- 1. Go to the **Credential Test Management** page (System > Customize > Credential Tests).
- 2. Locate the VMware Credential Test and click its lightning bolt icon (***). The Credential Tester modal page appears:

Credential Tester [BETA] ×
Test Type	[VMware Credential Test]
Credential	VMware Server Example
Hostname/IP	
Collector	KNT-Patch2-CU1-65
	Run Test

- 3. Supply values in the following fields:
 - Test Type. This field is pre-populated with the credential test you selected.
 - **Credential**. Select the credential to test. This drop-down list includes only credentials that you have access to that can be tested using the selected credential test.
 - Hostname/IP. Type the IP address for the vCenter server.
 - Collector. Select the All-In-One Appliance or Data Collector that will run the test.
- 4. Click the **[Run Test]** button. The **Test Credential** window appears, displaying a log entry for each step in the credential test. The steps performed are different for each credential test. The log entry for each step includes the following information:
 - Step. The name of the step.
 - Description. A description of the action performed during the step.
 - Log Message. The result of the step for this credential test.
 - **Status**. Whether the result of this step indicates the credential or the network environment is configured correctly (Passed) or incorrectly (Failed).
 - **Step Tip**. Hover over the question mark icon (^{CC}) with your mouse to display the tip text. The tip text recommends what to do to change the credential or the network environment if the step has a status of "Failed".

Configuring a VMware Device Template

A *device template* allows you to save a device configuration and apply it to multiple devices. The VMware: vSphere Base Pack PowerPack includes the "VMware vSphere Template." If you configure and apply this device template when you discover your vCenter server, SL1 aligns the appropriate Dynamic Applications to the discovered vCenter server device.

To configure the VMware device template:

- 1. Go to the **Configuration Templates** page (Devices > Templates or Registry > Devices > Templates in the SL1 classic user interface).
- 2. Locate the "VMware vSphere Template" and click its wrench icon (***). The **Device Template Editor** page appears.
- 3. Click the [Dyn Apps] tab. The Editing Dynamic Application Subtemplates page appears.
- 4. Complete the following fields:

Device Template Editor Click [Save] to	commit changes Editir	ng Dynamic Application Su	ibtemplates (Cl	ick field labels to enable/	disable them)		New	Reset
	Template Name VMware	vSphere Template						
Config Interface	CV Policies	Port Policies S	vc Policies	Proc Policies	Dyn Apps	Logs		
Subtemplate Selection 1. App: VMware: Inventory Cache 2. App: VMware: ComponentCount C 3. App: VMware: ComponentCount C 4. App: VMware: RootFolder Datacer 6. App: VMware: RootFolder Datacer 6. App: VMware: RootFolder Datacer 6. App: VMware: Inventory Cache M 6. App: VMware: Inventory Count Pe 1. App: VMware: RootFolder Folder L 6. App: VMware: RootFolder Folder C 6. App: VMware: RootFolder Folder Folder C 6. App: VMware: RootFolder Solder S 6. App: VMware: RootFolder Folder C 6. App: VMware: RootFolder S 6. App: VMware: R 6. App: R 6. App	VMware: Inventory C	applications and update co Settings cache cache vSphere Update Version Build Login Information Login Information Server API Version Server Type Service Information Username	edentials Uynamic Enabled Enabled Enabled Enabled Enabled Enabled Enabled	gn Dynamic Application Dynamic Application Application Presentation	▼) Ever	y 1 Minute	oll Rate	• • • • • • • • • • • • • • • • • • •

- Template Name. Type a new name for the device template.
- Credentials. Select the SOAP/XML credential that you created for VMware.

- 5. Click the next Dynamic Application listed in the **Subtemplate Selection** section on the left side of the page and then select the VMware SOAP/XML credential in the **Credentials** field.
- 6. Repeat step 5 until the you have selected the VMware SOAP/XML credential in the **Credentials** field for all of the Dynamic Applications listed in the **Subtemplate Selection** section.
- 7. Click [Save As].

CAUTION: Do not click the **[Save]** button, as it will save over the "VMware vSphere Template", which you may need for future use.

Chapter



Discovery

Overview

The following sections describe how to discover a vCenter server and component devices for monitoring by SL1 using the VMware: vSphere Base Pack PowerPack.

Discovering a vCenter Server	
Discovering a vCenter Server in SL1	17
Discovering a vCenter Server in the SL1 Classic User Interface	19
Configuring the VMware Dynamic Applications	21
Configuring the "VMware: Events" Dynamic Application	
Configuring the Polling Frequency for VMware Performance Dynamic Applications	
Configuring the "VMware: Remove Session Cookies" Dynamic Application	
Using Collector Affinity with VMware Dynamic Applications	25
Configuring the "VMware: Tag Configuration" Dynamic Application	
Collecting Custom Performance Metrics	
vSphere Performance Collection	
VSAN Performance Collection	
Viewing Component Devices	
Viewing Component Devices in SL1	
Viewing Component Devices in the SL1 Classic User Interface	
Relationships with Other Types of Component Devices	
Determining Availability for Component Devices	

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon (三).

Discovering a vCenter Server

To modify either of the templates, perform the following steps according to your SL1 user interface:

- Discovering a vCenter Server in SL1
- Discovering a vCenter Server in the SL1 Classic User Interface

Discovering a vCenter Server in SL1

To create and run a discovery session that will discover a vCenter server, perform the following steps:

On the Devices page (I) or the Discovery Sessions page (Devices > Discovery Sessions), click the [Add Devices] button. The Select page appears:

Select the type of devices you want to monitor	×
	<section-header><section-header><section-header><text><list-item><list-item><list-item></list-item></list-item></list-item></text></section-header></section-header></section-header>
	Select

- 2. Click the **[Unguided Network Discovery]** button. Additional information about the requirements for discovery appears in the **General Information** pane to the right.
- 3. Click [Select]. The Add Devices page appears:
- 4. Complete the following fields:
 - **Name**. Type a unique name for this discovery session. This name is displayed in the list of discovery sessions on the **[Discovery Sessions]** tab.
 - **Description**. Optional. Type a short description of the discovery session. You can use the text in this description to search for the discovery session on the **[Discovery Sessions]** tab.
 - Select the organization to add discovered devices to. Select the name of the organization to which you want to add the discovered devices.
- 5. Click [Next]. The Credentials page of the Add Devices wizard appears:

	pose credentials that connect yo		✓ Create New Test Credential	
Q Typ	pe to search credentials		=	¢
•	NAME	TYPE	LASTEDIT	
	Azure Credential - Proxy	SOAP/XML	Tue Apr 23 2019 15:50:16 GMT+0000 (UTC)	^
	Azure Credential - SOAP/XML	SOAP/XML	Tue Apr 23 2019 15:50:16 GMT+0000 (UTC)	
	Cisco CE Series Configuration	SOAP/XML	Tue Apr 23 2019 15:50:29 GMT+0000 (UTC)	ł
	Cisco CE Series History	SOAP/XML	Tue Apr 23 2019 15:50:29 GMT+0000 (UTC)	
	Cisco CE Series Status	SOAP/XML	Tue Apr 23 2019 15:50:29 GMT+0000 (UTC)	
	Cisco CUCM Example	Basic/Snlppet	Tue Apr 23 2019 15:49:26 GMT+0000 (UTC)	1
	Cisco Meeting Server Example	Basic/Snippet	Tue Apr 23 2019 15:49:41 GMT+0000 (UTC)	
	Cisco SNMPv2 - Example	SNMP	Tue Apr 23 2019 15:50:10 GMT+0000 (UTC) ***	
	Cisco SNMPv3 - Example	SNMP	Tue Apr 23 2019 15:50:10 GMT+0000 (UTC)	
	Cisco VOS CUC Cluster Status	Basic/Snippet	Tue Apr 23 2019 15:49:07 GMT+0000 (UTC)	
	Cisco VOS IM&P Cluster Status	Basic/Snippet	Tue Apr 23 2019 15:49:07 GMT+0000 (UTC)	~

6. On the **Credentials** page, locate and select the **SOAP/XML credential** you created. If the Windows server that hosts the vCenter server is SNMP-enabled, then additionally select an SNMP credential for the vCenter server.

NOTE: For integration between SL1 and ServiceNow, it is recommended that you discover your VMware environment using SNMP, so that the root device is classified as a vCenter device rather than as a Ping device. If you discover as non-SNMP, you will need to manually reclassify the root device as a vCenter device class.

7. Click [Next]. The Discovery Session Details page of the Add Devices wizard appears:

Step 1 Basic Information		Step 2 Credential Selection	3	Step 3 Discovery Session Details	×
	En	ter basic discovery session details			
	List of IPs/Hostnames		File Upload		
	1 10.0.0.55				
	Which collector will discover these devices? CUG em7aio17: 10.64.68.17		~	l≩	
	Run after save				
	Advanced Options 🗸				
l					
< Back				Save And	Run

- 8. Complete the following fields:
 - List of IPs/Hostnames. Type the IP address for the vCenter server.
 - Which collector will monitor these devices?. Select an existing collector to monitor the discovered devices. Required.
 - Run after save. Select this option to run this discovery session as soon as you click [Save and Close].

In the Advanced options section, click the down arrow icon (\sim) to complete the following fields:


- **Discover Non-SNMP**. If the Windows server that hosts the vCenter server is not SNMP-enabled, then you must enable this setting.
- Apply Device Template. Select the device template that you created for VMware.
- 9. Click **[Save and Close]** to save the discovery session. The **Discovery Sessions** page (Devices > Discovery Sessions) displays the new discovery session.
- 10. If you selected the **Run after save** option on this page, the discovery session runs, and the **Discovery Logs** page displays any relevant log messages. If the discovery session locates and adds any devices, the **Discovery Logs** page includes a link to the **Device Investigator** page for the discovered device.

Discovering a vCenter Server in the SL1 Classic User Interface

To create and run a discovery session that will discover a vCenter server, perform the following steps:

1. Go to the **Discovery Control Panel** page (System > Manage > Classic Discovery).

2. Click the [Create] button to create a new discovery session. The Discovery Session Editor modal page appears:



- 3. Enter values in the following fields:
 - IP Address Discovery List. Type the IP address for the vCenter server.
 - SNMP Credentials. If the Windows server that hosts the vCenter server is SNMP-enabled, then select
 the SNMP credential for the vCenter server in this field. If you do not select an SNMP credential in this
 field, then you must select the Discover Non-SNMP checkbox.

NOTE: For integration between SL1 and ServiceNow, it is recommended that you discover your VMware environment using SNMP, so that the root device is classified as a vCenter device rather than as a Ping device. If you discover as non-SNMP, you will need to manually reclassify the root device as a vCenter device class.

- Other Credentials. Select the SOAP/XML credential that you created for VMware.
- **Discover Non-SNMP**. If the Windows server that hosts the vCenter server is not SNMP-enabled, then you must select this checkbox.
- Apply Device Template. Select the device template that you created for VMware.

- 4. Optionally, you can enter values in the other fields on this page. For more information about the other fields on this page, see the **Discovery & Credentials** manual.
- 5. Click the [Save] button and then close the Discovery Session Editor modal page.
- 6. The discovery session you created will appear at the top of the **Discovery Control Panel** page. Click its lightning-bolt icon (*F*) to run the discovery session.
- 7. The **Discovery Session** window appears. When the vCenter server is discovered, click its device icon (**W**) to view the **Device Properties** page for the vCenter server.

Configuring the VMware Dynamic Applications

The following sections describe how to configure some of the Dynamic Applications in the VMware: vSphere Base PackPowerPack .

Configuring the "VMware: Events" Dynamic Application

The "VMware: Events" Dynamic Application is designed to collect events from VMware devices using the VMware API and insert those events into the device log of the aligned vCenter server.

For SL1 to insert VMware events into the device log, the Data Collector that monitors the vCenter server must be configured to process API events. For instructions on how to configure a Data Collector to process API events, see the *Global Settings* chapter in the *System Administration* manual.

You can specify which types of events the "VMware: Events" Dynamic Application collects by editing the event dictionary Python script located in the "VMware Event Collection" snippet of the "VMware: Events" Dynamic Application. This event dictionary includes a series of rows that look like this:

"ClusterStatusChangedEvent": {"count": 0, "countAll": 0, "collect": True},

Each row begins with an event type. This event type value must match the "eventTypeId" value the VMware API uses in its "EventFilterSpec" data object to indicate which events should be collected. For more information, see VMware's documentation on the "EventFilterSpec" data object.

To specify which events the "VMware: Events" Dynamic Application collects:

- 1. Go to the Dynamic Applications Manager page (System > Manage > Applications).
- 2. Click the wrench icon (*Properties Editor*) for the "VMware: Events" Dynamic Application. The **Dynamic Applications Properties Editor** page appears.
- 3. Click the [Snippets] tab. The Dynamic Applications Snippet Editor & Registry page appears.
- 4. Click the wrench icon (🎤) for the "VMware Event Collection" snippet.

5. Locate the section that looks like this:

```
event_dict = {
   "AlarmStatusChangedEvent": {"count": 0, "countAll": 0, "collect": True},
   "ClusterStatusChangedEvent": {"count": 0, "countAll": 0, "collect": True},
   "HostStatusChangedEvent": {"count": 0, "countAll": 0, "collect": True},
   "UserLoginSessionEvent": {"count": 0, "countAll": 0, "collect": True},
   "UserLogoutSessionEvent": {"count": 0, "countAll": 0, "collect": True},
   "VmEvent": {"count": 0, "countAll": 0, "collect": True},
   "VmMigratedEvent": {"count": 0, "countAll": 0, "collect": True},
   "other": {"count": 0, "countAll": 0, "collect": True},
}
```

- 6. Following the format shown above, add new rows for any additional event types you want to include in the event dictionary or delete the rows of any event types you want to remove from the event dictionary.
- 7. For each event type listed in the event dictionary:
 - If you want the Dynamic Application to collect that event type, change the "collect" value to "True". For example:

"AlarmStatusChangedEvent": { "count": 0, "countAll": 0, "collect": True },

• If you do not want the Dynamic Application to collect that event type, change the "collect" value to "False". For example:

```
"UserLoginSessionEvent": {"count": 0, "countAll": 0, "collect": False},
```

• If you want the Dynamic Application to collect all event types, locate the "other" line and change the "collect" value to "True". For example:

"other": {"count": 0, "countAll": 0, "collect": True},

NOTE: Changing the "other" "collect" value to "True" overrides any event types with a "collect" value of "False". If you do not want to collect all event types, then you must either remove the "other" row or change its "collect" value to "False".

8. Click the **[Save]** button.

TIP: If you have edited the "VMware Event Collection" snippet and want to maintain your event_dict settings the next time the PowerPack is upgraded, you must copy the event dictionary Python script, install the new version of the PowerPack, and then follow the steps in this section to paste the settings into the "VMware Event Collection" snippet in the upgraded version of the "VMware: Events" Dynamic Application.

Configuring the Polling Frequency for VMware Performance Dynamic Applications

In the VMware: vSphere Base Pack PowerPack, some of the Dynamic Applications require that their **Poll** *Frequency* be set to a specific time to ensure the accuracy of the data they collect.

To set the polling frequency:

- 1. Go to the **Dynamic Applications Manager** page (System > Manage > Applications).
- Search for the Dynamic Application whose polling frequency you want to update and click on its wrench icon (
- 3. In the **Dynamic Applications Properties Editor**, use the drop-down in the **Poll Frequency** field to select the polling frequency.

Close	Properties	<u>c</u>	ollections		Preser	ntati <u>o</u> n:	s	<u>S</u> nippets		Th	resholds			Aler	ts		Subs	cribe	rs			
Dynamic Applications [1	72] Propertie	s Editor																	Guide		Rese	đ
Ap VMware: VirtualMa	plication Name achine CPU Pe	rforman	ce 😯		Ve [Versior	ersion N n 2.0]	lumber ▼	0	[Af	ter 4 Ti	Abano med-Out		ollecti tion C		s] v	• •			Disable	Rollup	of Data	a
Ap	plication Type formance]		▼ 🚱		[Enable	ed]	al State	0				Conte	ext			0			Compo	onent M	apping	
Execu [Default: VMwa	ition Environme ire: vSphere Ba		▼ 😯		[Defau P	oll Freq	▼ uency	0	[values		Row	Optior	1	٧	. 5						
	Device Dashboard [[VMware: Virtual Machine] v]					5 Minute 1 Minute 2 Minute 3 Minute 5 Minute	es es es]		[values		olum	n Opti	on	Ţ	2				Save Save As		
Description This dynamic applicati	escription This dynamic application collects performance data ass					10 Minu 15 Minu 30 Minu 1 Hour 2 Hours 3 Hours 12 Hour 24 Hour	tes tes	s group fo	or the '	Virtua	1Machine	e pro	vider.									
Release Notes & Change	Log							-														
🖹 - 🎽 B I	<u>U</u> S	A٠	TI- d	- (¶ -	% -	≣ -		12 3	i≡	⊞ -	-	Q		/	>						
Version 2.0: 1. Converted to I 2. Added suppor Version 1.0: 1. This dynamic provider. All n cache. 2. The following be configured	t for ESXI h application netrics used LEVEL 1 m	collect d by th etrics	is perform is applica are collec	tion ted:	are pro	ovided ady.su	by a se	parate p	roces	s wh	ich stor	es m	etric	data	a in ti	he pe	rform	ance	e metr	ics	st	•
Copyright (c) 2003	3-2016 Scie	nceLo	gic, Inc.																			-

- 4. Set the polling frequencies for the following Dynamic Applications using the guidelines listed:
 - VMware: VirtualMachine CPU Performance. No more than 5 minutes.
 - VMware: VirtualMachine Datastore Performance. No more than 5 minutes.
 - VMware: VirtualMachine Disk Performance. No more than 5 minutes.
 - VMware: QuickStats Cache. No less than 5 minutes.
 - VMware: Inventory Cache. Exactly 1 minute.
 - VMware: Datastore Space Performance. No less than 15 minutes.

Configuring the "VMware: Remove Session Cookies" Dynamic Application

The "VMware: Remove Session Cookies" Dynamic Application allows users to force a new API session to collect new objects.

To execute the Dynamic Application:

- 1. Go to the **Dynamic Applications Manager** page (System > Manage > Applications).
- 2. Find the "VMware: Remove Session Cookies" Dynamic Application and click on its wrench icon (🥍).
- 3. In the **Dynamic Applications Properties Editor** page, click the **Operational State** drop-down and select *Enabled*.

		<u>P</u> roper	ties	<u> </u>	ollectio	ns	<u>S</u> n	ippets		<u>T</u> hresh	olds		<u>A</u> lerts			Subso	ribers					
Dynamic App	plications	[1442] P	roperti	es Edito	яr															Guide		Reset
VMwa	are: Remov		n Cookie	s			\ [Versio	/ersion N on 1.0]) 😧	נס	efault]	Aba	ndon C		ction		• 😧		Disable	e Rollup	of Data
[Snip	opet Config				▼ 😧		O	peration led1						Cont				2		Comp	onent N	
[No	caching]	Cachi			▼ 😯		Enabl [Disab	ed			[-	- value:	3]	II Row				• 😮			Save	
None		Device Dat	shboard		• ?			24 Hou		0	[-	- value:		Colum	ın O	otion	•				Save A	5
																						li
Release Note	es & Chan																					
		ige Log																				
<u>∎</u> • 2	В		S	A٠	T!-	ð -	¶ -	% -	≣·	ē		i≡	•	-	Q			>				
Version		ΙU										i		-	Q							
Version	1.0: al versio	I <u>U</u> n of the	VMwa	are: Re	emove	Sessi						I	Ⅲ •	-	Q							_
Version 1. Initia Copyrigh This soft	1.0 : al versio ht (c) 20 tware is	I U n of the 03-2018 the cop	VMwa 3 Sciel yrighte	are: Re nceLo ed wor	emove gic, Inc	Sessi	ion Coc	okies D Inc.	ynamic	: Applic		i=	⊞ •	-	Q]					_
Version 1. Initia Copyrigh This soft Use of th agreement	1.0: al versio ht (c) 20 tware is he Softw ent, whice	I U n of the 03-2018 the cop vare is g ch accor	VMwa 3 Scier yrighte overn mpanie	are: Re nceLo ed wor ed by es or i	emove gic, Inc rk of So the ter s inclue	Sessi cience ms of ded w	Logic, the sof	okies D Inc. tware I Softwa	iynamic license re	: Applic	cation.	12	Ⅲ •	-	Q							_
Version 1. Initia Copyrigh This soft Use of th agreeme ("License	1.0: al versio ht (c) 20 tware is he Softw ent, whic e Agree	I U n of the 03-2018 the cop vare is g ch accor ment").	VMwa 3 Sciel yrighte overn mpanie An en	are: Re nceLo ed wor ed by es or i d user	emove gic, Ind tk of So the ter s inclue	Sessi cience ms of ded w permi	Logic, the sof	okies D Inc. tware I Softwa install	iynamic license re any So	: Applic	cation.	i=	⊞ •	-	GO							
Version 1. Initia Copyrigh This soft Use of th agreement	1.0: al versio ht (c) 20 tware is he Softw ent, whice e Agree ccompares to th	I U n of the 03-2018 the cop vare is g ch accor ment"). nied by e Licen:	VMwa 3 Scier yrighte jovern mpanie An en or incl se Agr	are: Re nceLo ed wor ed by es or i d user ludes a reeme	emove gic, Inc the ter s inclue is not a Licen nt term	Sessi cience ms of ded w permi ise Ag	Logic, the sof ith the s itted to preeme	okies D Inc. tware I Softwa install nt, unle	license re any So ess he o	tware	cation.	I	Ⅲ -	-	Q			<>				

- 4. Align the "VMware: Remove Session Cookies" Dynamic Application to any VMware root device.
- On the root device, go to the [Collections] tab on the Device Properties page and run the "VMware: Remove Session Cookies" Dynamic Application you just aligned by clicking the lightning bolt icon (\$\vec{F}\$).
- 6. After running the Dynamic Application, check the session logs. If you get an "Failed to retrieve security token from vSphere SSO server" error, run the Dynamic Application again.
- 7. When the "VMware: Remove Session Cookies" Dynamic Application has successfully run, change its **Operational State** back to Disabled.

Using Collector Affinity with VMware Dynamic Applications

Collector Affinity specifies the Data Collectors that are allowed to run collection for Dynamic Applications aligned to component devices.

NOTE: The Collector Affinity feature is available only in SL1 versions 8.9.0 and greater, and applies only to distributed SL1 systems, not All-In-One Appliances.

By default, the Dynamic Applications in the VMware: vSphere Base Pack PowerPack are configured so that the Data Collector assigned to the root device will collect data for any Dynamic Applications in the PowerPack that are auto-aligned to component devices during discovery. This guarantees that data for all of the Dynamic Applications aligned to all of your VMware components will be collected by a single Data Collector.

When monitoring a VMware environment with a large number of component devices, however, running all of the Dynamic Applications on the root device's Data Collector could potentially overload the Data Collector, either because the Dynamic Applications take too long to complete or because they consume too much CPU or memory. When this occurs, some data might not be collected. This can lead to missed alerts and events, as well as gaps in graphs and reports.

To better support such large VMware environments, you can distribute the load of the VMware Bulk Performance Dynamic Applications across the Data Collectors in a collector group by changing the **Collector Affinity** setting for those Dynamic Applications to Assigned Collector. When the VMware Bulk Performance Dynamic Applications are configured this way, SL1 monitors the load on each Data Collector in the collector group and tries to evenly distribute the VMware Bulk Performance Dynamic Applications across the Data Collectors, thereby reducing total collection latency. It also has the benefit of distributing the PowerPack's CPU load and memory utilization.

CAUTION: The following VMware Bulk Performance Dynamic Applications are exceptions, and their **Collector Affinity** values *must* be changed to Root Device Collector:

- VMware: HostSystem Datastore Performance
- VMware: ResourcePool Performance
- VMware: VirtualMachine DataStore Performance

CAUTION: The Collector Affinity value should be changed to Assigned Collector only for VMware Bulk Performance Dynamic Applications (with the exception of the ones listed in the previous note). The VMware Configuration Dynamic Applications *must* run on the VMware root device's Data Collector. As such, their Collector Affinity values should remain set Default. **NOTE**: The VMware: vSphere Base PackPowerPack currently requires that all VMware devices be discovered in a single collector group, regardless of whether that group consists of a single collector or multiple collectors. All **Collector Affinity** values in the PowerPack are delivered set to *Default*, overwriting any prior settings.

NOTE: All Bulk Performance Dynamic Applications, except 'VMware: ResourcePool Performance', were updated in version 212 of the PowerPack to allow data to be cached on a local collector so virtual machines can be assigned to any collector.

For more information about configuring Collector Affinity settings for Dynamic Applications, see the "Collector Affinity" topic in the Dynamic Component Mapping chapter of the **Dynamic Application Development** manual.

Configuring the "VMware: Tag Configuration" Dynamic Application

By default the "VMware: Tag Configuration" Dynamic Application is disabled. Once enabled, you can use the data collected by this Dynamic Application to populate custom attributes for device groups. To do this, you need to define some of the fields as Custom Attributes.

To do this:

- 1. Go to the **Dynamic Applications Manager** page (System > Manage > Applications).
- 2. Find the "VMware: Tag Configuration" Dynamic Application and click its wrench icon (🥍).
- 3. Click the **[Collections]** tab. In the **Collection Objects** page, click the wrench icon (***) for the **Category** object.
- 4. In the **Custom Attribute** field, select Dynamic Name. Click the **[Save]** button.
- 5. Click the wrench icon for **Assigned Tag**. In the **Custom Attribute** field, select Dynamic Value, and then select Category in the second dropdown menu.
- 6. Click the **[Save]** button.

Close	Properties	<u>C</u> ollecti	ons <u>S</u>	nippets	<u>T</u> hresholds	<u>A</u> lerts		Subscrib	ers				
Dynamic Applications	[204] Collection Object	ts										Guide F	Reset
Object Name	Category								Desc	ription			
Snippet Arguments	tag_category					The category o	f the (collectio	n of t	ags.			
Class Type	[10 Config Character]			///									
String Type		~			·								
Custom Attribute	[Dynamic Name]	~											
Snippet	VMware Tag Configu	iration J		*									
Group / Usage Type	[Group 1]	~	[Standard]	~					For	mula			
Asset / Form Link	[None]	~	[None]	•									
Inventory Link	[Disabled]	~											
Change Alerting	[Disabled]		1	~									
-	_	~										2	
Hide Object												45	
					Save Sav	ve As				Dis	able O	oject Maintenance	
Collection Object Re	egistry												
	Object Name			Clas Type		Snippet Arguments	Group	ID	Asset Link	Change Alerting	Align	Edit Date	
1. Assigned Tag				Config Charac		tag_name	1	o_1992		Disabled	Left	2020-08-06 18:44:5	50
2. Category				Config Chara		tag_category	1	o_1994		Disabled		2020-08-10 18:49:	
3. PDescription				Config Charac		tag_description	1	o_1993		Disabled		2020-08-06 18:44:5	
4. Andex 5. Antags				Config Charac Label (Config		tag_index	1	o_1991		Disabled		2020-08-06 18:44:5 2020-08-06 18:44:5	
5. Ariags				Laber (Coning	Group) 106			o_1995		Disabled	Leit	2020-00-00 10.44.0	
						[Sel	ect Actio	onl				~	Go
L						[36]	OUT MULL	ang .				•	
opyright © 2003 - 2020	ScienceLogic, Inc. All r	ights reser	ved.										

For more information about Custom Attributes, see the **Device Management** manual.

Collecting Custom Performance Metrics

vSphere Performance Collection

The VMware: vSphere Base Pack PowerPack enables you to collect custom performance metrics.

To add a new vSphere performance metric:

- In the Dynamic Applications Manager page (System > Manage > Applications), find the Bulk Snippet Performance Dynamic Application aligned to the particular device type of interest(i.e., Virtual Machine or Datastore). Click on the wrench icon () next to the Dynamic Application to open the Dynamic Applications Properties Editor page.
- 2. In the **[Collections]** tab, clone an existing collection object by selecting the wrench icon (
- 3. Add a new object name and metric label using the Snippet Arguments field.

The metric label format is: <metric_group>.<metric_name>.<rollupType>.

4. Click [Save As] to save the collection object as a new object without saving over the object that you cloned.

Details about the precise metric name, group, and rollup type can be found in <u>the vSphere documentation for</u> <u>PerformanceManager</u>. The vCenter managed object browser (MOB) at https://<vCenter IP>/mob/?moid=PerfMgr is an alternative source for counter labels if you know the counter ID. If it is decided that a new snippet must be added to the performance Dynamic Application, the following snippet code can be used as the basis for the new snippet:

```
from content import content_errors
from content import content_logger
from silo_vmware.VMwareBulkPerfMetrics import VMwareBulkPerfMetrics
CONTROL_PARAMS = {
    # 'maxThreads': 8, # maximum number of threads per execution
    # 'maxQueryMetrics': 64, # maximum number of metrics to include in QueryPerf,
    default is 64 or comes from API if set
    # 'intervalId': 300 # Default vCenter performance statistical interval
    with content_errors.ErrorManager(self):
    with content_logger.LogManager(self) as logger:
    app_name = "VMwareClusterComputeResourcePerformanceSnippet"
    inst = VMwareBulkPerfMetrics(self, app_name, snippet_id, devices, self.oids,
    entity_type='ComputeResource', ctrl_params=CONTROL_PARAMS)
    inst.process()
```

VSAN Performance Collection

The process for VSAN performance collection is similar to the process for vSphere performance collection, but the snippet argument uses a URL-style pattern to designate the metric to be collected. Refer to the <u>VSAN Management</u> API documentation for more information.

For example, for VSAN cluster front-end stats, the collection object snippet arguments use a pattern similar to this, where the entity type and metric can be exchanged with the new metric of interest:

```
vsan://vsan-performance-manager/VsanPerfQueryPerf?entityType=cluster-
domclient&entityUuid=*&metricLabel=congestion
```

Details on the precise parameters that can be provided to the query can be found in the <u>vSphere documentation</u> for VsanPerfQueryPerf.

If a new snippet is required, the following snippet code can be used as the basis for the new snippet:

```
from content import content_errors
from content import content_logger
from silo_vmware_vsan.vsan_perf_app_collector import VsanPerfAppCollector
TAG = "VsanStoragePerfStats"
with content_errors.ErrorManager(self):
    with content_logger.LogManager(self) as logger:
        vsan_app = VsanPerfAppCollector(self, TAG, snippet_id)
        vsan_app.get_collections()
        vsan_app.collect()
        vsan_app.store()
```

Viewing Component Devices

When SL1 performs collection for the "VMware: RootFolder Datacenter Discovery" Dynamic Application, SL1 will create component devices for the components managed by the vCenter server and align other Dynamic Applications to those component devices. Some of the Dynamic Applications aligned to the component devices are also used to create additional component devices. All component devices appear on the **Devices** page.

NOTE: During initial discovery, SL1 requests information about 200 devices per poll period until all component devices are discovered. After initial discovery, SL1 requests only the changes from the previously collected topology. If you have a large VMware infrastructure, it can take several collection cycles after the initial collection of the "VMware: RootFolder Datacenter Discovery" Dynamic Application for all component devices to be discovered.

In addition to the **Devices** page, you can view the vCenter server and all associated component devices in the following places in the user interface:


- Viewing Component Devices in SL1
- Viewing Component Devices in the SL1 Classic User Interface

Viewing Component Devices in SL1


- The **Device Investigator** Map page (click **Map** in the **Device Investigator** page) displays a map of a particular device and all of the devices with which it has parent-child relationships. Double-clicking any of the listed devices reloads the page to make the selected device the primary device.
- The Device Components page (Devices > Device Components) displays a list of all root devices and
 component devices discovered by SL1. The Device Components page displays all root devices and
 component devices in an indented view, so you can easily view the hierarchy and relationships between child
 devices, parent devices, and root devices. To view the component devices associated with a vCenter server,
 find the vCenter server and click its plus icon (+).
- The Component Map page (Classic Maps > Device Maps > Components) allows you to view devices by
 root node and view the relationships between root nodes, parent components, and child components in a
 map. This makes it easy to visualize and manage root nodes and their components. SL1 automatically
 updates the Component Map as new component devices are discovered. The platform also updates each
 map with the latest status and event information. To view the map for a vCenter server, go to the
 Component Map page and select the map from the list in the left NavBar. To learn more about the
 Component Map page, see the Views manual.

Viewing Component Devices in the SL1 Classic User Interface


• The **Device View** modal page (click the bar-graph icon [**1**] for a device, then click the **Topology** tab) displays a map of a particular device and all of the devices with which it has parent-child relationships. Double-clicking any of the listed devices reloads the page to make the selected device the primary device:



• The **Device Components** page (Registry > Devices > Device Components) displays a list of all root devices and component devices discovered by SL1. The **Device Components** page displays all root devices and component devices in an indented view, so you can easily view the hierarchy and relationships between child devices, parent devices, and root devices. To view the component devices associated with a vCenter server, find the vCenter server and click its plus icon (+):



The Component Map page (Classic Maps > Device Maps > Components) allows you to view devices by root node and view the relationships between root nodes, parent components, and child components in a map. This makes it easy to visualize and manage root nodes and their components. SL1 automatically updates the Component Map as new component devices are discovered. The platform also updates each map with the latest status and event information. To view the map for a vCenter server, go to the Component Map page and select the map from the list in the left NavBar. To learn more about the Component Map page, see the Views manual.



Relationships with Other Types of Component Devices

In addition to the parent/child relationships between component devices, the following relationships are automatically created by the Dynamic Applications in the VMware: vSphere Base Pack PowerPack:

- VMware Virtual Machines and VMware Datastores
- VMware Virtual Machines and VMware Networks
- VMware Virtual Machines and Cisco Cloud Center
- VMware VirtualApps and VMware Networks
- VMware Hosts and VMware Datastores
- VMware Hosts and VMware Networks
- VMware Hosts and VMware Virtual Machines
- VMware Datastore Clusters and VMware Virtual Machines
- VMware Datastore Clusters and VMware Host Clusters
- VMware Datastore Clusters and VMware Hosts

SL1 can also automatically build relationships between VMware component devices and other associated devices. If you discover one or more of the following:

- A Dynatrace host using the Dynamic Applications in the Dynatrace PowerPack
- A Cisco UC VOS application using the Dynamic Applications in the Cisco: UC VOS PowerPack
- A Cisco CUCM cluster using the Dynamic Applications in the Cisco: CUCM PowerPack
- An EMC VNX device using the Dynamic Applications in the EMC: VNX PowerPack
- A NetApp device using the Dynamic Applications in the NetApp Base Pack PowerPack
- A UCS device using the Dynamic Applications in the Cisco: UCS PowerPack

SL1 automatically creates relationships between the following types of component devices, where appropriate:

- Dynatrace hosts and VMware Datastores
- Cisco UC VOS applications and VMware Datastores
- Cisco CUCM clusters and VMware Datastores
- EMC VNX LUNs and VMware Datastores
- NetApp LUNs and VMware Datastores
- VMware Hosts and UCS Service Profiles

Determining Availability for Component Devices

The Dynamic Applications that discover the component devices managed by a vCenter server include collection objects that define the availability status of those component devices.

The following types of component devices are considered unavailable if a vCenter server reports that the power state is off:

- Compute Resource
- Host Server (i.e., ESX and ESXi Servers)
- Virtual Machine

The following types of component devices are considered unavailable if a vCenter server loses its connection to an ESXi hypervisor host server:

- Host Server
- Virtual Machine

The following types of component devices are considered unavailable if a vCenter server does not include information about those components in the appropriate response:

- Distributed Virtual Switch
- Distributed Virtual Portgroup
- Folder
- Network
- Resource Pool

The following types of component devices are considered unavailable based on other conditions:

- **Datastore**. A datastore is considered unavailable if it is not accessible. A datastore is not accessible if no hosts have successfully mounted the datastore volume.
- **Cluster**. A cluster is considered unavailable if no hosts are associated with the cluster or all hosts associated with the cluster are powered off.

When a VMware device is shut down, an event is created to alert the user that the device is unavailable. If you turn off VMware devices intentionally, you can suppress these availability events.

To suppress these events:

- Create a device group that contains the VMware devices for which you want to suppress availability events.
- Suppress that device group in the relevant Event Policies.

To create the device group:

1. Go to the **Device Groups** page (Devices > Device Groups or Registry > Devices > Device Groups in the SL1 classic user interface).

2. Click the [Create] button. The Device Group Editor page appears:

Device Group Editor Creating new group						Guide Reset
Device Group Name	9	F	orce Child Visibility?		Sharing Permissions	
		[No]		-	[Private (visible to you only)]	-
lcon			Visibility		Permission Keys	
		Maps/Views Config Policies/Bulk Edit Notification/Automation Discovery Device Schedules Event Suppression RSS Feeds		*	EM7 System Administration Grant All Ticket Att Test IT Services b_TTSM mh-fT Services - View	×
Static Devices and Groups Devices [0]	Groups [0]					Del Add
Device Name •	Class Sub-class	D Organization		Device Grou	up Name • ID Devices	<u>Groups Rules</u>
No device	es in current device group.			Ņ	lo sub-groups in current device group.	
Dynamic Rules Rules Found [0]						Del Add
Selector Type			Selector Targets			Matched Devs 🗹
		No dynamic	rules in current device group.			
						Matched
			Save			

- 3. Enter values in the following fields:
 - Device Group Name. In this field you can enter a customized Device Group Name. For example, "Event Suppressed VMs".
 - Visibility. Select Event Suppression.

4. If you want to suppress one or a few individual devices, click the **[Add]** button under the **Static Devices and Groups** pane and select *Add Devices*. The **Device Alignment** modal page appears:

ce Alignment						Res	et
Device Name •	IP Address	Category	Class Sub-class	ID	Organization	Action	
. , M.Xen		Servers	Xen Cluster Xen Cluster	1924	Svstem	_	e,
. 10-Forward	10.20.30.195	Servers	NET-SNMP FreeBSD	115	System		
. 10.0.0.3	10.0.0.3	Unknown	Cisco Systems OEM	1944	System		i.
. 10.0.0.5	10.0.0.5	Unknown	Cisco Systems OEM	1943	System		
. 10.0.10.21		VMware	VMware Host Server	1722	System		ī.
. 10.0.10.22		VMware	VMware Host Server	1723	System		
. 10.0.10.23		VMware	VMware Host Server	1721	System		
. 10.0.10.24		VMware	VMware Host Server	1716	System		
. 10.0.10.25		VMware	VMware Host Server	1719	System		ï
. 10.0.10.26		VMware	VMware Host Server	1709	System		
. 10.0.10.27		VMware	VMware Host Server	1710	System		ï
. 10.0.10.29		VMware	VMware Host Server	1690	System		
. 10.0.10.30		VMware	VMware Host Server	1712	System		ï
. 10.0.10.31		VMware	VMware Host Server	1714	System		
. 10.0.10.32		VMware	VMware Host Server	1927	System		ï
. 10.0.10.33		VMware	VMware Host Server	1912	System		
. 10.0.10.33		VMware	VMware Host Server	1711	System		ï
. 10.0.10.34		VMware	VMware Host Server	1708	System		
. 10.0.10.40		VMware	VMware Host Server	1922	System		
. 10.0.9.180		VMware	VMware Host Server	1657	System		
. 10.0.9.180		VMware	VMware Host Server	1408	System		
. 10.0.9.181		VMware	VMware Host Server	1411	System		
. 10.0.9.181		VMware	VMware Host Server	1656	System		ï
. 10.0.9.182		VMware	VMware Host Server	1558	System		
. 10.0.9.182		VMware	VMware Host Server	1409	System		
. 10.0.9.183		VMware	VMware Host Server	1414	System		
. 10.0.9.183		VMware	VMware Host Server	1646	System		Ē
10.0.9.184		VMware	VMware Host Server	1645	System		
. 10.0.9.184		VMware	VMware Host Server	1412	System		Ĩ
10.0.9.185		VMware	VMware Hoet Server	1410	Svetem		

- 5. In the **Device Alignment** modal page, perform a search in the **Class | Sub-class** column for "Virtual Machine" to bring up the available VMware devices.
- 6. Find the device(s) for which you want to suppress availability events and select their checkbox (
- 7. Click the [Add/Remove] button to add the device(s).

8. To add all VM devices to the device group, click the **[Add]** button in the **Dynamic Rules** pane of the **Device Group Editor** page. The **Device Group Rule Editor** page appears:

evice Group Rule Editor							Res	et
Active Selectors	Selector Definition	s						
Organization								
Device Class								
Device Category								
Device Name								
Device IP								
Device State								
Collection State								
Open TCP Ports								
Running Process								
Windows Service								
Subscribed Product								
Active Event								
Active Event								
Matched Devices [1120]								
Device Na	ame •	Category	Class Sub-class	ID	Orgar	nization	Collection State	^
1Xen		Servers	Xen Cluster Xen Cluster	1924	System	Active		1
2. 📶 10-Forward		Servers	NET-SNMP FreeBSD	115	System	Active		
3. 📶10.0.0.3		Unknown	Cisco Systems OEM	1944	System	Active		
4. 10.0.0.5		Unknown	Cisco Systems OEM	1943	System	Active		
5. 10.0.10.21		VMware	VMware Host Server	1722	System	Active		
6. 10.0.10.22		VMware	VMware Host Server	1723	System	Active		
7. 10.0.10.23 8. 11.10.0.10.24		VMware VMware	VMware Host Server VMware Host Server	1721 1716	System System	Active		
0. 10.0.10.24		VMware	VMware Host Server	1710	System	Active		
9 10 0 10 25				11.10		Activo		
9. 10.0.10.25 10. 11.0.10.26		VMware	VMware Host Server	1709	System	Active		
9. 10.0.10.25 10. 10.0.10.26 11. 10.0.10.27		VMware VMware	VMware Host Server VMware Host Server	1709 1710	System System	Active Active		
10. 10.0.10.26				1710				Ţ

9. In the **Device Group Rule Editor** page, select the checkbox (12) for **Device Class** in the **Active Selectors** pane.

10. In the Selector Definitions pane, the Device Class field appears. Perform a search for "VMware" in the Device Class field, and select VMware | Virtual Machine. All virtual machines will appear in the Matched Devices pane:

vice Group Rule Editor							R	
ctive Selectors	Selector Definition	ons						
Organization		Device	Class	Invert 🗐				
Device Class	VMware							
Device Category	VMware Host Se							
Device Name	VMware Networ							
Device IP	VMware Resour							
Device State	VMware vCenter							
	VMware Virtual							
Collection State	VMware Virtual	Machine		T				
Open TCP Ports								
Running Process								
Windows Service								
windows Service								
Subscribed Product								
Subscribed Product								
Subscribed Product Active Event Asset Make Contemport		Category	<u>Class Sub-class</u>	D		Organization	<u>Collection</u> State	
Subscribed Product Active Event Asset Make Asset Make Devices [360] Device 1 . [n][100.10_IS_10.10.10]	00.17	VMware	VMware Virtual Machine	1587	System	<u>Organization</u>	Active State	
Subscribed Product Active Event Asset Make Center State C	00.17	VMware VMware	VMware Virtual Machine VMware Virtual Machine	1587 1591	System	Organization	Active Active	
Subscribed Product Active Event Asset Make Control Con	00.17 0.15	VMware VMware VMware	VMware Virtual Machine VMware Virtual Machine VMware Virtual Machine	1587 1591 1490	System System	Organization	<u>State</u> Active Active Unavailable	,
Subscribed Product Active Event Asset Make atched Devices [360]	00.17 0.15 al	VMware VMware VMware VMware	VMware Virtual Machine VMware Virtual Machine VMware Virtual Machine VMware Virtual Machine	1587 1591 1490 1482	System System System	Organization	State Active Active Unavailable Unavailable	
Subscribed Product Active Event Asset Make atched Devices [360] <u>Device 1</u> 	00.17 0.15 al	VMware VMware VMware VMware VMware	VMware Virtual Machine VMware Virtual Machine VMware Virtual Machine VMware Virtual Machine VMware Virtual Machine	1587 1591 1490 1482 1672	System System System System	Organization	State Active Active Unavailable Unavailable Unavailable	
Subscribed Product Active Event Asset Make atched Devices [360] <u>Device</u> 1 1. m[100.10_IS_10.100.10 2. m[100.8]S_10.100.10 3. m[7.1.10_IS 4. m[7.1.X-7.2.beta.intern: 5. m[7.1.X-7.2.beta.intern: 6. m[7Safe Test System]	00.17 0.15 al	VMware VMware VMware VMware VMware VMware	VMware Virtual Machine VMware Virtual Machine VMware Virtual Machine VMware Virtual Machine VMware Virtual Machine VMware Virtual Machine	1587 1591 1490 1482 1672 1606	System System System System	Organization	State Active Active Unavailable Unavailable Unavailable Unavailable	
Subscribed Product Active Event Asset Make Device 1. m[100.10_IS_10.100.10 . m[17.1.10_IS . m[7.1.X-7.2 beta.intern 5. m[7.1X-7.2 beta.intern 6. m[7Safe Test System 7. m[7Safe Test System	00.17 0.15 al	VMware VMware VMware VMware VMware VMware VMware	VMware Virtual Machine VMware Virtual Machine VMware Virtual Machine VMware Virtual Machine VMware Virtual Machine VMware Virtual Machine	1587 1591 1490 1482 1672 1606 1500	System System System System System	Organization	State Active Active Unavailable Unavailable Unavailable Unavailable	
Subscribed Product Active Event Asset Make atched Devices [360]	00.17 0.15 al	VMware VMware VMware VMware VMware VMware VMware VMware	VMware Virtual Machine VMware Virtual Machine VMware Virtual Machine VMware Virtual Machine VMware Virtual Machine VMware Virtual Machine VMware Virtual Machine	1587 1591 1490 1482 1672 1606 1500 1635	System System System System System System	Organization	State Active Unavailable Unavailable Unavailable Unavailable Unavailable Active	
Subscribed Product Active Event Asset Make atched Devices [360] Pevice 1 , m[100.10_IS_10.100.10 , m[17.1.X-7.2.beta.intern , m[7.1.X-7.2.beta.intern , m[7.5afe Test System , m[8633_Al0], m[8633_Al0]	00.17 0.15 al	VMware VMware VMware VMware VMware VMware VMware VMware VMware	VMware Virtual Machine VMware Virtual Machine	1587 1591 1490 1482 1672 1606 1500 1635 1516	System System System System System System System	Organization	State Active Unavailable Unavailable Unavailable Unavailable Unavailable Active Active	
Subscribed Product Active Event Asset Make Cevice Internet Content of the set	00.17 0.15 al	VMware VMware VMware VMware VMware VMware VMware VMware	VMware Virtual Machine VMware Virtual Machine VMware Virtual Machine VMware Virtual Machine VMware Virtual Machine VMware Virtual Machine VMware Virtual Machine	1587 1591 1490 1482 1672 1606 1500 1635	System System System System System System System	Organization	State Active Unavailable Unavailable Unavailable Unavailable Unavailable Active	

11. Click the **[OK]** button. The Device Class will appear in the **Dynamic Rules** pane.

Next, you need to suppress two Event Policies for this Device Group.

- Suppressing the Event Policies in SL1
- Suppressing the Event Policies in the SL1 classic user interface

To suppress two Event Policies for this Device Group:

- 1. Go to the **Event Policies** page (Events > Event Policies).
- 2. Perform a search for "Availability".
- 3. Locate the **Poller: Availability Check Failed** policy, click the actions icon (---) and select **Edit**. The **Policy Description** page appears. Click the **[Suppression]** tab.

						🔍 Activity	Em7admin 🗸	
Poller: Availability Check F	ailed	Enable Event Pol	licy 🌑				Cancel	Save
Policy Description Ma	tch Logic E	vent Message	Suppression					
Devices		_		Select Devices	Device Groups		Sele	ct Device Groups
No Devices Selected					No Device Groups Selected			

- 4. In the Device Groups pane, click the [Select Device Groups] button.
- 5. In the **Available Device Groups** window, locate the device group you created and select its checkbox. Click the **[Select]** button. The selected device group now appears in the **Device Groups** pane.
- 6. Click the **[Save]** button.
- 7. Repeat these steps for the **Poller: Availability Healthy** event policy to suppress events that will occur when a VMware device is turned back on again.

To suppress the two Event Policies in the SL1 classic user interface:

- 1. Go to the **Event Policy Manager** page (Registry > Events > Event Manager).
- 2. Perform a search in the Event Policy Name column for "Availability".

3. Click the wrench icon (for the **Poller: Availability Check Failed** policy. The **Event Policy Editor** page appears:

Event Policy Editor Editing Event Policy [927]	New Reset Guide
Policy Advanced Suppressions	
Available Device Groups	Suppressed Device Groups
mh-Test Group aws Data Centers mh Testgroup2	Event Suppressed VMs
	2
	v v
Available Devices	Suppressed Devices
Advanced Telecommunications Modules Ld: OEM: Broadxent system Altiga Networks: OEM: Custo_10.20.30.134 Atiga Networks: OEM: Custo_VPN3000 Altiga Networks: OEM: Custo_VPN3000 APC: MasterSwitch PDU: Imnt-reset1 APC: SmartUPS 2200: ups1.twm.az APC: Web/SNMP Management Card: power16 APC: Web/SNMP Management Card +: LA3-POWER101 Ascend Communications: Pipeline BRI: acct-341474 Ascend Communications: Pipeline BRI: acct-341474 ASKEY Computer Comp.: OEM: 10.2.0.30.52 Avage: DEM: INCTS8720Act Avacent: DSR1021 03.03.00.07: DSR1021 06-E0-7D Avocent: DESR1021 03.03.00.07: DSR1021 06-E0-7D Avocent: DEM: COM: 1650 05-57-7A Avocent: DEM: CPS: 1610 90-8F-22 Avocent: OEM: DSR1022 02-10-63	(lo devices suppressed)
	Save Save As

- 4. Click the [Suppressions] tab in the Event Policy Editor page.
- 5. In the **Available Device Groups** field, select the device group you created. In this example, you would select *Event Suppressed VMs*.
- 6. Click the right arrow button, [>>], and the device group moves to the **Suppressed Device Groups** field.
- 7. Click the **[Save]** button.
- 8. Repeat these steps for the **Poller: Availability Healthy** event policy to suppress events that will occur when a VMware device is turned back on again.

Chapter



Dashboards

Overview

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon (三).

SL1 includes the VMware: vSphere Dashboards PowerPack, which contains dashboards that display data collected from VMware systems.

In addition, the VMware: vSphere Base Pack PowerPack includes device dashboards that provide summary information for VMware component devices. Each of these device dashboards is aligned as the default device dashboard for its equivalent device class.

The following sections describe how to install the VMware: vSphere Dashboards PowerPack and a description of each dashboard that is included in the VMware: vSphere Dashboards and VMware: vSphere Base Pack PowerPacks:

Installing the VMware: vSphere Dashboards PowerPack						
VMware Host Performance Dashboard						
VMware vCenter Overview Dashboard						
VMware Device Dashboards						
VMware: Cluster						
VMware: Datastore						
VMware: Datastore Cluster						
VMware: Host						
VMware: Resource Pool						

VMware: Virtual App	
VMware: Virtual Machine	

Installing the VMware: vSphere Dashboards PowerPack

Before you can view the VMware Host Performance or VMware vCenter Overview dashboards in SL1, you must first install the VMware: vSphere Dashboards PowerPack. To do so:

- 1. Go to the **PowerPack Manager** page (System > Manage > PowerPacks).
- 2. Click the [Actions] button, then select Install PowerPack. The Imported PowerPacks modal page appears.
- 3. Use the search filter in the **PowerPack Name** column heading to locate the PowerPack you want to install. To do so, enter text to match, including special characters, and the **Imported PowerPacks** modal page displays only PowerPacks that have a matching name.

mported PowerPacks™ PowerPack Files Found [298]										
	PowerPack Name	Version	Revisio <u>n</u>	GUID	Last E	Edited	Importe	ed •		
					All	<u> </u>	All	_	_	
1.	Event Association Test	1	1	DED1884762194566B70BCD4DF3A742	2015-12-1	6 09:43:07	2015-12-16	09:43:00	1	
2.	Event Suppression Test	1	1	EC64565DCA55E155135F91F81F44D8-	2015-12-0	9 07:44:17	2015-12-09	07:44:12	1	
3.	SLPSD: Onboarding	0.20000	287	E121312B60972ED35BEDA19E88D195	2015-11-1	2 12:14:05	2015-11-12	12:13:50	1	
4.	SL_PS Cisco 3rd Party Device Support	1.39999	151	8B78EDB3A373B2D187ECEAE2545744	2015-11-0	5 12:17:39	2015-11-05	12:16:54	1	
5.	NetApp Base Pack	7.7.0	6873	8014D5DAD2B8C9AC3E1DD84CC227E	2015-10-2	1 13:31:47	2015-10-29	14:56:55	1	
6.	Cisco: Contact Center Enterprise *BETA*	0.5	1119	7CC6AD933EFB4FF5D840EFEA40F85C	2015-12-1	4 13:50:50	2015-10-29	14:56:54	1	
7.	EM7 Standard Device Categories	7.7.0	255	7A7322AA30F189B42943C082EFD7121	2015-06-0	2 18:30:56	2015-10-29	14:56:54	1	
8.	BL Test	1	2	74F7E816CF0FC9153700D2AF0982C2	2015-10-2	9 10:56:11	2015-10-29	10:56:06	1	
9.	BL Test	1	1	74F7E816CF0FC9153700D2AF0982C2	2015-10-2	9 10:56:11	2015-10-29	10:54:15	1	
10.	Microsoft: Office 365 *BETA*	0.5	138	8FA30F7D1FAC9162DD8C717D9EF778	-	-	2015-10-20	16:44:37	1	
11.	NetApp Base Pack	7.7.0	6838	8014D5DAD2B8C9AC3E1DD84CC227E	2015-10-2	1 13:31:47	2015-10-20	16:44:37	1	
12.	Cisco: Contact Center Enterprise *BETA*	0.5	1109	7CC6AD933EFB4FF5D840EFEA40F85C	2015-12-1	4 13:50:50	2015-10-20	16:44:36	1	
13.	EM7 Default Internal Events	7.7.0	316	BE1F363DB4BA9A10F5C6BC28931F0B	2015-10-2	8 13:26:25	2015-10-20	16:44:36	1	
14.	F5 BIG-IP *BETA*	7.7.0	3242	BFA4E6B316FD2302D913EF38FE7FF82	2015-10-2	8 13:26:27	2015-10-20	16:44:36	1	
15.	Microsoft: Office 365 *BETA*	0.5	136	8FA30F7D1FAC9162DD8C717D9EF778	-	-	2015-10-14	15:12:24	1	
16.	Cisco: Contact Center Enterprise *BETA*	0.5	1022	7CC6AD933EFB4FF5D840EFEA40F85C	2015-12-1	4 13:50:50	2015-10-14	15:12:23	1	
17.	Microsoft Base Pack	7.7.0	868	97469E96E98B5DAB516F3CCC8747CE	2015-10-2	8 13:26:26	2015-10-13	12:47:54	1	
18.	EM7 Default Internal Events	7.7.0	315	BE1F363DB4BA9A10F5C6BC28931F0B	2015-10-2	8 13:26:28	2015-10-13	12:47:54	1	
19.	NetApp Base Pack	7.7.0	6792	8014D5DAD2B8C9AC3E1DD84CC227E	2015-10-2	1 13:31:47	2015-10-13	12:47:54	1	

4. Click the lightning-bolt icon (//) for the PowerPack that you want to install.

5. The Install PowerPack modal page appears. To install the PowerPack, click [Install].


nstall Power-Pack™ .kates_test_pp_3 Ve	rsion 1			Reset
Package Information GUID: 9F7ECF5 Created: 2015-07-28 14:10:53	CBC81D713AD94AF704FBA136C Updated: 2015-07-28 14:10:53	Revision: 2 Compi	Exported From: 7.6.0.beta iled: 2015-07-28 14:12:21	
Package Content				
	Theme Name		GUID	Action
1. kates_test_theme_3			A6D9EA56C5FAE1F35E6F0411BD79AD	
2. kates_test_theme_4			ADA02B6763C3CCA014FBB00A9A21A6	4 update
Installation Key: hBGC6WETV3SH8Epey	o7cpySyuEak0FeBpD/IYENPd0oBSc) Insta		2molbNRR/6MJw6aZOvgFY(

6. The PowerPack now appears in the **PowerPack Manager** page. The contents of the PowerPack are automatically installed in your SL1 System.

VMware Host Performance Dashboard

The VMware Host Performance dashboard allows service providers to monitor VMware hosts and diagnose problems with those hosts. The dashboard can include data from up to four hosts in each graph. This allows users to find correlations between hosts in data drops or spikes, making it easier for users to identify and diagnose issues.

The dashboard displays the following widgets:



Context Quick Selector. This widget is located along the top of the dashboard and contains:

- *Time span presets*. Users select the time span over which they want to view data. Selections range from 6 hours to 90 days.
- vCenter Selector. If a user has multiple vCenters, this drop-down list allows the user to select one or several vCenters for which they want to view data.
- Organizations Selector. This drop-down list allows a user to select specific organizations for which they want to view data.
- IT Services Selector. If a user has an ITSM service (for example, for e-commerce), the IT Services Selector drop-down list allows them to select an IT service for which they want to view data.

Host Status. Displays the IP address of each VMware ESX/ESXi server and its status with a color-coded "traffic light" icon. When you select one or more VMware ESX/ESXi server, the four performance widgets are populated with data from that host server(s). The status of each host is indicated as follows:

- Critical. Host has a serious problem that requires immediate attention.
- Major. Host has a problem that requires immediate attention.
- Minor. Host has a less-serious problem.
- Notice. Host has an informational event associated with it.
- Healthy. Host is running with no problems.

NOTE: More than four hosts can be selected in the **Host Status** widget, but the dashboard will only display data from the first four that have been selected.

VMware Inventory. This widget displays information based on the user's credentials. The widget displays inventory information about the following:

- vCenters
- Clusters
- Resource Pools
- Hosts
- VMs
- Total CPU Cores
- Total RAM
- Platform

The following four widgets measure different aspects of VMware performance. Select one or more hosts in the *Host Status* widget to view data in these widgets:

• VMware Host CPU & Memory Utilization. Displays overall and average CPU and Memory Utilization in percent. Displays a line graph with a line each for CPU Utilization and Memory Utilitization over the time period selected in the Context Quick Selector by percent.


- VMware Host Disk Read Performance. Displays the Disk Read Performance of the selected host in a line graph.
- VMware Host Network Utilization. Displays the Network Utilization of the selected host in a line graph.
- VMware Host Disk Write Performance. Displays the Disk Write Performance of the selected host in a line graph.

Each of the four performance widgets has the following features:

- The X-axis of each widget displays time selected in the Context Quick Selector by hours or days.
- For the selected VMware ESX/ESXi server, the Y-axis displays either performance or utilization by percentage or in a format that is auto-converted to the most consumable value based on the server.
- You can hide a data series by selecting the label in the legend that appears at the bottom of the widget. To show a hidden data series, select the label again.
- You can zoom in on a section of the graph by clicking, holding, and dragging your mouse across the section you want to view. If you are zoomed in on a section of the graph, you can revert to the original time span by selecting *Reset zoom* in the top-right corner of the graph.
- Hovering the cursor over a single line reveals details about specific data points. If you select a data point, the **Device Performance** page will open in a separate window with the graph for the selected metric displayed.

VMware vCenter Overview Dashboard

The VMware vCenter Overview dashboard allows users to have visibility into their VMware environment. Users can view how their VMs and hosts are performing over a given period of time. The dashboard allows diagnostics with its overlay capability. By selecting up to four hosts, the usage average of those devices and hosts can reveal correlations in spikes or drops in data, allowing the user to quickly diagnose issues.



Context Quick Selector. This widget contains the time span presets buttons, vCenter Selector, VMware VM Selector, Organizations Selector, and IT Services Selector.

• *Time span presets*. Users select the time span over which they want to view data. Selections range from 6 hours to 90 days.

- vCenter Selector. If a user has multiple vCenters, this drop-down list allows the user to select one or several vCenters for which they want to view data
- VMware Host Selector. This drop-down list allows a user to select up to four VMware Hosts for which they want to view data.
- Organizations Selector. This drop-down list allows a user to select specific organizations for which they want to view data
- IT Services Selector. If a user has an ITSM service for e-commerce, for example, the IT Services Selector drop-down list allows them to select an IT service for which they want to view data.

Host Status. Displays the IP address of each VMware server and its status with a color-coded "traffic light" icon. When one or more are selected, the graphs will be populated with data from that host server(s). The status of each host is indicated as follows:

- Critical. Host has a serious problem that requires immediate attention.
- Major. Host has a problem that requires immediate attention.
- Minor. Host has a less-serious problem.
- Notice. Host has an informational event associated with it.
- Healthy. Host is running with no problems.

NOTE: More than four hosts can be selected in the *Host Status* widget, but the dashboard will only display data from the first four that have been selected. It is recommended that you select VMware devices from the *VMware VM Selector* drop-down list in the *Quick Context Selector* widget.

VMware Inventory. This widget displays information based on the user's credentials. The widget displays inventory information about the following:

- vCenters
- Clusters
- Resource Pools
- Hosts
- VMs
- Total CPU Cores
- Total RAM
- Platform

VM CPU Utilization. Displays the 10 guest VMs with the highest average CPU utilization over the selected time period. The widget displays a bar graph with percentage utilized as the Y-axis.

VM Memory Top 10. Displays the 10 guest VMs with the highest average memory utilization over the selected time period. The widget displays a bar graph with percentage utilized as the Y-axis.

VM Disk IO Top 10. Displays the 10 guest VMs with the highest average disk usage over the selected time period. The widget displays a bar graph with disk utilization as the Y-axis.

VM Network Transmit Top 10. Displays the 10 guest VMs with the highest average outbound network utilization over the selected time period. The widget displays a bar graph with outbound network utilization as the Y-axis.


VM Network Receive Top 10. Displays the 10 guest VMs with the highest average inbound network utilization over the selected time period. The widget displays a bar graph with inbound network utilization as the Y-axis.

Detailed Performance Graph. The widget in the bottom-right of the dashboard displays data when a bar on any of the other graphs in this dashboard is selected. When a bar is selected, it displays the selected metric over time. You can select up to eight metrics to display in this graph by holding down the **<Ctrl>** key when you select each bar.

VMware Device Dashboards

The VMware: vSphere Base Pack PowerPack includes device dashboards that provide summary information for VMware component devices. Each of these device dashboards is aligned as the default device dashboard for its equivalent device class.

VMware: Cluster



The VMware: Cluster device dashboard displays the following information:

- The basic information about the cluster
- The current health, availability, and latency for the cluster
- A list of active events and open tickets associated with the cluster
- A count of, and links to, the elements associated with the cluster
- Four instances of the Multi-series Performance Widget that display the following metrics trended over the last 12 hours:
 - Cluster Effective CPU Average
 - CPU Usage Average
 - Cluster Effective Memory Average
 - Memory Total Average
 - Memory Swapped Average
 - Memory Consumed Average
 - Memory Balloon Average
 - Memory Active Average

VMware: Datastore



The VMware: Datastore device dashboard displays the following information:

- The basic information about the datastore
- The current health, availability, and latency for the datastore
- A list of active events and open tickets associated with the datastore
- A count of, and links to, the elements associated with the datastore
- Six instances of the Multi-series Performance Widget that display the following metrics trended over the last 12 hours:
 - Datastore Throughput Usage
 - Datastore Throughput Contention
 - Datastore Capacity
 - Datastore Free Space
 - Datastore Space Used
 - Datastore Uncommitted Space
 - Datastore Utilization
 - Datastore Host Total IOPS
 - Datastore Host Read IOPS
 - Datastore Host Write IOPS
 - Datastore VM Total IOPS
 - \circ $\,$ Datastore VM Read IOPS $\,$
 - Datastore VM Write IOPS
 - Storage I/O Control Aggregate IOPS
 - Virtual Disk Average Read IOPS
 - Virtual Disk Average Write IOPS

VMware: Datastore Cluster

	hboard: VMware: Datastore Cluster 💌											
De	evice Name DS Cluster	DS Cluster										
	D 7306			Category	Virtual.Infrastructure	9						
	Class VMware			Sub-Class	Datastore Cluster						5	
0	rganization System			Uptime	0 days, 00:00:00					Datastore 0	luster	
R	toot Device flexpod-vcenter			Group / Collector	CUG AWSdevAIO					🔺 😂 al (
Par	rent Device Datastores									DS Clu		
Device	Hostname									US CIL	ster	
									Elements			
Datastore	Cluster Capacity (Last 12 hours)								ciements	Active Events		
476.84GiB												
				_						Cleared Events		
238.42GiB				There are	no events or tickets for t	his device				Active Tickets [OWP	-	
200.42010										Resolved Tickets	~	
										Log Message:	21 强	
0GiB	04:00 08:00	12:00								Software Title:	- 🕥	
	- Datastore Cluster Capacity (kiB)									Processes	- 🍄	
	- Datastore Cluster Space Used (kiB)									Services	- 🍄	
	— Datastore Cluster Space Allocated (kiB)									TCP Ports	📣	
Datastore	Cluster IOPS (Last 12 hours)	Da	Datastore Cluster Space (Last 12 hours)				Datastore Cluster Latency (Last 12 hours)					
0.07IOPs												
		47	76.84GIB				20ms					
0.06IOPs		47	0.04010									
							17 Emo					
							17.5ms					
0.05IOPs		38	31.47GiB				17.5ms					
0.05IOPs -		38	31.47GiB				15ms					
0.05IOPs -												
			81.47GiB 286.1GiB				15ms					
		2	286.1GIB				15ms 12.5ms					
0.04IOPs		2					15ms 12.5ms					
0.04IOPs		2	286.1GIB				15ms 12.5ms 10ms 7.5ms					
0.04IOPs		19	286.1GIB				15ms 12.5ms 10ms					
0.04IOPs 0.03IOPs 0.02IOPs		19	286.1GiB 90.73GiB				15ms 12.5ms 10ms 7.5ms					
0.04IOPs		19	286.1GIB 90.73GIB 5.367GIB				15ms 12.5ms 10ms 7.5ms 5ms 2.5ms					
0.04IOPs 0.03IOPs 0.02IOPs 0.01IOPs		2 19 95	286.1GiB 90.73GiB	0400	05:00	12:00	15ms 12.5ms 10ms 7.5ms 5ms	04'00		08.00	12:00	
0.04IOPs 0.03IOPs 0.02IOPs	04.00 08.00	19	286.1GIB 90.73GIB 5.367GIB 0GIB	04/00 attastore Cluster Spa		12:00	15ms 12.5ms 10ms 7.5ms 5ms 2.5ms		Average	08 ¹ 00 Lead Latency (ms)	12:00	

The VMware: Datastore Cluster device dashboard displays the following information:

- The basic information about the datastore cluster
- A list of active events and open tickets associated with the datastore cluster
- A count of, and links to, the elements associated with the datastore cluster
- Four instances of the Multi-series Performance Widget that display the following metrics trended over the last 12 hours:
 - Datastore Cluster Capacity
 - Datastore Cluster Space Used
 - Datastore Cluster Space Allocated
 - Storage I/O Control Aggregate IOPS
 - Virtual Disk Average Read Latency
 - Virtual Disk Average Write Latency
 - Virtual Machine Observed Latency

VMware: Host


Device Dashboard: VMware: H	Host 💌					
Device Name 10.100.1	100.46		Managed Type	Component Device		
D 136			Category	Servers.VMware		76
Class VMware	e		Sub-Class	Host Server		
Organization System	1		Uptime	0 days, 00:00:00		Host System
Root Device labycente	er55		Group / Collector	CUG em7_ao		🔺 🕮 🛋 📾 🤌
Parent Device Hosts						10.100.100.46
Device Hostname						10.100.100.40
Vitals (Last 12 hours)		Tickets and Events				Elements
		1. \	/Mware: Host Memor	y Usage Has Exceeded Thresh	old (80%), currently (91%)	Active Events 1
100%						Cleared Events 15 🔺
						Active Tickets [OWP] 🐯
50% - Marthanhanh	almah h h h h h h h .					Resolved Tickets 🐯
50%						Log Messages 38 💽
						Software Titles
0%						Processes
0% 03. Feb 0	04:00 08:00					Services -
- Device Stats Availa	ability — CPU (%) — Memory (%)					TCP Ports
Root ResourcePool CPU Perfo	ormance (Last 12 hours)	HostSystem Memory	Performance (Last 12	2 hours)	HostSystem Network Perfo	1011010
		, ,	· ·	'	vmnic3	
5000Mhz	illili İlmanın danı danı danı danı da	20GB			vmnic0	
					overall	
					vmnic1	
2500Mhz		0GB 03. Feb	04:00	08:00	vmnic2	
0Mhz 03. Feb	04:00 08:00		Memory Swap Used Memory Consumed		0KB/sec 10KB/sec	20KB/sec 30KB/sec 40KB/sec 50KB/
		— I	Memory Balloon Av	erage (KB)		ork Transmitted Average
- CPU Us	sage Average (Mhz) (Mhz)		Memory Active Aver	rage (KB)	Netw	ork Received Average
Root ResourcePool Memory F	Performance (Last 12 hours)	HostSystem Disk Per	formance (Last 12 ho		HostSystem Datastore Per	formance (Last 12 hours)
20GB			1			
2068		20ms			0.05	
10GB			and and the	Mar will		
		10ms	-Minha, Maka	MMAMMM		
0GB 03. Feb 0	04:00 08:00	0ms			003. Feb	04:00 08:00
	Swapped Average (MB)	0ms 03. Feb	04:00	08:00	- Datastor	e Average Read Commands
- Memory	Consumed Average (MB)		k Total Write Laten		- Datastor	e Average Write Commands
	Active Average (MB)		k Total Read Laten k Commands Abort			e Write Latency (ms) e Read Latency (ms)
wemory	Active Average (MD)		N Commanus ADON		- Datastor	e read catelley (IIIS)

The VMware: Host device dashboard displays the following information:

- The basic information about the host
- A list of active events and open tickets associated with the host
- A count of, and links to, the elements associated with the host
- Seven instances of the Multi-series Performance Widget that display the following metrics trended over the last 12 hours:
 - Availability
 - CPU (%)
 - Memory (%)
 - CPU Usage Average
 - Memory Swap Used Average
 - Memory Consumed Average
 - Memory Balloon Average
 - Memory Active Average
 - Network Transmitted Average

- Network Received Average
- Disk Total Write Latency Average
- Disk Total Read Latency Average
- Disk Commands Aborted Summation
- Datastore Average Read Commands
- Datastore Average Write Commands
- Datastore Write Latency
- Datastore Read Latency

VMware: Resource Pool



The VMware: Resource Pool device dashboard displays the following information:

- The basic information about the resource pool
- A count of, and links to, the elements associated with the resource pool
- Two instances of the Multi-series Performance Widget that display the following metrics trended over the last 12 hours:
 - CPU Usage Average
 - Memory Active Average

- Memory Swap Used Average
- Memory Consumed Average
- Memory Balloon Average
- A topology map that shows the devices that are directly related to the resource pool

VMware: Virtual App

Device Dashboard: VMware: Virtual App 🔹		
Device Name Test vApp Test	Managed Type Component Device Category Virtual.Infrastructure Sub-Class Virtual App Uptime 0 days, 00:00:00 Group / Collector CUG AWSdevAIO	Virtual App
CPU Usage Average (Mhz) (Last 12 hours)	ResourcePool Memory Performance (Last 12 hours) 30MB 10MB 00.5 Feb 03:00 00:00 09:00 - Memory Active Average (MB) Memory Swapped Average (MB) Memory Balloon Average (MB)	Active Events - 4 Cleared Events 22 4 Active Tickets (OWP) - 23 Resolved Tickets - 25 Log Messages 24 3 Software Titles - 3 Processes - 3 Services - 3 TCP Ports - 4
Topology Map		Component Mapping VMware: VAppNetwork Relation VMware: VM/Network Relation

The VMware: Virtual App device dashboard displays the following information:

- The basic information about the virtual app
- A count of, and links to, the elements associated with the virtual app
- Two instances of the Multi-series Performance Widget that display the following metrics trended over the last 12 hours:
 - CPU Usage Average
 - Memory Active Average
 - Memory Swap Used Average
 - Memory Consumed Average
 - Memory Balloon Average

• A topology map that shows the devices that are directly related to the virtual app

VMware: Virtual Machine

Root Device labocenter55 Group / Collector CUG em7_ao Current Parent Device 10:100:100.46 Elements Current Current Overall Heath Heathly Current Current Current Vitals [Current] Elements Active Takes Active Takes Memory 18.45% There are no events or tickets for this device Active Takes Vitals (Latency mis There are no events or tickets for this device Active Takes Vitals (Latency 100% Current 100% Current 100% Latency 101, 102, 20% Memory Performance (Last 12 hours) Network Performance (Last 12 hours) Vitals (Last 12 hours) Memory Performance (Last 12 hours) Network Performance (Last 12 hours) 100% Geo 03, Feb 03/00 06/00 09/00	Device D	Dashboard: VI	Wware: Virtual Ma	achine 💌												
Root Device Islandscenter/55 Group / Calector CUG] em7_a0 Parent Device Islandsmall Group / Calector CUG] em7_a0 Vitals [Current] Group / Calector CUG] em7_a0 Over all tables Group / Calector CUG] em7_a0 Vitals [Average] Actor Actor Actor Tick Group / Calector CUG] em7_a0 Vitals [Average] Actor Actor Actor Tick Group / Calector CUG] em7_a0 Vitals [Average] Actor Actor Actor Tick Group / Calector Cug] em7_a0 Vitals [Average] Actor Actor Actor Tick Group / Calector Cug] em7_a0 Vitals [Average] Actor Actor Actor Tick Group / Calector Cug] em7_a0 Vitals [Average] Actor Actor Actor Tick Group / Calector Cug] em7_a0 Vitals [Average] Actor Actor Vitals [Average] Actor Actor Vitals [Average] Memory Performance (Last 12 hours) Overall 00% 03 Feb 0400		D	441	0.100.8			Category	Servers.VMware					٢	vm		
Parent Device 10.100.100.46 Control Device Itestame Elements Availability Overall Itesting Itesting Active Total Availability Overall Itesting Elements Availability Overall Itesting Elements Availability Overall Itesting Elements Availability Overall Itesting Elements Availability Overall Overall Overall Overall Overall Overall Overall Overall Overall Overall Overall Overall Overall Overall Overall O		Organization	System				Uptime	0 days, 00:00:00					Vi	tual Mac	hine	
Understand Elements Vitals [Current] Cover lessing							Group / Collector	CUG em7_ao					4	🗢 al e	1.0	
Under Reserved Clear and the served is or tickets for this device Clear and the served is or tickets for this device Action Clear and the served is or tickets for this device Action Clear and the served is or tickets for this device Action Clear and the served is or tickets for this device Action Clear and the served is or tickets for this device Action Clear and the served is or tickets for this device Action Clear and the served is or tickets for this device Action Clear and the served is or tickets for this device Action Clear and the served is or tickets for this device Action Clear and the served is or tickets for this device Action Clear and the served is or tickets for this device Action Clear and the served is or tickets for this device Action Clear and the served is or tickets for this device Action Clear and the served is or tickets for this device Action Clear and the served is or tickets for this device Action Clear and the served is or tickets for this device Action Clear and the served is or tickets for this device Action Clear and the served is or tickets for this device Action Clear and the served is or tickets for this device Action Clear and the served is of tickets for this device Action Clear and the served is of tickets for this device Action Clear and the served is of tickets for this device Action Clear and the served is of tickets for this device Action Clear and the served is of tickets for this device Action Clear and the served is of tickets for this device Action Clear and the served is of tickets for this device Action Clear and the served		Parent Device	ent Device 10.100.100.46											AIO_10.1		•
Availably Okay Letercy ms Letercy 724 m (000 ms Case Availably Okay Letercy 724 m (000 ms Case Available Case Letercy 724 m (000 ms Case Case Available Cas														IO IO. I	00.10	~
Availably Okay Litercy ms Memory 18 45% Vitals [Average] Avail (24 m; 100% Latercy (24 h; 0) 00 ms CrCU (14); 19 28% Memory (16); 22 3% Memory (16); 22 3% Memory Class 12 hours) Memory Class 12 hours) Device Stats Availability — CPU Usage Average (%) (%) Storage Performance (Last 12 hours) Device Stats Availability — CPU Usage Average (%) (%) Memory Class 12 hours) Device Stats Availability — CPU Usage Average (%) (%) Memory Class 12 hours) Device Stats Availability — CPU Usage Average (%) (%) Memory Class 12 hours) Device Performance (Last 12 hours) Device Performance (Last 12 hours) Device Stats Availability — CPU Usage Average (%) (%) Memory Class 12 hours) Device Stats Availability — CPU Usage Average (%) (%) Memory Class 12 hours) Device Stats Availability — CPU Usage Average (%) (%) Memory Class 12 hours) Device Stats Availability — CPU Usage Average (%) (%) Memory Class 12 hours) Device Stats Availability — CPU Usage Average (%) (%) Memory Class 12 hours) Device Stats Availability — CPU Usage Average (%) (%) Memory Class 12 hours) Device Stats Availability — CPU Usage Average (%) (%) Memory Class 12 hours) Device Stats Availability — CPU Usage Average (%) (%) Memory Class 12 hours) Device Stats Availability — CPU Usage Average (%) (%) Memory Class 12 hours) Device Stats Availability — CPU Usage Average (%) (%) Memory Class 12 hours) Device Stats Availability — CPU Usage Average (%) (%) Memory Class 12 hours) Device Stats Availability — CPU Usage Average (%) (%) Memory Class 12 hours) Device Stats Availability — CPU Usage Average (%) (%) Memory Class 12 hours) Device Stats Availability — CPU Usage Average (%) (%) Memory Class 12 hours) Device Stats Availability — CPU Usage Average (%) (%)												Elements	1			
Latency Tis 5 tiency 18 45% Vitals (Average) Avail (24 tro) 100/6 Latency 24 tro) 0.00 ms CPU (11r) 19.2% Memory (1 tro) 22.9% Vitals (Last 12 hours) Memory Performance (Last 12 hours) Network Performance (Last 12 hours) 100% 5GB 03.Feb 04.00 08.00 Device Stats Availability — CPU Usage Average (%) (%) Storage Performance (Last 12 hours) Dick Performance (Last 12 hours) Memory Swaped Average (KB) Memory Stats One Stats Availability — CPU Usage Average (%) (%) Storage Performance (Last 12 hours) Dick Performance (Last 12 hours) Datastore Performance (Last 12 hours) Dick Performance (Last 12 hours) Dick Performance (Last 12 hours) Dick Performance (Last 12 hours) Dick Performance (Last 12 hours) Dick Performance (Last 12 hours) Dick Performance Dick Performan	0												A	ctive Events		1
Memory 18:45% There are no events or ticklets for this device Active Tech Vitals (Average) Avail (24 tro; 100% Litericy (24 tro; 100% Litericy (24 tro; 100% Litericy (24 tro; 100% Litericy (24 tro; 100% Litericy (24 tro; 100% Litericy (24 tro; 100% Vitals (Last 12 hours) Memory Performance (Last 12 hours) Network Performance (Last 12 hours) Network Performance (Last 12 hours) 100% 5GB 03. Feb 04.00 06'00 Device Stats Availability - CPU Usage Average (%) (%) Disk Performance (Last 12 hours) Datastore Performance (Last 12 hours) Storage Performance (Last 12 hours) Disk Performance (Last 12 hours) Datastore Performance (Last 12 hours) 75GB 2MBps 0.3. Feb 0.4.00 0.6.00 11Bps 0.5. Performance (Last 12 hours) Datastore Performance (Last 12 hours)													Cle	ared Events	7	1
Vitals (Last 12 hours) Vitals						There an	e no events or tickets fo	r this device					Active Ti	ckets [OWP]		- 13
Avail (24 in) 100% Latery (24 in) 0.00 ms CPU (14) 19.2% Memory 29% Vitals (Last 12 hours) Memory Performance (Last 12 hours) Network Performance (Last 12 hours) 00% 03 Feb 04:00 06:00 Device Stats Availability — CPU Usage Average (%) (%) Storage Performance (Last 12 hours) Disk Performance (Last 12 hours) Device Stats Availability — CPU Usage Average (%) (%) Storage Performance (Last 12 hours) Disk Performance (Last 12 hours) Disk Performance (Last 12 hours) Disk Performance (Last 12 hours) Disk Performance (Last 12 hours) Disk Performance (Last 12 hours) Perf		–											Reso	Ived Tickets		- 23
Latercy (24 Kr) 0.0 ms CPU (1kr) 19.2% Memory (1kr) 19.2% Memory (1kr) 22.9% Vitals (Last 12 hours) Memory Performance (Last 12 hours) Memory Performance (Last 12 hours) Memory Saped Average (KB) Memory Consumed Average (KB) Memory Consumed Average (KB) Memory Consumed Average (KB) Memory Consumed Average (KB) Memory Cast 12 hours) Disk Performance (Last 12 hours)			%										Lo	g Messages	12	
Memory (1 Hr.) 22 9% Vitals (Last 12 hours) Memory Performance (Last 12 hours) Network Performance (Last 12 hours) 100% 0%<													Sof	tware Titles		۲
Vitals (Last 12 hours) Network Performance (Last 12 hours) 100% 5GB 50% 04'00 0% 03'Feb 04'00 08'00 Memory Swapped Average (KB) Memory (Ks) Storage Performance (Last 12 hours) Disk Performance (Processes		-
Vitals (Last 12 hours) Memory Performance (Last 12 hours) Network Performance (Last 12 hours) 100% 5GB 5GB org 0% 03. Feb 04:00 06:00 Device Stats Availability — CPU Usage Average (%) (%) Memory Baloon Average (KB) Memory Active Average (KB) Storage Performance (Last 12 hours) Disk Performance (Last 12 hours) Datastore Performance (Last 12 hours) Storage Performance (Last 12 hours) Disk Performance (Last 12 hours) Datastore Performance (Last 12 hours) Storage Performance (Last 12 hours) Disk Performance (Last 12 hours) Datastore Performance (Last 12 hours) Storage Performance (Last 12 hours) Disk Performance (Last 12 hours) Datastore Performance (Last 12 hours)	Me	emory (1 Hr.) <mark>22.</mark>	3%											Services		-
100% 5GB 5GB 5GB 06 03. Feb 03.00 06:00 09:00 00:00 </td <td></td> <td>TCP Ports</td> <td></td> <td>-</td>														TCP Ports		-
50% 50% 50% 50% 4000 wmicid 0% 03. Feb 04.00 06.00 wmicid wmicid 0 Device Stats Availability — CPU Usage Average (%) (%) Memory Swapped Average (KB) Memory Average (KB) Device Stats Availability — CPU Usage Average (%) (%) Storage Performance (Last 12 hours) Detk Performance (Last 12 hours) Datastore Performance (Last 12 hours) 75GB 2MBps 03. Feb 04.00 06.00 1MBps 03. Feb 04.00 06.00 0MBps 03. Feb 04.00 06.00	Vitals (I	(Last 12 hours)			Men	nory Performance (Last 12 hours)		Ne	twork Perfor	mance (Last 1					
0% 03. Feb 04'00 06'00 08'00 08'00 0% Device Stats Availability — CPU Usage Average (%) (%) Memory Snapped Average (KB) Memory Active Average (KB) Network Transmitted Average Storage Performance (Last 12 hours) Disk Performance (Last 12 hours) Datastore Performance (Last 12 hours) Datastore Performance (Last 12 hours) 56GB 04.00 08:00 00.00 08:00 00.00 MBps 03. Feb 04:00 08:00 00.00					5GB	A		have been be	vr	4000 nnic0						
0% 03. Feb 04:00 08:00 03. Feb 00:00 06:00 09:00 Device Stats Availability — CPU Usage Average (%) (%) Memory Swapped Average (KB) Memory Stats Average (KB) Memory Swapped Average (KB) Memory Stats Average (KB) Device Stats Availability — CPU Usage Average (%) (%) Device Stats Average (KB) Detvice Stats Average (KB) Storage Performance (Last 12 hours) Disk Performance (Last 12 hours) Datastore Performance (Last 12 hours) Datastore Performance (Last 12 hours) 50GB 1MBps 03. Feb 04:00 08:00 00. Feb 04:00 00:00		Autoch	robulant	webschahnbor	•	1000-0410	1000-000	i di di di de de de								
U3.Feb 04.00 06.00 Device Stats Availability — CPU Usage Average (%) (%) Memory Swapped Average (KB) Memory Casumed Average (KB) Memory Active Average (KB) Storage Performance (Last 12 hours) Disk Performance (Last 12 hours) Datastore Performance (Last 12 hours) 75GB IMBps 03.Feb 04.00 08.00 600 Memory Salloon Average (KB) Datastore Performance (Last 12 hours) Datastore Performance (Last 12 hours) 75GB IMBps 03.Feb 04.00 08.00	0%				OGB	03. Feb	03:00	06:00 09:00	v							
Device Stats Availability — CPU Usage Average (%) (%) Memory Consumed Average (KB) Memory Active Average (KB) Memory Cast 12 hours) Disk Performance (Last 12 hours) Disk P		03. Feb	04:00	0 08:00		- Memory Swap	ped Average (KB)			0KB/sec	5KB/sec	: 10K	(B/sec	15KB/sec		
Storage Performance (Last 12 hours) Disk Performance (Last 12 hours) Datastore Performance (Last 12 hours) 75GB 2MBps 2MBps 2MBps 50GB 1MBps 0.3 Feb 0.400 00 0.3 Feb 0.400 0.800	-			 CPU Usage Average (%) (%) 		 Memory Const 	umed Average (KB									
75GB 2MBps 2MBps 2MBps 50GB 1MBps 0.5 Feb 0.4 00 0.8 00 0MBps 0.3 Feb 0.4 00 0.8 00 0.0 00		- memory (%	6)			- Memory Balloo	on Average (KB)-	 Memory Active Average (KB)		Netwo	ork Receive	ed Average	:		
Social Images Images<	Storage	e Performance	(Last 12 hours)		Disk	Performance (Las	t 12 hours)		Da	itastore Perfo	irmance (Last	12 hours)				
25GB 0MBps 03 Feb 04'00 08'00 OMBps 03 Feb 04'00'00 OMBps 03 Feb 04'00'00'00'00'00'00'00'00'00'00'00'00'0		-			2MB	ps			21/	Bps			h			
03. Feb 04:00 08:00 Datasiole Read Rate (RD/Sec						min	malan	p	м ом	Bps 03. Fe	halo <mark>Med</mark>	04:00	08:	00	**	0ms
1 03 Feb 03:00 06:00 09:00 1 Datastore Write Rate (KB/sec	0GB				0MB	ps 03. Feb	04:00	08:00								
- Disk Read Average (KB/sec) Disk Write Average (KB/sec) Datastore Read Latency (ms) Disk Commands Aborted Summation						Disk Read Av Disk Comman	erage (KB/sec) — Ids Aborted Summa	Disk Write Average (KB/se ation	ec)		- Datas	tore Read	Latency (m	is)		

The VMware: Virtual Machine device dashboard displays the following information:

- The basic information about the virtual machine
- The current health, availability, latency, CPU, and memory for the virtual machine
- A list of active events and open tickets associated with the virtual machine
- A count of, and links to, the elements associated with the virtual machine
- Six instances of the Multi-series Performance Widget that display the following metrics trended over the last 12 hours:
 - Availability
 - CPU (%)
 - Memory (%)
 - Memory Swapped Average
 - Memory Consumed Average
 - Memory Balloon Average
 - Memory Active Average

- Network Transmitted Average
- Network Received Average
- Storage Committed
- Storage Uncommitted
- Disk Read Average
- Disk Write Average
- Disk Commands Aborted Summation
- Datastore Read Rate
- Datastore Write Rate
- Datastore Read Latency
- Datastore Write Latency

© 2003 - 2021, ScienceLogic, Inc.

All rights reserved.

LIMITATION OF LIABILITY AND GENERAL DISCLAIMER

ALL INFORMATION AVAILABLE IN THIS GUIDE IS PROVIDED "AS IS," WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED. SCIENCELOGIC [™] AND ITS SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT.

Although ScienceLogic[™] has attempted to provide accurate information on this Site, information on this Site may contain inadvertent technical inaccuracies or typographical errors, and ScienceLogic[™] assumes no responsibility for the accuracy of the information. Information may be changed or updated without notice. ScienceLogic[™] may also make improvements and / or changes in the products or services described in this Site at any time without notice.

Copyrights and Trademarks

ScienceLogic, the ScienceLogic logo, and EM7 are trademarks of ScienceLogic, Inc. in the United States, other countries, or both.

Below is a list of trademarks and service marks that should be credited to ScienceLogic, Inc. The ® and ™ symbols reflect the trademark registration status in the U.S. Patent and Trademark Office and may not be appropriate for materials to be distributed outside the United States.

- ScienceLogic[™]
- EM7[™] and em7[™]
- Simplify IT™
- Dynamic Application™
- Relational Infrastructure Management[™]

The absence of a product or service name, slogan or logo from this list does not constitute a waiver of ScienceLogic's trademark or other intellectual property rights concerning that name, slogan, or logo.

Please note that laws concerning use of trademarks or product names vary by country. Always consult a local attorney for additional guidance.

Other

If any provision of this agreement shall be unlawful, void, or for any reason unenforceable, then that provision shall be deemed severable from this agreement and shall not affect the validity and enforceability of any remaining provisions. This is the entire agreement between the parties relating to the matters contained herein.

In the U.S. and other jurisdictions, trademark owners have a duty to police the use of their marks. Therefore, if you become aware of any improper use of ScienceLogic Trademarks, including infringement or counterfeiting by third parties, report them to Science Logic's legal department immediately. Report as much detail as possible about the misuse, including the name of the party, contact information, and copies or photographs of the potential misuse to: legal@sciencelogic.com



800-SCI-LOGIC (1-800-724-5644)

International: +1-703-354-1010