

System Administration

SL1 version 12.2.1 (Document revision 1)

Table of Contents

Introduction	15
Who Should Read This Manual?	16
What's In This Manual?	16
Requirements	16
Global Settings	17
Global Settings for API	18
Global Settings for Appliances	19
The Web Configuration Utility	21
Global Settings for Asset Automation	22
Global Settings for User Logins, Discovery, Data Collection, UI Features, and Expiration Warnings	23
Configuring Single Instance Login for AP2	37
Global Settings for Data Retention	38
Normalization and Roll-Up of Performance Data	41
Collection of Raw Data	41
Data Normalization and Rollup	43
Example	44
Storage of Raw and Rolled Up Data	45
Global Settings for Inbound Email and Outbound Email	45
Global Settings for Login Alert Messages	49
Global Settings for Password Reset Emails	49
Defining the Email Message for "I forgot my password"	49
Global Settings for Security	51
Global Settings for System Thresholds	51
Global Settings for Interface Thresholds	56
Settings in Silo.Conf	64
Disabling the User Interface on a Database Server	72
Collector Groups	74
What is a Collector Group?	76
Installing, Configuring, and Licensing Data Collectors	76
Technical Information About Data Collectors	77
Duplicate IP Addresses	77

Open Ports	77
Viewing the List of Collector Groups	78
Viewing the List of Collector Groups in the Classic SL1 User Interface	78
Creating a Collector Group	79
Pre-Deployment Questions for a Collector Group	79
Capacity Planning for a Collector Group	79
Defining a Collector Group	80
Defining a Collector Group in the Classic SL1 User Interface	80
Editing a Collector Group	84
Editing a Collector Group in the Classic SL1 User Interface	84
Collector Groups and Load Balancing	85
Tuning Collector Groups in the silo.conf File	86
Load Balancing and Device State	88
Collector Affinity	88
Failover for Collector Groups for Component Devices	89
Collector Groups for Merged Devices	89
Creating a Collector Group for Data Storage Only	90
Deleting a Collector Group	90
Deleting a Collector Group in the Classic SL1 User Interface	90
Assigning a Collector Group for a Single Device	91
Assigning a Collector Group for a Single Device in the Classic SL1 User Interface	91
Aligning the Collector Group in a Device Template	92
Changing the Collector Group for One or More Devices	92
Managing the Host Files for a Collector Group	92
Processes for Collector Groups	93
Enabling and Disabling Concurrent PowerShell for Collector Groups	94
Enabling Concurrent PowerShell on All Collector Groups	94
Disabling Concurrent PowerShell on All Collector Groups	95
Enabling Concurrent PowerShell on a Specific Collector Group	95
Disabling Concurrent PowerShell on a Specific Collector Group	96
Enabling and Disabling Concurrent SNMP for Collector Groups	96
Enabling and Disabling Concurrent SNMP for All Collector Groups	97

Enabling and Disabling Concurrent SNMP for Collector Groups	97
Enabling Multi-tenancy for Collector Groups	98
Aligning Collector Groups to Organizations	98
Aligning Collector Groups to Organizations in the Classic SL1 User Interface	99
Daily Health Tasks	100
What is a Healthy SL1 System?	101
SL1 Self-Healing	104
Monitoring System Events	104
Searching the System Logs	105
Deleting Entries from the System Logs	107
Monitoring System Processes	107
Viewing the List of System Processes	107
Recommended System Maintenance	108
Searching and Filtering the List of System Processes	109
Monitoring the Status of Each Appliance	110
Logging in SL1 Version 11.3.0 and Later	113
Configuring TLS Certificates	114
Forwarding Local Syslog Messages to Remote Systems	115
Specifying Alternate Inbound TCP or UDP Ports	116
Adjusting the Priority Filter for Inbound Messages	118
Filtering or Discarding Inbound Messages	119
Sending Logs via Syslog to a Remote Server in SL1 Version 11.2.x and Earlier	119
Monitoring User Actions and Events on the Audit Logs Page	120
Viewing the List of Audit Logs	121
Searching and Filtering the List of Audit Logs	122
Generating Reports on Audit Logs	123
Using auditd to Monitor Sensitive Files	123
Files Logged by Default	123
Modifying the List of Files to be Logged	124
Monitoring the Status of Data Collectors	125
Updating SL1	127
The System Updates Page	128

The Workflow for Updating SL1	131
Planning the Update	132
Scheduling Maintenance Windows	132
Pre-Upgrade Best Practices for SL1	133
Backing Up SSL Certificates	133
Setting the Timeout for PhoneHome Watchdog	134
Adjusting the Timeout for Slow Connections	134
Running the System Status Script Before Upgrading	135
Running the System Status Script	135
Updating the SL1 Distributed Architecture	136
Downloading the Update	137
Importing the Update	137
Staging the Update	138
Automatic Staging	139
Manually Staging an Update	139
Monitoring Staging	140
Running the Pre-Upgrade Check	141
Running the Pre-Upgrade Check	141
Potential Issues to Address	142
CentOS 5 Failure	142
Collector Group Membership	142
Eligibility Failure	142
Enabled Failure	142
Free Disk-Space Failure	142
Host File Failure	142
Patch-Hook Ownership Failure	143
RPM Database Failure	143
RPM Package Failure	143
Putting All SL1 Appliances into Maintenance Mode	144
Deploying the Update	144
Troubleshooting System Update	145
Using the sysuptb Troubleshooting Tool	146

Available Commands	146
Using the phtb Troubleshooting Tool	150
Available Commands	151
Monitoring Deployment	151
Remove SL1 Appliances from Maintenance Mode	152
Updating SL1 Extended Architecture	. 153
Automatically Upgrading MariaDB with a Script	153
Additional Steps for MariaDB Upgrades in SL1 10.1.x	155
Manually Upgrading MariaDB	157
Download RPMs to SL1 Appliances	. 158
Manually Upgrade Two Database Servers Configured for High Availability or Disaster Recovery	159
Step 1: On the Secondary Database Server	. 159
Step 2: On the Primary Database Server	. 160
Step 3: On the Secondary Database Server	. 162
Manually Upgrade Three Database Servers Configured for High Availability and Disaster Recovery	. 163
Step 1: On the Secondary Database Server	. 163
Step 2: On the Primary Database Server	. 164
Step 3: On the Secondary Database Server	. 166
Step 4: On the Disaster Recovery Database Server	167
Manually Upgrading Standalone Database Servers, All-In-One Appliances, Data Collectors, and Message Collectors	. 169
Additional Steps for MariaDB Upgrades in 10.1.x	. 170
Rebooting Appliances in the SL1 Distributed Stack	. 173
Rebooting the Administration Portal	173
Rebooting Multiple Administration Portals	. 173
Rebooting a Single Administration Portal	173
Rebooting Data Collectors and Message Collectors	. 174
Rebooting Data Collectors and Message Collectors from the Appliance Manager page	. 174
Rebooting Data Collectors and Message Collectors from the Command Line	174
Rebooting Standalone All-In-One Appliance and Standalone Database Server	175
Rebooting Two Database Servers Configured for Disaster Recovery	. 175
Rebooting Two Database Servers in a High Availability Cluster	. 176

Rebooting Three Database Servers Configured for High Availability and Disaster Recovery	177
Restoring the SSL Certificates	179
Resetting the Timeout for PhoneHome Watchdog	179
Updating Default PowerPacks	180
Configuring Subscription Billing	181
Upgrading SL1 Extended Architecture	182
Workflow	183
Prerequisites	183
Resizing the Disks on the Compute Node	184
Installing ORAS	185
Obtaining Your Harbor Credentials	186
Upgrading to 12.2.x	186
Upgrading from 12.1.1 to 12.2.x	186
Upgrading from 12.1.0 (OL8) to 12.2.x	188
Step 1: Preupgrade	189
Step 2: Upgrade with Scylla or Disable the Scylla Cluster	190
Option 1: Upgrade with Scylla	190
Option 2: Disable Scylla	190
Step 3: Upgrade the SL1 Distributed Architecture	191
Upgrading to 12.1.1	192
Upgrading from 11.2.x, 11.3.x, or 12.1.0.x (OL7) to 12.1.1 (OL8)	192
Step 1: Preupgrade	192
Step 2: Upgrade or Disable the Scylla Cluster	193
Option 1: Rolling Upgrade	193
Option 2: Backup and Restore	196
Option 3: Disable Scylla	199
Step 3. Upgrade the SL1 Distributed Architecture	201
Step 4. Upgrade the Compute Node Cluster	201
Option 1: Six-node Clusters	201
Option 2: Three-node Clusters	202
Step 5. Upgrade the Management Node	203
Upgrading to 12 1 0 x	204

Upgrading from 11.2.x or 11.3.x to 12.1.0.x:	204
Upgrading from 11.1.x to 12.1.0.x	206
Upgrading to 11.3.x	208
Upgrading from 11.3.x to the Latest Version of 11.3.x	208
Upgrading from 11.2.x to 11.3.x	210
Upgrading from 11.1.x to 11.3.x	213
Upgrading from 10.2.x to 11.3.x	216
Upgrading to 11.2.x	219
Upgrading from 11.2.x to the Latest Version of 11.2.x	219
Upgrading from 11.1.x to 11.2.x	221
Upgrading from 10.2.x to 11.2.x	223
Upgrading from 10.1.x to 11.2.x	225
Upgrading to 11.1.x	228
Upgrading from 11.1.x to the Latest Version of 11.1.x	228
Upgrading from 10.2.x to 11.1.x	230
Upgrading from 10.1.x to 11.1.x	232
Upgrading from 8.14.x to 11.1.x	234
SL1 Self-Monitoring	238
The Workflow for SL1 Self-Monitoring	239
PowerPacks Required for Self-Monitoring	239
ScienceLogic Support Pack	239
Data Pull Support	240
SL1: Operational Insights PowerPacks	241
Credentials Required for Self-Monitoring	242
Discovering Your SL1 Devices	243
Enabling Connectivity on Port 7707	243
Aligning SL1 Self-Monitoring Dynamic Applications	244
Aligning the Correct Credentials to Your Devices	246
Configuring Run Book Automations to Populate Dashboards	246
Verifying Your Devices	247
Configuring the Run Book Automations	248
Additional Self-Monitoring Resources	249

Monitoring and Maintaining SL1	250
Monitoring and Managing User Access	250
Viewing Information about Each Access Session	251
Deleting a User's Session	251
Limiting the Number of Simultaneous User Sessions	252
Viewing Lockouts and Unlocking Lockouts	252
Global Settings for Lockouts	253
Audit Logs	253
Improved User Session Control with tmux	253
Managing Scheduled Tasks	253
Recommended System Maintenance	254
Viewing the List of Schedules	255
Enabling or Disabling One or More Schedules	256
Deleting One or More Schedules	257
Putting the Database Server into Maintenance Mode	257
Monitoring Overall System Usage and Statistics	258
Viewing an Overview of All Events	259
Viewing Events by Appliance and Event Source	260
Admin Notifier	262
How Does the Admin Notifier Work?	263
Admin Notifier in the Classic SL1 User Interface	263
What Issues Does the Admin Notifier Monitor?	264
Diagnostic Tools	267
Viewing Information About ScienceLogic Processes	267
Viewing the List of ScienceLogic Processes	268
Searching and Filtering the List of ScienceLogic Processes	270
Editing the Parameters of a ScienceLogic Process	271
Debugging a Process and Viewing Debug Logs	273
Viewing Information About Unhandled Exceptions	274
Viewing the List of Unhandled Exceptions	274
Searching and Filtering the List of Unhandled Exceptions	275
Saving the Unhandled Exception to the Local Computer	276

Viewing the Output of the System Status Script	277
Viewing the Database Tables on the Database Server	277
Accessing the Database Tool	278
Disabling Normalization, Re-Enabling Normalization, and Backfilling Raw Data	279
Enable Logging for Data Pull Storage Objects	282
Enable	282
Disable	283
Controlling Log Settings	283
Setting UI Developer Log Levels	283
Setting UI/REST MySQL Query Log Levels	284
Configuring Advanced Log Settings	284
Downloading Logs from the PHP Developer Logs page	284
Changing Passwords	286
Disabling phpMyAdmin	287
Changing the Password for the Default User Interface Account	287
Changing the Password for the Default Console User	288
Changing the Password for the Web Configuration Utility	288
Changing Database Passwords	288
Configuring a New Password on Collector Appliances	289
Editing Silo.Conf	290
Updating the master.system_settings_licenses Table	290
Changing the MySQL Root Password on Database Appliances	291
Recovering the Root MySQL Password	292
Recovering the MySQL SNMP User Account on Data Collector	293
Changing the MariaDB Password on SL1 Appliances	293
Changing the MariaDB Password in SL1 11.3.0 and Above	293
Changing the MariaDB Password in SL1 Versions Prior to 11.3.0	294
Changing the IP Address of an SL1 Appliance	297
Changing the IP Address on an All-In-One Appliance	298
Step 1. Stop the EM7 Service	298
Step 2. Change the IP Address in the silo.conf File	298
Step 3. Change the IP Address in the /etc/hosts File	298

Step 4. Change the IP Address in the Network Interface Configuration File	299
Step 5. Update the IP Address in the MySQL Database	301
Step 6. Reboot the Appliance	301
Step 7. Confirm the Change in SL1	301
Changing the IP Address on a Database Server	301
Step 1. Stop the EM7 Service	302
Step 2. Change the IP Address in the silo.conf File	302
Step 3. Change the IP Address in the /etc/hosts File	302
Step 4. Change the IP Address in the Network Interface Configuration File	303
Step 5. Update the IP Address in the MySQL Database	305
Step 5a: For Database Servers Configured with PhoneHome	305
Step 5b For Clustered Database Appliances (using HA, DR, or HA+DR)	307
Step 6. Reboot the Appliance	309
Step 7. Change the Database Appliance IP Address in the Administration Portals, Data Collect and Message Collectors	
Step 8. Confirm the Change in SL1	310
Changing the IP Address on a Data Collector or Message Collector	310
Using the Web Configuration Utility to Change the IP Address of a Data Collector or Message Collector	311
Using the Command Line to Change the IP Address of a Data Collector or Message Collector	312
Confirming the IP Address Change on the Appliance Manager Page	312
Changing Name Servers on an SL1 Appliance	313
Changing Name Servers on an SL1 Appliance	314
Installing Additional RPMs on an SL1 Appliance	315
Backup Management	316
Types of SL1 Backups	317
Configuration Backups	317
What Does a Configuration Backup Include?	318
Full Backups	319
What Does a Full Backup Include?	319
Disaster Recovery Backups	320
What Does a Disaster Recovery Backup Include?	320
The Workflow for Backing Up and Restoring SL1	320

Planning for SL1 Backups	321
Creating Backup Credentials	321
Creating an S3 Backup Credential	321
Creating a Basic/Snippet Backup Credential	322
Configuring Backups	323
Adding Files to Include in Configuration Backups	324
Viewing the Databases and Tables Included or Excluded from a Configuration Backup	324
Defining a Configuration Backup	325
Defining a Full Backup	327
Defining a Disaster Recover Backup	329
Mounting Backup Files	331
Mounting NFS Shares	331
Mounting SMB Shares	332
Restoring Backups	333
Restoring a Configuration Backup from an S3 Bucket	333
Restoring a Configuration Backup from a Remote NFS or SMB Share	335
Restoring a Full Backup from an S3 Bucket	337
Restoring a Full Backup from a Remote NFS or SMB Share	340
Restoring a DR Backup from an S3 Bucket	345
Restoring a DR Backup from a Remote NFS or SMB Share	348
Retaining Backups	349
Retaining Full Backups	350
Retaining DR Backups	350
Additional Configuration for Solaris NFS Remote Shares	351
Performing Configuration and Full Backups on the DR Database Server	351
Configuration Backup on a Disaster Recovery Database Server	352
Full Backup on a Disaster Recovery Database Server	352
Viewing License Data	354
Viewing License Information	354
Subscription Data	357
Ensuring Accurate Data	358
Viewing Subscription Usage	358

Current License Usage Totals	358
Historical License Usage Totals	359
Current License Totals	360
Viewing Delivery Status	361
Manually Uploading License Usage to ScienceLogic	362
Downloading the Daily License Usage File	362
Manually Uploading the Daily License Usage File to ScienceLogic	362
Uploading the ScienceLogic Receipt	363
Data Retention Settings for Licensing	363
CAC Authentication	365
Using CAC Authentication	367
Prerequisites	368
Importing SSL Certificates	369
Extracting the Common Name from a Certificate for Authentication	370
Defining the Client Certificate Chain	371
Verifying SSL Certificate File Import and Resolving Issues	373
Clearing the SL1 Cache and Restarting NGINX	374
Testing the Configuration	374
Troubleshooting CAC Authentication	375
Failed to Identify Personal Identity Verification (PIV) Card	376
Failed CAC Authentication After Disaster Recovery (DR) Failover	376
Failed CAC Authentication After Setting Up High Availability (HA)	376
Accessing the Appliance without CAC Authentication	377
Special Circumstance: Multiple Levels of Intermediate Certificates	377
Authentication Profiles and Resources	379
Authentication Profiles	380
Viewing the List of Authentication Profiles	380
Filtering the List of Authentication Profiles	381
The "default" Authentication Profile	382
Creating an Authentication Profile	383
Editing an Authentication Profile	385
Deleting One or More Authentication Profiles	385

Authentication Resources	385
Viewing the List of Authentication Resources	385
Filtering the List of Authentication Resources	386
The "EM7 Internal" Resource	388
Creating an LDAP/AD Authentication Resource	388
Creating an SSO Authentication Resource	394
Editing an Authentication Resource	398
Deleting an Authentication Resource	398
Installing an SSL Certificate	399
Using SSL Certificates	400
Certificates for ScienceLogic Servers	400
Requesting a Commercial SSL Certificate	400
Creating Your Own Certificate	402
Installing the Certificate on an SL1 Appliance	404
Managing Host Files	406
Viewing the List of Host Entries	407
Creating a New Host Entry	407
Editing a Host Entry	408
Using an Existing Host File Entry to Create a New Host File Entry (Save As)	408
Deleting One or More Host Entries	409

Chapter

1

Introduction

Overview

This manual describes the tasks that System Administrators who monitor and maintain the health of SL1 must perform, and the tools they can use to perform those tasks.

This chapter covers the following topics:

Who Should Read This Manual?	16
What's In This Manual?	16
Requirements	16

Who Should Read This Manual?

This manual is intended for System Administrators who must monitor and maintain the health of SL1.

This manual describes tasks on the **System** menu (the **[System]** tab in the classic user interface) that are related to the maintenance and monitoring of SL1. This manual also includes advanced tasks that are performed at the console or in an SSH session.

What's In This Manual?

This manual includes information on global settings, collector groups, upgrading SL1, health tasks, maintenance tasks, licensing, and tools for troubleshooting and debugging.

Requirements

To follow some of the steps listed in this manual, you must have administrator-level access to the console of your SL1 appliances.

Chapter

2

Global Settings

Overview

In SL1, global settings allow you to define default behavior that applies to all elements in the platform. For settings that affect devices, you can override global settings with device-level settings.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon
- To view a page containing all of the menu options, click the Advanced menu icon (---).

This chapter covers the following topics:

Global Settings for API	18
Global Settings for Appliances	19
Global Settings for Asset Automation	. 22
Global Settings for User Logins, Discovery, Data Collection, UI Features, and Expiration Warnings	23
Global Settings for Data Retention	38
Global Settings for Inbound Email and Outbound Email	45
Global Settings for Login Alert Messages	49
Global Settings for Password Reset Emails	49
Global Settings for Security	51
Global Settings for System Thresholds	51
Global Settings for Interface Thresholds	56
Settings in Silo.Conf	64
Disabling the User Interface on a Database Server	72

Global Settings for API

The **REST API Settings** page (System > Settings > API) allows you to define global parameters that affect the behavior of the REST API. When defined, these parameters affect all interaction with the API.

NOTE: This page is available only to administrator users.

To edit the settings in the REST API Settings page:

- 1. Go to the **REST API Settings** page (System > Settings > API).
- 2. In the **REST API Settings** page, edit the values in one or more of the following fields:
 - Internal Request Account. Specify the user account that allows SL1 to make API requests without a password.
 - **X-EM7-run-as Header Support**. Specifies whether administrator users can make API requests using the permissions of another user without that user's password. Choices are:
 - ° Disabled. Administrator users cannot make API requests using the permissions of another user.
 - Enabled (Admin only). Administrator users can include the X-EM7-run-as Header to make API requests using the permissions of another user.
 - Logging. Specifies which logs SL1 will write to when tickets are created or updated using the API.
 Choices are:
 - Transaction Logging Only (System Logs). If a ticket is created or updated using the API, SL1 will write the standard entry to the audit log that indicates a user performed a write-operation using the API. However, SL1 will not write to the ticket log for the ticket that was created or updated.
 - Normal (Ticket and System Logs). If a ticket is created or updated using the API, SL1 will write to the audit log and to the ticket log for the ticket that was created or updated.
 - X-EM7-suppress-logging Header Support. If Normal (Ticket and System Logs) is selected in the Logging field, this field specifies whether the X-EM7-suppress-logging header can be used when an administrator creates or updates a ticket using the API. If the X-EM7-suppress-logging header is used when creating or updating a ticket, SL1 will not write to the ticket log for the ticket that was created or updated. Choices are:
 - Disabled. The X-EM7-suppress-logging header cannot be used.
 - Enabled (Admin only). The X-EM7-suppress-logging header can be used to stop SL1 from writing to the ticket log for the ticket that was created or updated.
 - **Send Notification**. When a ticket is created or updated, SL1 can automatically send notification emails to the ticket assignee and ticket watchers. This option specifies the conditions under which SL1 will send notification emails when tickets are created or updated using the API. Choices are:

18 Global Settings for API

- ° Only if X-EM7-send-notification: 1 is sent. SL1 will send notification emails for a ticket only when the X-EM7-send-notification header is set to 1.
- Sent after every write operation. SL1 will send notification emails for every API request that creates or updates a ticket.
- 3. Click the [Save] button to save changes in this page.

Global Settings for Appliances

The **Appliance Manager** page (System > Settings > Appliances) provides for global appliance configuration and management for your entire system or stack. This includes collector group and load distribution, version information, license status, and other items that are important when you upgrade.

From the **Appliance Manager** page, you can also access the Web Configuration Utility for each ScienceLogic appliance by clicking the toolbox icon(), or you can access the database administration tool for each Database Server or All-In-One Appliance by clicking the gear icon ().

For each Database Server, Data Collector, and Message Collector, you can click on the magnifying-glass icon (
) to view the output of the system status script for that appliance.

During upgrade, table cells will highlight known, pending action items that must be done to successfully complete an upgrade, such as highlighting an SL1 appliance that is running a different version of SL1 than the Database Server.

This page is useful for ensuring that every Data Collector is assigned to a Collector Group before you begin an upgrade. In some cases, the Data Collector might be assigned to an empty Collector Group, if the collector is

You can also use this page to ensure that Data Collector load is near or below the system requirements for each collector.

To edit and view information about an SL1 appliance:

- 1. Go to the **Appliance Manager** page (System > Settings > Appliances).
- 2. Locate the SL1 appliance you want to edit. Click its wrench icon (*). The fields in the top pane are populated with values from the selected SL1 appliance.
- 3. You can edit one or more of the following fields:
 - Host Name. Name of the appliance.
 - IP Address. Primary IP address for the appliance.
 - Model Type/Module Type. Type of appliance. If an appliance is added with the wrong appliance type, SL1 generates a critical error to notify the user. The types include:
 - All In One Server
 - Database
 - Administration Portal

- Data Collection Unit
- Message Collection Unit

NOTE: The combination appliance with a Database Server and an Administration Portal on a single appliance will appear with *Module Type* of *Database*. The combination appliance with a Message Collection Unit and a Data Collection Unit will appear with *Module Type* of *Data Collection Unit*.

- Integration Server (SL1PowerFlow)
- **Description**. Description of the appliance.
- 4. You can edit two optional fields for Data Collector or Message Collector.
 - DB User. User name that can access the MariaDB database on the Data Collector or Message Collector.
 - **DB Password**. Password that allows access the MariaDB database on the Data Collector or Message Collector.

If you are using AWS RDS with your SL1 System, you must define the **DB User** and **DB Password** for each Data Collector or Message Collector.

NOTE: ScienceLogic recommends that you vary the Data Collector and Message Collector database credentials for enhanced per-appliance security. This greatly enhances the security of your central database by disallowing a successful attack to go unnoticed on your Data Collector and then succeed without failure on the central database.

The Appliance Manager page also displays the following columns:

- Collector Group. For Data Collectors and All-In-One Appliances, specifies the Collector Group
 associated with the appliance.
- ^o **Build**. Specifies the latest build installed on the appliance.

NOTE: If an SL1 appliance is running a different version of SL1 than the Database Server, the corresponding cell in the **Build** column will be highlighted.

- MariaDB. Specifies the version of MariaDB running on the All-In-One Appliance, Database Server, Data Collector, or Message Collector.
- ° Capacity. For Database Servers, specifies the licensed capacity of the appliance.
- Allocation. For Data Collectors, specifies the number of devices aligned with the appliance.

- *ID*. Unique numeric ID, automatically assigned by the platform to each appliance in the **Appliance Manager** page.
- Validated. Specifies whether the license is valid.
- Endpoint. SL1 Agent endpoint for the Gen 1 Agent.
- Needs Reboot?. Specifies whether the appliance requires reboot to add latest kernel or security updates. This column is updated every 30 minutes. Hover your mouse to determine why the reboot is required and information about kernel version, packages, and last reboot.
- Task Manager Paused? . Specifies whether the task manager service (em7) is paused. This value is updated every two minutes.
- Edit Date. Date the appliance's information was discovered or last edited.
- Edit User. User who last edited the appliance's information.
- ° Create Date. Date and time the appliance was registered and licensed.
- 5. To view the Web Configuration Utility for an appliance, where you can track license data, interfaces, and other device settings, click the Appliance Manager icon (). Use the same login credentials that you used to log into SL1, and close the pop-up window for the Utility when you are done.
- 6. If an SL1 appliance is running a different version of SL1 than the Database Server, that appliance is highlighted in the **Appliance Manager** page. The version number, if known, is listed in the **Build** column.
- 7. For all SL1 appliances, SL1 runs the system status script every 15 minutes. You can click the logs icon (to view the results of the latest system status script.
- 8. If you are logging in to the "sl1admin" account on an appliance, you can click the padlock () icon for that appliance to get a one-time password. For more information, see "Using the sl1admin Account" in the Role-Based User Accounts chapter of the **Organizations and Users** manual.
- 9. For Database Servers, you can click the gear icon (*) to access the phpMyAdmin interface for the Database Server. In this interface, you can view all the database tables on the Database Server.
- 10. For Data Collectors and Message Collectors, you can click the lightning bolt icon () to manually force the Database Server to send the latest configuration information.

NOTE: The bomb icon () does not appear for Database Servers that are not configured for High Availability or Disaster Recovery. The bomb icon does not appear for Database Servers that are configured as the primary database in a High Availability or Disaster Recovery configuration.

11. Click the **[Save]** button to save any changes. Click the **[Save As]** button to save your changes to a new appliance name.

The Web Configuration Utility


The Web Configuration Utility allows you to configure system-level settings for your appliances. Each appliance includes access to the Web Configuration Utility.

The Web Configuration Utility adds an additional layer of security to SL1 by segregating administrative functions from the rest of the user interface and by exposing system-level settings and diagnostic tools that might otherwise require command-line access to the appliance. The Web Configuration Utility can be accessed only through an HTTPS connection and requires its own administrator-level password.

Perform the following steps to log in to the Web Configuration Utility:

- 1. You can log in to the Web Configuration Utility using any web browser supported by SL1. The address of the Web Configuration Utility is in the following format:
 - https://ip-address-of-appliance:7700
- 2. Type the address of the Web Configuration Utility into the address bar of your browser, replacing "ipaddress-of-appliance" with the IP address or public-facing fully qualified hostname of the appliance.
- 3. You will be prompted to type your username and password. Log in as **em7admin** with the appropriate password. After logging in, the main **Configuration Utility** page appears:

NOTE: For better security, change your Web Configuration Utility credentials. If you leave your Web Configuration Utility credentials as the stock credentials, you greatly increase the risk that your central database could be attacked, or that you could be locked out of the Web Configuration Utility.



- 4. In the **Configuration Utility**, you can license a SL1 appliance, configure interfaces, and edit settings for the SL1 appliance and the Database Server if applicable.
 - For details on using the Configuration Utility to license a SL1 appliance, see the manual Installation and Initial Configuration.
 - For details on using the Configuration Utility to inform Data Collectors, Message Collectors, and Administration Portals when you change the IP address of a Database Server, see the section on Changing IP Addresses.

Global Settings for Asset Automation

The **Asset Automation** page (System > Settings > Assets) allows you to define the default behavior for all asset records.

For each standard asset field, you can specify:

- Whether the field can be automatically populated by SL1.
- Whether the field's value should be automatically updated by SL1.
- Whether or not SL1 should generate an event if the field's value changes.

You can define the default behavior for each standard field in the following asset pages:

- Asset Properties
- Asset Maintenance & Service
- Asset Configuration
- Asset Licenses
- Asset IP Networks
- Asset Components

The defined behavior will be applied to every asset record in SL1.

For more details on asset records and enabling automation for asset records, see the manual **Asset Management and Vendors**.

Global Settings for User Logins, Discovery, Data Collection, UI Features, and Expiration Warnings

To define or edit the settings in the **Behavior Settings** page:

- 1. Go to the **Behavior Settings** page (System > Settings > Behavior).
- 2. On the **Behavior Settings** page, edit the values in one or more of the following fields:
 - Interface URL. URL for accessing the user interface. This value should be in URL format and can be up to 64 characters in length. Do not include a trailing forward slash ("/") at the end of the Interface URL. When SL1 generates URLs for tickets or events (for example, in email messages), the trailing forward slash will be automatically included.
 - Require TLS Validation for Gen 0 Agent checkbox. When this checkbox is selected, Gen 0 agents that operate outside of the Extended Architecture will require TLS validation to upload data.

NOTE: To enable this validation, all Data Collectors and Message Collectors that will ingest agent data must have a valid and signed TLS certificate.

- Password Expiration. Specifies whether or not the password for a user account will expire and if so, when the password will expire. Choices are:
 - Disabled. Passwords do not expire or are managed externally to SL1.
 - ° 30 Days. Passwords will expire after 30 days.

- 60 Days. Passwords will expire after 60 days.
- 90 Days. Passwords will expire after 90 days.
- ° 180 Days. Passwords will expire after 180 days.
- Password Reset Interval. The minimum amount of time that must pass before a user can change a password. For example, if the value in this field is 2 Hours, a user can change a password every two hours. This applies to users changing their own passwords and administrators changing other users' passwords. Values range from 1 hour to 24 hours, in increments of one hour.
- Password Hash Method. Specifies how user passwords will be encrypted for storage in the ScienceLogic database. You can choose the hashing algorithm that works best for your enterprise. Choices are:
 - ° SHA-512. AS of 10.2.0, this is the default value. Previous passwords will use their previous hash method until the password is changed.
 - Automatic (PHP Password API)
- **Password Minimum Length**. Specifies the minimum number of alphanumeric characters allowed for the password. You can specify any value from 1 to 99. The default value is "8" characters.
- User Login Session Timeout. Select the amount of idle time that can pass without any user activity before that user's SL1 session expires. For better security, use a shorter time frame. By default, user sessions expire after 10 minutes of inactivity.
- Account Lockout Type. If a user enters incorrect login information multiple times in a row, that user
 will be locked out of the user interface. In this field, you can select how the lockout will be applied.
 Choices are:
 - Lockout by IP Address. All subsequent login attempts from the IP address will be denied once a lockout for that IP address has been identified. Use this option to isolate all access from the remote IP address for any account until a system administrator has validated the lockout and cleared it.
 - Lockout by Username and IP Address. All subsequent login attempts by this username from the IP address will be denied. This will permit other users from the same IP address to continue to access the system as long as they are not locked out.
 - Lockout by Username (default). All subsequent login attempts by this username from any IP address will be denied
 - Disabled. Lockouts are disabled. This setting can leave your system vulnerable to attacks and as such, it is not recommended.
- Account Lockout Attempts. Number of times a user can enter incorrect login information before a lockout occurs. Choices are 1 time through 10 times.
- Login Delay. To prevent unauthorized users from using brute-force login attempts, you can set a login delay in this field. After each failed login, SL1 will not allow another attempt for the number of seconds specified in this field. Choices are:

- Disabled. SL1 does not enforce a delay between failed logins.
- ^o 1 Second. After a failed login, SL1 will not allow another attempt for one second.
- ^o 2 seconds. After a failed login, SL1 will not allow another attempt for two seconds.
- 4 seconds. After a failed login, SL1 will not allow another attempt for four seconds.
- 8 seconds. After a failed login, SL1 will not allow another attempt for eight seconds.
- Single Instance Login (Admins). Specifies whether more than one instance of a single username can be logged in to the user interface at the same time. Defines the default behavior for users of account type "Administrator". You can specify the following types of behavior:
 - Disabled. Multiple instances of the same account name can be logged in to the user interface. There are no requirements or limitations on any of the instances. None of the instances will be automatically logged out.
 - Session can be transferred after. If you select one of these options, the second instance of a user account can log in only after the first instance of the account is inactive. In SL1, an account is considered "inactive" if the user has not performed any tasks or navigated within the user interface. You can specify how long the first instance must be inactive before the second instance can log in. When the second instance successfully logs in to the user interface, the browser where the first instance is logged in will display the following message: "User id 'account name' logged in from a different browser and transferred this session."

NOTE: If this field is set to any value other than disabled, you can still override an earlier instance. If you try to log in to the user interface and there is another instance of the account already logged in to the user interface, the login page will display the following message: "User id 'account name' is already logged in to the system. To transfer the session, check 'Transfer Session' and log in."

- If you select the *Transfer Session* checkbox, this logs the first instance out of the user interface and allows the second instance to log in to the user interface. The browser where the first instance was logged in will display the following message: "User id 'account name' logged in from a different browser and transferred this session."
- Other (manual entry). Allows you to enter a custom value, in seconds. When the first instance of a user account is inactive in the user interface for the specified number of seconds, the first instance is logged out and the second instance is allowed.

NOTE: To support single instance login in the current SL1 user interface ("AP2"), you must make the appropriate settings in this field and then perform additional steps. For more information, see the section on Configuring Single Instance Login in AP2.

- Single Instance Login (Users). Specifies whether more than one instance of a single username can be logged in to the user interface at the same time. Defines the default behavior for users of account type "User". You can specify the following types of behavior:
 - Disabled. Multiple instances of the same account name can be logged in to the user interface. There are no requirements or limitations on any of the instances. None of the instances will be automatically logged out.
 - Session can be transferred after. If you select one of these options, the second instance of a user account can log in only after the first instance of the account is inactive. In SL1, an account is considered "inactive" if the user has not performed any tasks or navigated within the user interface. You can specify how long the first instance must be inactive before the second instance can log in. When the second instance successfully logs in to the user interface, the browser where the first instance is logged in will display the following message: "User id 'account name' logged in from a different browser and transferred this session."

NOTE: If this field is set to any value other than disabled, you can still override an earlier instance. If you try to log in to the user interface and there is another instance of the account already logged in to the user interface, the login page will display the following message: "User id 'account name' is already logged in to the system. To transfer the session, check 'Transfer Session' and log in."

- If you select the *Transfer Session* checkbox, this logs the first instance out of the user interface and allows the second instance to log in to the user interface. The browser where the first instance was logged in will display the following message: "User id 'account name' logged in from a different browser and transferred this session."
- Other (manual entry). Allows you to enter a custom value, in seconds. When the first instance of a user account is inactive in the user interface for the specified number of seconds, the first instance is logged out and the second instance is allowed.

NOTE: To support single instance login in the current SL1 user interface ("AP2"), you must make the appropriate settings in this field and then perform additional steps. For more information, see the section on **Configuring Single Instance Login in AP2**.

- Account Lockout Duration. Specifies how long a user will be locked out of the user interface. Choices are 1 hour 24 hours, in one hour increments. The shorter the duration, the sooner the system is again vulnerable to a potential attack; however, a shorter duration will also allow a user to attempt to log in again without the help of a system administrator.
- Lockout Contact Information. This contact information will be displayed when a user is locked out of the user interface. Can be any combination of alphanumeric characters, up to 255 characters in length. This information should allow the user to contact his/her administrator to unlock the account.
- Login Header Title. HTML title of the login page. This text will appear at the very top of the browser on the login page.

- **System Identifier**. Unique name for the current SL1 system. Can be up to 128 characters in length. This field is useful for companies or organizations with multiple SL1 systems. If a value is provided in this field, SL1 will include a "system identifier" value in each event generated by the current SL1 system. This allows users to easily determine the source SL1 system associated with the event.
- Ping & Poll Timeout (Msec.). This field specifies the number of milliseconds the discovery tool or
 availability polling will wait for a response after pinging a device. After the specified number of
 milliseconds have elapsed, the poll will timeout. The choices are between 100 and 5000
 milliseconds.
- **SNMP Poll Timeout (Msec.)**. This field specifies the number of milliseconds the discovery tool will wait for a response after sending an SNMP query to a device. After the specified number of milliseconds have elapsed, the SNMP poll will timeout. The choices are between 100 and 5000 milliseconds.
- **SNMP Failure Retries**. This field specifies the number of times the discovery tool will try to communicate with a device after a timeout or failure. After that number of times has been met, the discovery tool will not retry unless the user manually restarts the discovery process. The choices are 0–6.
- Initially Discovered Interface Poll Rate. This field specifies the frequency with which SL1 will poll
 newly discovered interfaces. This setting does not affect interfaces that have been previously
 discovered with a different value in this field or interfaces for which the Frequency field has been
 manually edited in the Interface Properties page.
- DHCP Community Strings (Comma separated). SNMP "read only" community string to use during discovery. This is required only if DHCP servers and devices use a different SNMP community string than other devices in the network. If the community string specified in the Discovery Control Panel page (System > Manage > Classic Discovery) does not work for DHCP devices, SL1 will automatically use the community string specified in this field.
- Strip FQDN From Inbound Email Device Name. In Events from Email policies, specifies how SL1 will match the regular expression for device name. Choices are:
 - Enabled. SL1 will search the text string in the incoming email and match all characters up to the first period that appears in the text string. If multiple devices match the characters up to the first period (for example, my_device.1 and my_device.2), SL1 will align the event with the matching device with the highest Device ID.
 - Disabled. SL1 will search the text string in the incoming email for a match for the device name. The text string must include an exact match to the regular expression (defined in the Events from Email policy), including any text following a period in the device name. If SL1 does not find an exact match in the incoming email, SL1 creates an entry in the system log.
- Inbound Email Alert Message. In each event policy, the First Match String and Second Match
 String fields specify the string or regular expression used to correlate the event with a log message.
 To trigger an event, the text of a log message must match the value in the First Match String and
 Second Match String fields in that event's policy. For Events from Email policies, this field specifies
 whether only the email message body will be written to the device log or whether both the email
 message subject and email message body will be written to the device log. Choices are:

- Email Message Body Only. Only the email message body is written to the device log. The First
 Match String and Second Match String fields can examine and match only the email message
 body.
- Email Message Subject and Body. Both the email message body and the email message subject are written to the device log. The *First Match String* and *Second Match String* fields can examine and match against both the email message body.

NOTE: The global setting *Inbound Email Alert Message* affects how events are triggered.

This field does not affect the *Regex Pattern* field in the Event from Email policy. The *Regex Pattern* field in an Event from Email policy specifies which device log to write to.

- Event Console Ticket Life Ring Button Behavior. Specifies how the life-ring icon () in the Event Console will behave. Choices are:
 - Create/View EM7 Ticket. When you click the life-ring icon () for an event in the **Event Console**, SL1 will display the **Ticket Editor** page, where you can define a ticket and automatically associate it with the selected event. This is the default behavior.
 - Create/View External Ticket. If an external ticket is aligned with an event, when you click the life-ring icon () for that event (from the **Event Console**), SL1 spawns a new window and displays the external ticket (as specified in the **force_ticket_uri** field). If an external ticket is not yet aligned with an event, when you click the life-ring icon () for that event, SL1 sets a "request" flag for the ticket and displays an acknowledgment that a new ticket has been requested. You can then use the "request" in run book logic, to create the ticket on the external system.

CAUTION: If you select Create/View External Ticket in the Event Console Ticket Life
Ring Button Behavior field, you can no longer create tickets from the
Event Console.

- Automatic Ticketing Emails. Specifies whether ticket watchers will automatically receive email notification when a ticket is created or changes status. Choices are:
 - Enabled. This is the default value. When you select this option, SL1 automatically sends email notifications to all watchers when a ticket is created, assigned, or updated.
 - Disabled. When you select this option, SL1 does not automatically send email notifications to all watchers when a ticket is created, assigned, or updated.

- **Prevent Browser Saved Credentials**. This checkbox specifies whether SL1 will allow the browser to cache login credentials and perform auto-complete in the login page. By default, the user interface will allow browsers to cache login credentials. Choices are:
 - Selected. The user interface will not allow browsers to cache credentials and use auto-complete in the login page. Use this setting to comply with PCI DSS and other security protocols.
 - Not Selected. This is the default setting. The user interface will allow browsers to cache credentials and use auto-complete in the login page. The implementation of this functionality varies between browsers.
- **Prevent Loading Interface in External Frames**. If you select this checkbox, other pages cannot be loaded in external frames in the same browser session that includes SL1. This is a security measure, to prevent click-jacking attacks.
- Hide Perpetual License Count. Specifies whether to display the device count graph in the System
 Usage page (System > Monitor > System Usage). The default behavior is to hide the graph in the
 System Usage page. Users might find this graph useful to troubleshoot licensing issues. For a
 description of the System Usage page, see the Monitoring Overall System Usage and
 Statistics section.
- Hide "New" button on the Ticket Editor. If you select this checkbox, the Ticket Editor page will not display the [New] button. This field is unselected by default.
- Enable Unique Asset Tag to Organization Constraint. Select this option if you want to prevent an asset from being moved to another organization if the new organization is already aligned to an asset with the same Asset Tag. Do not select this option if you want to allow assets with the same Asset Tags in the same organization. This field is selected by default.
- Display Previous Login In Footer. If you select this checkbox, the user interface will display information about the last successful login to the user interface and the last failed login (if applicable). The user interface will display the following in the lower right of the page:

 Previous Login: yyyy-mm-dd hh-mm-ssfrom user's IP address.

Failed Login: yyyy-mm-dd hh-mm-ssfrom user's IP address.

- Ignore trap agent-addr varbind. If you select this checkbox, SL1 will align incoming SNMP trap messages with the forwarding device (last hop) instead of searching for the IP address of the originator of the trap.
- Enable Selective PowerPack Field Protection. If you select this checkbox, the following fields will **not** be updated when you update a PowerPack:
 - Event Policy > Operational State
 - Event Policy > Event Severity
 - Event Policy > Event Message
 - Event Policy > Occurrence Count
 - Event Policy > Occurrence Time

- Event Policy > Expiry Delay
- Event Policy > Detection Weight
- Event Policy > External Event ID
- Event Policy > External Category
- Event Policy > Use multi-match
- Event Policy > Use message-match
- Event Policy > Topology Suppression
- Dynamic Application > Properties > Operational State
- Dynamic Application > Properties > Poll Frequency
- Dynamic Application > Properties > Disable Data Rollup
- Dynamic Application > Collection > Custom Attribute
- Dynamic Application > Collection > Asset / Formlink
- Dynamic Application > Collection > Change Alerting
- Dynamic Application > Collection > Hide Object
- Dynamic Application > Presentation > Active State
- Dynamic Application > Threshold > Override Threshold Value
- Dynamic Application > Threshold > Numeric Range: High
- Dynamic Application > Threshold > Numeric Range: Low
- Dynamic Application > Threshold > Threshold Value
- Device Class > Device Dashboard
- Hide "Create a Ticket" in Toolbox menu. If you select this checkbox, the Toolbox menu (three stacked horizontal lines in the upper-left corner in the classic user interface) will not display the Create a Ticket option. This field is unselected by default.
- **Hide "other" filesystem types**. If you select this checkbox, file systems of type "other" (which includes XFS file systems) will not be discovered and monitored. This checkbox is selected by default.
- **Enable CDP Topology**. If selected, SL1 will use Cisco Discovery Protocol (CDP) for each device that supports CDP. SL1 will then generate topology maps from the discovered CDP relationships.

NOTE: CDP is a proprietary protocol developed by Cisco and is not supported by all network hardware. If your network includes both CDP enabled and non-CDP network switches and routers, the topology data reported by the CDP enabled devices might not be accurate. In SL1, if a conflict exists between the collected CDP topology data and the collected layer-2 topology data, the CDP topology data takes precedence. In some cases, the ScienceLogic layer-2 data might be more accurate. Therefore, if your network includes both CDP enabled and non-CDP network switches and routers, you might want to disable CDP topology collection. For details, see the *Views* manual.

Enable LLDP Topology. If selected, SL1 will use Link Layer Discovery Protocol (LLDP) for each device
that supports LLDP. SL1 will then generate topology maps from the discovered LLDP relationships.

IMPORTANT: Enabling a discovered device configured with CDP or LLDP topology in SL1 will cause the device to provide information on its neighbor. This information only identifies that there is a neighbor device, not which is the parent or the child. This may cause the parent-child relationship to switch which requires you to manually reverse the issue within the SL1 user interface. SL1 allows you to manually build parent-child relationships between specific device categories. For more information, see *Defining Parent and Child Devices* in the *Events* manual.

- Enable Community String Indexing (VLAN Topology). If selected, SL1 will perform discovery of VLANs during topology collection. By default, this option is not selected because the SNMP requests used to discover VLANs might cause some types of hardware to erroneously reboot.
- **Default Country**. Specifies the country that will be selected by default in each page where the user specifies a country. The user can override this default value in each page.
- **System Timezone**. Specifies the default timezone for SL1. In each page where the user can select a timezone, this value will be selected by default. The user can override this default value in each page. SL1 also uses this default value to perform timezone conversions when no user timezone setting is available. For example, if SL1 sends an email to an address not associated with a user, any timestamps contained in the email will use the value from the **System Timezone** field. You can select from a list of all timezones. The default value is "UTC".
- **NFS Detection Disable**. If selected, this checkbox prevents SL1 from monitoring and reporting on NFS "shared" file systems. SL1 will monitor and report only on local file systems.
- Port Polling Type. Specifies how SL1 should poll devices to discover open ports. The choices are:
 - Half Open. Uses a faster TCP/IP connection method and does not appear on the device's logs.
 - Full Connect. Uses the standard TCP/IP connection to detect open ports.
- Initial Discovery Scan Level. Specifies the data to be gathered during the initial discovery session. You can override this setting for a single discovery session in the Discovery Session Editor modal page. The options are:

- O. Model Device Only. Discovery tool will discover if device is up and running and if so, collect the make and model of the device. SL1 will then generate a device ID for the device, so it can be managed by SL1.
- 1. Initial Population of Apps. Discovery tool will search for Dynamic Applications to associate with the device. Discovery tool will attempt to collect data for the aligned Dynamic Applications. Discovery will also perform 0. Model Device Only discovery.
- ^o 2. Discover SSL Certificates. Discovery tool will search for SSL certificates and retrieve SSL data. Discovery tool will also perform 1. Initial Population of Apps and 0. Model Device Only.
- 3. Discover Open Ports. Discovery tool will search for open ports. Discovery tool will also perform 2. Discover SSL Certificates, 1. Initial Population of Apps, and 0. Model Device Only. If your system includes a firewall and you select 3. Discover Open Ports, discovery might be blocked and/or might be taxing to your network.
- 4. Advanced Port Discovery. Discovery tool will search for open ports, using a faster TCP/IP connection method. Discovery tool will also perform 2. Discover SSL Certificates, 1. Initial Population of Apps, and 0. Model Device Only. If your system includes a firewall and you select 4. Advanced Port Discovery, some auto-discovered devices might remain in a pending state (purple icon) for some time after discovery. These devices will achieve a healthy status, but this might take several hours.
- 5. Deep Discovery. Discovery tool will use nmap to retrieve operating system name and version. Discovery will also scan for services running on each open port and can use this information to match devices to device classes. Discovery tool will search for open ports, using a faster TCP/IP connection method. Discovery tool will also perform 2. Discover SSL Certificates, 1. Initial Population of Apps, and 0. Model Device Only. For devices that don't support SNMP, option 5. Deep Discovery allows you to discover devices that don't support SNMP and then align those devices with a device class other than "pingable".

CAUTION: Option 5. Deep Discovery is compute-intensive and might significantly tax your network if used as the default setting. ScienceLogic recommends that you use this option on a per-discovery basis by selecting it in the **Discovery Session Editor** page.

Rediscovery Scan Level (Nightly). Specifies the data to be gathered/updated each night during
auto-discovery. The auto-discovery process will find any changes to previously discovered devices
and will also find any new devices added to the network. The options are the same as for Initial
Discovery Scan Level.

TIP: ScienceLogic recommends that you delete all unused PowerPacks from your SL1 system to improve the performance of the nightly auto-discovery process.

- Discovery Scan Throttle. Specifies the amount of time a discovery process should pause between
 each IP address or hostname in a discovery session. (You specify the list of IP addresses or hostnames
 for a discovery session in the IP Address/Hostname Discovery List field in the Discovery Session
 Editor page.) Pausing discovery processes between IP addresses or hostnames spreads the amount
 of network traffic generated by discovery over a longer period of time. The choices are:
 - Disabled. Discovery processes will not pause.
 - 1000 Msec to 10000 Msec. A discovery process will pause for a random amount of time between half the selected value and the selected value.
- Port Scan All IPs. Specifies whether SL1 should scan all IP addresses on a device for open ports. You
 can override this setting for a single discovery session in the Discovery Session Editor modal page.
 The choices are:
 - O. Disabled. SL1 will scan only the primary IP address (the one used to communicate with SL1) for open ports.
 - ° 1. Enabled. SL1 will scan all discovered IP addresses for open ports.
- **Port Scan Timeout**. Length of time, in milliseconds, after which SL1 should stop trying to scan an IP address for open ports and begin scanning the next IP address (if applicable). You can override this setting for a single discovery session in the **Discovery Session Editor** modal page. Choices are between 60,000 and 1,800,000 milliseconds.
- Restart Windows Services (Agent required). Specifies whether SL1 should automatically restart
 failed Windows services that have been defined on the device with a startup type of "automatic". To
 use this feature, the managed device must be running the agent SNMP Informant, WMI Edition. For
 assistance or information on purchasing and installing this agent, please contact ScienceLogic. Users
 must also supply a value in the SNMP Write field in the Device Properties page for the device. The
 choices are:
 - ° 0. Disabled. SL1 will not automatically restart failed Windows services that have been defined on the device with a startup type of "automatic".
 - 1. Enabled. SL1 will automatically restart failed Windows services that have been defined on the device with a startup type of "automatic".
- Hostname Precedence. Specifies which name SL1 will use for each discovered device. Choices are:
 - SNMP System Name. Use the device name specified in the device's SNMP System MIB. If SNMP System Name is selected and SL1 cannot find an SNMP name for the device, SL1 will assign the name returned by the DNS Reverse Lookup. If SL1 cannot find a DNS Reverse Lookup name for the device, SL1 will use the device's Admin Primary IP address as the device name in SL1.
 - DNS Reverse Lookup. Use the device name specified in the device's reverse-lookup record.

- Event Interface Name Format. Specifies the format of the network interface name that you want to appear in events. If you selected Interface Alias for the deprecated Interface Name Precedence field in a previous release of SL1, the format for existing interfaces is set to {alias}. If you selected Interface Name for the deprecated Interface Name Precedence field in a previous release of SL1, the format for existing interfaces is set to {name}. The default format is {name}. You can use a combination of string text and the following tokens to define the interface name format for events, such as string_{name}, string_{alias}, {name}{alias}, or {ifdesc}:
 - ° {alias}
 - ° {name}
 - ° {state}
 - ° {ifdescr}
 - ° {if id}
 - ² {did}
 - ° {ifindex}
 - ° {ifphysaddress}
 - {iftype}
 - {ifspeed}
 - ° {ifhighspeed}
 - ° {ifoperstatus}
 - ° {ifadminstatus}
- **DNS Hostnames**. If SL1 will use the DNS Reverse Lookup name as the device name (see the description of the field **Hostname Precedence**), this field specifies whether SL1 will use the fully-qualified domain name or only the hostname for each discovered device. Choices are:
 - Strip Device Name (Hostname). SL1 will use only the device name as the DNS hostname for each device.
 - Use Full Domain Name (FQDN). SL1 will use the fully-qualified domain name as the device name for each device.
- Event Clearing Mode. Describes how clearing an event will affect correlated events. Choices are:
 - ° Clear Selected Only. Clear only the selected events. If a parent event is cleared, the previously suppressed child events will appear in the Event Console.
 - ° Clear All in Group. When parent event is cleared, all child events correlated with parent event will be cleared. This is the default behavior.

- Maintenance Minimum Severity. Specifies the minimum severity required for an event to be suppressed during device maintenance and user maintenance for devices. The default value is Healthy, which causes all events to be suppressed. Choices are Healthy, Notice, Minor, Major, or Critical.
- Patch Maintenance Minimum Severity. If you schedule Device Maintenance and have defined a
 Patch Window within the larger maintenance interval, this field allows you to specify the event
 severity that will trigger the beginning of the Patch Window. The first event that both matches the
 severity in this field and occurs within the larger maintenance window triggers the start of the Patch
 Window. Choices are Healthy, Notice, Minor, Major, or Critical.
- **SSL Certificate Expiry Soon**. Specifies, in number of days, when SL1 should generate an event for an SSL Certificate that is about to expire. The choices range from 1 day to 9 months.
- **SSL Certificate Expiry Imminent**. Specifies, in number of days, when SL1 should generate a more urgent event for an SSL Certificate that is about to expire. The choices range from 1 day to 9 months.
- Asset Warranty Expiry. Specifies, in number of days, when SL1 should generate an event for an asset warranty that is about to expire. The choices range from 1 day to 9 months.
- **Domain Name Expiry**. Specifies, in number of days, when SL1 should generate an event for a domain's registration that is about to expire. The choices range from 1 day to 9 months.
- Validate Phone Number. Specifies whether or not phone numbers entered into the user interface must be in US format. Choices are:
 - ^o Disabled. Phone numbers are not required to be in US format.
 - ° Enabled. Phone numbers must be in US format.
- Dashboard Maximum Series Count Per Widget. This field allows you to select the maximum number of time-series lines that can appear in a single Multi-series Performance widget. Choices are 8–25. Increasing this setting might cause longer load times in the [Dashboards tab] page.
- Responder API Base URL. This field lets you update the Responder API Base URL, which is required if you want to align PowerShell Dynamic Applications to the agent. In SL1 version 11.2.0 and later, SL1 completes this field for you.
- Component Device Map Update Mode. This field specifies how SL1 rebuilds relationships between component devices that are created by Dynamic Applications (DCM-R). Choices are:
 - [Periodic]. (Default). A rebuild of the component device map occurs at a set interval, which is defined in the **DCM+R Rebuild** process (System > Settings > Processes). By default, the process runs every five minutes. Note that the Operating State for the **DCM+R Rebuild** process must be set to "Enabled" before periodic component device map updates will work. For more information, see **Viewing Information About ScienceLogic Processes**.
 - DCM-R Triggers. A rebuild of the component device map occurs immediately after topology changes are registered.

CAUTION: Setting the Component Device Map Update Mode to "DCM-R Triggers" might impact your system if your environment has large topology trees or if the environment experiences frequent simultaneous topology changes.

- Enable CBQoS Collection. If selected, SL1 will collect configuration data about Class-Based Quality-of-Service (CBQoS) from interfaces that are configured for CBQoS. If selected, you can enable collection of CBQoS metrics per-interface. The collected CBQoS metrics are displayed in Device Performance reports associated with the device that contains those interfaces. This setting is disabled by default. (For more information about Device Performance reports, see the manual Monitoring Device Infrastructure Health.)
- Enable Variable Rate Interface Counters. If selected, enables more accurate collection of data from interfaces. If enabled, when SL1 retrieves data from an interface, that data is stored in the ScienceLogic database along with the timestamp associated with the exact collection time. Before normalization occurs, SL1 applies an interpolation function that spaces the data at regular time intervals. For example, suppose you have specified that SL1 should collect interface data every five minutes. However, due to network traffic across the Data Collectors, SL1 might collect data from an interface at 13:01 and then 13:05. Because the ScienceLogic normalization process expects data that has been collected every five minutes, SL1 first applies an interpolation to the data to prepare the data for normalization. With Enable Variable Rate Interface Counters enabled, graphing interpolates between two collected data points without a limit of the distance between those data points. However, performance graphs will not display interpolation between two points where there is no supporting collected data, or "data gap", for a collection time when this feature is disabled.
- Enable Concurrent SNMP Collection. If selected, enables Concurrent SNMP Collection for all SNMP collection. Concurrent SNMP Collection allows multiple collection tasks to run at the same time with a reduced load on Data Collectors. Concurrent SNMP Collection also prevents missed polls and data gaps because collection will execute more quickly. For details see the manual SNMP Dynamic Application Development..

NOTE: If the "Data Collection: SNMP Collector" process is disabled on the **Process Manager** page (System > Settings > Admin Processes), the **Enable Concurrent**SNMP Collection option is disabled.

NOTE: Concurrent SNMP Collection is not available in military unique deployments (MUD) or STIG-compliant deployments.

• Enable Concurrent Network Interface Collection. If selected, enables asynchronous concurrent SNMP collection for all network interfaces. This provides better scalability for large networks by allowing multiple collection tasks to run at the same time with a reduced load on Data Collectors.

- New UI Default. Starting with SL1 11.1.0, the new SL1 user interface ("AP2") is the default user interface. If you want to make the classic user interface the default interface, de-select this option. If your 11.1.0 SL1 system was installing using an ISO, the SL1 user interface is set as the default, but if your SL1 system was upgraded with a patch, the classic user interface will still be set as the default user interface.
- Include PowerPack Sensitive Fields. If selected, lets you include sensitive fields when sharing a PowerPack. These sensitive fields include passwords and SSH keys.
- Prefer Global Device Summary Dashboard Over Category/Class. If you select this checkbox, the
 global default device dashboard will be displayed as the default in the Device Summary page
 instead of the device dashboard assigned to the device category or device class of the device. For
 more information about device dashboards, see the Dashboards manual.
- Enhanced OID Translation. If selected, ensures that varbind OIDs that use multi-dimensional indexes are translated correctly. The symbolic translation of the known portion of the OID is included in the log message associated with the trap. Enabling the Enhanced OID Translation option might affect performance on large environments with a large number of traps.
- Enable Concurrent PowerShell Collection. If selected, enables concurrent PowerShell collection for all PowerShell collection, which allows multiple collection tasks to run at the same time with a reduced load on Data Collectors.

NOTE: If the "Data Collection: PowerShell Collector" process is disabled on the **Process**Manager page (System > Settings > Admin Processes), the **Enable Concurrent**PowerShell Collection option is disabled.

NOTE: Concurrent PowerShell Collection is not available in military unique deployments (MUD) or STIG-compliant deployments.

- Report Size Estimation. If selected, enables the Row Count Estimate field for custom reports on the Run Report page (Reports > Run Report). This field provides an estimate of the number of rows that will appear in the report before SL1 generates the report. The estimate changes based on the selections you make for the report. You can use this field to manage the size of the generated report by adding or removing items from the report as needed.
- 3. Click the [Save] button to save changes in this page.

Configuring Single Instance Login for AP2

The **Single Instance Login** fields on the **Behavior Settings** page enable you to specify whether more than one instance of a single username can be logged in to the user interface at the same time.

In the classic SL1 user interface, you can configure single instance login using just those fields. However, for the current SL1 user interface ("AP2"), you must complete several additional steps.

To configure single instance login in AP2:

- 1. Go to the **Behavior Settings** page (System > Settings > Behavior).
- 2. Make the appropriate selections in the **Single Instance Login (Admins)** and **Single Instance Login (Users)** fields, and then click [Save].
- 3. Either go to the console of the SL1 Database Server or use SSH to access the SL1 All-In-One Appliance.
- 4. Log in as user **em7admin**.
- 5. At the command line, open the nextui.env file in the vi editor:

```
sudo vi /opt/em7/nextui/nextui.en
```

- 6. Un-set the environment variable AUTH CACHE=300000 by adding # as a prefix to that line.
- 7. Save and exit the nextui.env file.
- 8. Restart the nextui server:

sudo systemctl restart nextui

Global Settings for Data Retention

The **Data Retention Settings** page (System > Settings > Data Retention) allows you to define parameters for log and data retention.

These settings apply to all logs and all collected data. However, you can override these system settings on a case-by-case basis. For example, you can define data-retention thresholds for a device in the **Device Thresholds** page. The settings you define for the specific device override the settings in the **Data Retention Settings** page.

NOTE: For details on data roll-up and data normalization, see Normalization and Roll-Up of Performance Data.

From the **Data Retention Settings** page, you can edit how long the platform stores log entries and collected data. To edit the settings for data retention:

- 1. Go to the **Data Retention Settings** page (System > Settings > Data Retention).
- 2. On the **Data Retention Settings** page, you can drag sliders to change the value of each field or manually enter values in the fields to the right of the sliders. You can edit the value for one or more of the following fields:
 - Audit Logs. Number of months to retain log entries in the Audit Logs page (System > Monitor >
 Audit Logs). Log entries that are older than the specified number of months are automatically
 deleted. The default value is 3 months.
 - Event Logs. Number of days to retain event logs. Event history data is used to generate the Event Overview page (System > Monitor > Event Overview). Log entries that are older than the specified number of months are automatically deleted. The default value is 3 months.

- Access Logs. Number of months to retain log entries in the Access Sessions page (System > Monitor > Access Logs). Log entries that are older than the specified number of months are automatically deleted. The default value is 12 months.
- System Logs. Number of days to retain log entries in the System Logs page (System > Monitor > System Logs). Log entries that are older than the specified number of days are automatically deleted. The default value is 31 days.
- Collection Unit Data Buffer. Number of days each Data Collector and Message Collector should store collected data. Choices are 1-10 days. Data that has been retrieved by the Database Server will be stored on the Data Collector(s) and optional Message Collector(s) for the specified number of days and then automatically deleted from the server(s). This setting does not apply to All-In-One Appliances. The default value is 2 days.
- Ad-hoc and Scheduled Reports. Number of days SL1 will retain Quick Reports and Scheduled Reports in the Scheduled Report Archive page (Scheduled Job > Report Archive > Archived Job button). Possible values are 0 365, in days. If you use the default value of 0, SL1 will remove files older than 30 days from the populated directory: /opt/em7/gui/ap/www/em7/libs/od_templates/populated.
- Raw Performance Data. Number of days to retain performance data collected from devices. This setting applies to all performance data types, except for bandwidth data. Performance data that is older than the specified number of days is automatically deleted. This is the default system-wide value. The value in the Device Thresholds page for each device can override this value. The default value is 7 days.
- Hourly Rollup Performance Data. Number of days to retain hourly normalized performance data for devices. This setting applies to all performance data types, except for bandwidth data. Hourly normalized performance data that is older than the specified number of days is automatically deleted. This is the default system-wide value. The value in the Device Thresholds page for each device can override this value. The default value is 90 days.
- Daily Rollup Performance Data. Number of months to retain daily normalized performance data for devices. This setting applies to all performance data types, except for bandwidth data. Daily normalized performance data that is older than the specified number of months is automatically deleted. This is the default system-wide value. The value in the Device Thresholds page for each device can override this value. The default value is 24 months.
- Configuration Data. Number of days to retain data from Dynamic Applications of type "configuration". The value in the Device Thresholds page for each device can override this value. The default value is 7 days.
- Journal Data. Number of days to retain collected data from Dynamic Applications of type "journal".
 The value in the Device Thresholds page for each device can override this value. The default value is 60 days.
- Bandwidth Data. Number of days to retain bandwidth data and CBQoS data collected from each interface on a device. Bandwidth data that is older than the specified number of days is automatically deleted. The value in the Device Thresholds page for each device can override this value. The default value is 31 days.
- Hourly Rollup Bandwidth Data. Number of days to retain hourly normalized data and hourly normalized CBQoS data for each interface on a device. Hourly normalized data that is older than the specified number of days is automatically deleted. The value in the Device Thresholds page for each device can override this value. The default value is 90 days.

- Daily Rollup Bandwidth Data. Number of months to retain daily normalized data and daily normalized CBQoS data for each interface on a device. Daily normalized data that is older than the specified number of months is automatically deleted. The value in the Device Thresholds page for each device can override this value. The default value is 24 months.
- **Bandwidth Billing Data**. Number of months to retain data collected by each bandwidth billing policy. Bandwidth billing data that is older than the specified number of months is automatically deleted. The default value is 24 months.
- Device Logs Age. Number of days to retain each device log. Log records that are older than the
 specified number of days are automatically deleted. The value in the Device Thresholds page for
 each device can override this value. The default value is 90 days.
- Device Logs Max. Maximum number of records to store in each device log. When this number is
 exceeded, the oldest entries will be deleted. The value in the Device Thresholds page for each
 device can override this value. The default value is 10,000 records.
- Raw ITSM Data. Before the value for a metric in an IT Service policy is calculated, a copy of all the
 device data that will be aggregated is saved. This setting is the number of days to retain the unaggregated copies of device data associated with each IT Service. The default value is 31 days.
- ITSM Service Metrics Data. Number of days to retain values for metrics in IT Service policies. The default value is 30 days, with a maximum of 30 days.
- Hourly Rollup ITSM Service Metrics Data. Number of days to retain hourly normalized values for metrics in IT Service policies. The default value is 90 days, with a maximum of 90 days.
- Daily Rollup ITSM Service Metrics Data. Number of months to retain daily normalized values for metrics in IT Service policies. The default value is 12 months.
- ITSM Key Metrics Data. Number of days to retain values for key metrics in IT Service policies (Health, Availability, and Risk). The default value is 30 days, with a maximum of 30 days.
- Hourly Rollup ITSM Key Metrics Data. Number of days to retain hourly normalized values for key
 metrics in IT Service policies (Health, Availability, and Risk). The default value is 90 days, with a
 maximum of 180 days.
- Daily Rollup ITSM Key Metrics Data. Number of months to retain daily normalized values for key metrics in IT Service policies (Health, Availability, and Risk). The default value is 24 months.
- **Ports Data Retention**. Specifies the number of days after which expired port data will be marked for deletion during the hourly maintenance process. The default value is 730 days.
- Services Data Retention. Specifies the number of days after which expired services data will be marked for deletion during the hourly maintenance process. The default value is 24 hours.
- *Filesystems Data Retention*. Specifies the number of hours after which expired filesystems data will be marked for deletion during the hourly maintenance process. The default value is 24 hours.
- Subscriber Device Configuration Data. For users with a subscriber license. Number of months to retain the files and database tables that contain configuration information for a device. Default value is 6 months.
- Subscriber Device Usage Data. For users with a subscriber license. Number of months to retain the files and database tables that contain usage information for a device. Default value is 6 months.

- Subscriber System Configuration Data. For users with a subscriber license. Number of months to retain the files and database tables that contain configuration information for the SL1 system. Default value is 3 months.
- Subscriber System Usage Data. For users with a subscriber license. Number of months to retain the files and database tables that contain usage information for the SL1 system. Default value is 3 months.
- Subscriber Device Type Data. For users with a subscriber license. Number of months to retain the files and database tables that map each device to a device category, as per your subscriber license. Default value is 3 months.
- Subscriber Daily Delivery Data. For users with a subscriber license. Number of months to retain the "crunched" license usage data that is calculated each day using the Subscriber Device Configuration Data, Subscriber System Configuration Data, Subscriber System Usage Data, and Subscriber Device Type Data. SL1 will not prune data that has not yet been delivered to the ScienceLogic Licensing and Billing server. Default value is 3 months.
- 3. Click the [Save] button to save any changes to the data-retention settings.

NOTE: In SL1, normalized data does not include polling sessions that were missed or skipped. So for normalized data, null values are not included when calculating maximum values, minimum values, or average values.

TIP: You might want to retain normalized data for longer periods of time and non-normalized data for shorter periods of time. This allows you to save space and still create historical reports.

Normalization and Roll-Up of Performance Data

Normalization and roll-up are the ways in which SL1 processes collected performance data for display and storage. Note the following important distinctions:

- Raw data is the data exactly as it was collected from a device or application.
- Normalized and rolled up data is data for which SL1 has calculated summary statistics (sample size, count, maximum value, minimum value, mean value, average value, sum, and standard deviation) over a period of time.

Collection of Raw Data

Collector	Collected Data and Intervals		
Dynamic Applications	Collects raw performance data from a device at the following intervals:		
	• 1 minute		
	• 2 minutes		
	3 minutes		

Collector	Collected Data and Intervals
	• 5 minutes
	• 10 minutes
	• 15 minutes
	30 minutes
	• 1 hour
	• 2 hours
	• 6 hours
	• 12 hours
	• 24 hours
	For performance Dynamic Applications, you specify this interval in the Poll Frequency field, in the Properties Editor page (System > Manage > Applications > Create or use the).
IT Services	IT Service policies can generate raw performance data for an IT service by aggregating raw performance data from devices in the policy at the following intervals:
	• 1 minute
	• 2 minutes
	• 3 minutes
	• 5 minutes
	• 10 minutes
	• 15 minutes
	30 minutes
	• 1 hour
	• 2 hours
	6 hours
	• 12 hours
	• 24 hours
	You can specify the interval at which the IT Service policy collects and aggregates data in the Aggregation Frequency field, in the IT Service Editor page (Registry > IT Services > IT Service Manager > Create or use the).
Bandwidth	Collects raw bandwidth data from a network interface at the following intervals:
	• 1 minute
	• 5 minutes
	• 10 minutes

Collector	Collected Data and Intervals	
	• 15 minutes	
	30 minutes	
	60 minutes	
	• 120 minutes	
	You can specify the frequency at which SL1 collects raw data for a specific interface by selecting the interval in the <i>Frequency</i> field, in the <i>Interface Properties</i> page (Registry > Networks > Interfaces > interface wrench icon and select the for the given interface).	
Additional Performance Data	SL1 collects additional raw performance data about availability, latency, file systems, and statistics generated by monitoring policies for DNS availability, Email round-trip time, system processes, system services, port availability, web-content availability, and SOAP/XML transactions. By default, SL1 collects this data every 5 minutes.	

Data Normalization and Rollup

SL1 rolls up performance data so that reports with a larger timespan do not become difficult to view and to save storage space in the database. When SL1 rolls up data, SL1 groups data into larger sets and calculates the average value for the larger set.

SL1 supports two types of rollup:

- Hourly. Groups and averages data that is collected at intervals of 60 minutes or less. SL1 rolls up data and calculates an average hourly value for each metric. Hourly samples include samples from the top of the hour to the end of the hour. For example, for an hourly rollup of data collected at 1 minute intervals between 1:00 and 2:00, the first data point would be the one collected at 01:00:00 and the last would end at 01:59:00.
- Daily. Daily rollup groups and averages all collected data. SL1 rolls up data and calculates an average daily value for each metric. Daily samples include samples from the beginning of the day until the end of the day. For example, for a daily rollup of data collected at 1 minute intervals, the first data point would be the one collected at 00:00:00 and the last data point would the one collected at 23:59:00.

SL1 rolls up raw performance data as follows:

Frequency of Raw Collection	Rollup
Every 1 minute	60 minutes, 24 hours
Every 2 minutes	60 minutes, 24 hours
Every 3 minutes	60 minutes, 24 hours
Every 5 minutes	60 minutes, 24 hours
Every 10 minutes	60 minutes, 24 hours
Every 15 minutes	60 minutes, 24 hours
Every 30 minutes	60 minutes, 24 hours

Frequency of Raw Collection	Rollup
Every 60 minutes	60 minutes, 24 hours
Every 120 or longer	24 hours

Before SL1 normalizes date, SL1 transforms the data. To transform the data, SL1 does the following:

- For bandwidth data and data from Dynamic Applications of type "Performance", SL1 derives rates from counter metrics. The rate from counter metrics are expressed in units-per-polling_interval. For example, rates for 5 minute collections are expressed as units-per-5-minutes.
- For data from Dynamic Applications of type "Performance", SL1 evaluates presentation formulas. Counter metrics are first transformed into rates before evaluation.

NOTE: During the data transform steps, SL1 does not directly rollup the raw data in the database tables.

When SL1 rolls up data, SL1 must normalize that data, as follows:

NOTE: As a new piece of data is collected by SL1, the hourly normalization and daily normalization is calculated. SL1 does not wait for the end of an hour or the end of a day to calculate the hourly and daily normalization.

- Groups and orders the data
- Determines the sample size
- Calculates the count
- Determines the maximum value
- Determines the minimum value
- Calculates the mean value
- Calculates the average value
- Calculates the sum
- Determines the standard deviation

NOTE: In SL1, normalized data does not include polling sessions that were missed or skipped. For normalized data, null values are not included when calculating sample size, maximum values, minimum values, or average values.

Example

Suppose that every five minutes, SL1 collects data about file system usage on the device named *my_device*. As each raw data point is collected, SL1 normalizes and rolls up the collected data for file system usage for my_device. SL1 does the following:

- 1. Apply any necessary data transforms (as discussed in the previous section).
- 2. Repeat the following for both hourly normalization and daily normalization:
 - a. If this is the first data point for an hourly normalization or a daily normalization, insert summary statistics for that one data point
 - ° Sample size = 1
 - Average = value of new data point
 - Max = value of new data point
 - ° Min = value of new data point
 - Sum = value of new data point
 - Standard Deviation = 0
 - b. For all subsequent data points for an hourly normalization or a daily normalization, update the summary statistics of the existing rollup bucket
- 3. If there no gaps in collection, the summary statistics for hourly normalization will represent 12 data points and the summary statistics for daily normalization will represent 288 data points.

Storage of Raw and Rolled Up Data

There are two ways you can define how long SL1 should store raw data and rolled up and normalized data:

- You can define system-wide, default settings in the **Data Retention Settings** page (System > Settings > Data Retention). These settings apply to all collected data. However, you can override these system settings in the **Device Thresholds** page (Registry > Devices > Device Manager > wrench icon > Thresholds).
- For IT Service policies, aggregated device data is saved to a new database table specifically for the IT service policy. For each IT Service policy, data is normalized and rolled up. You define the data retention settings for an individual IT Service policy in the IT Service Editor page (Registry > IT Services > IT Service Manager > Create or). These settings override the data retention settings in the Data Retention Settings page (System > Settings > Data Retention).

Global Settings for Inbound Email and Outbound Email

The **Email Settings** page (System > Settings > Email) allows you to define how SL1 will send and receive email. SL1 automatically sends email when tickets are updated, when automation actions are triggered, and to monitor email round-trip time. Email can be sent to the platform to create tickets and/or events.

From the **Email Settings** page, you can edit the global email parameters. To do so:

- 1. Go to the **Email Settings** page (System > Settings > Email).
- 2. In the **Email Settings** page, you can edit the value for one or more of the following fields:
 - Authorized Email Domains. One or more SMTP domains that will be used by SL1. SL1 will use these domains to receive incoming email. This list of domains should include:

- ^o All domains used for loopback addresses in email round-trip monitoring policies.
- ° All domains used to generate tickets from emails.
- ° All domains used to receive event messages from third-party monitoring systems.
- ^e Each entry in this field must be a fully-qualified email domain and cannot exceed 64 characters. If you include a list of domains, separate the list with commas.
- ^e Each domain in this field must be managed by the Database Server. This means that a DNS MX record must already exist or be created for each domain specified in this field. Each DNS MX record must map the domain to the Database Server. When creating the DNS MX record, use the fully-qualified name of the Database Server as the name of the email server.
- System From Email Address. The email address from which SL1 will send all outbound email.

NOTE: Some outbound email servers, such as Gmail, might overwrite the **System From Email Address** value and instead use the email address of the authenticated user.

- **Email Formal Name**. Name that will appear in the "from" field in email messages sent from SL1. This value can be any alphanumeric value, up to 64 characters in length.
- *Email Gateway*. IP address or fully-qualified name of SL1's SMTP Relay server. If SL1 is to send outgoing messages, this field must be defined. Examples of when SL1 sends outgoing email messages are:
 - ° Automatically in response to Tickets from Email policies.
 - ^o Automatically in response to changes in a ticket (ticket is assigned, edited, or resolved).
 - Automatically based on Ticket Escalation policies.
 - ^o Automatically when executing Email Round-Trip Monitoring policies.
 - ^o Automatically when executing Run Book policies that include email actions.
 - ° Automatically based on Report Jobs policies.
 - ° Manually, when a user selects the **Send Message** page from the ticket panel pages.

Each Database Server and All-In-One Appliance includes a built-in SMTP Relay server. The fully-qualified name of SL1 SMTP Relay server is the same as the fully-qualified name of the Database Server or All-In-One Appliance.

If SL1 cannot use its built-in SMTP relay server to route email messages directly to their destination server (for example, due to firewall rules or DNS limitations), SL1 can use another relay server. You can specify the IP address or fully-qualified name of the relay server in this field. Make sure you have configured your network to allow the Database Server or All-In-One Appliance to access this SMTP Relay server.

NOTE: The *Email Gateway* field must be configured to use the appropriate port number to use, which is designated by a preceding colon. When no port number is specified, SL1 uses the default SMTP port (25).

- Email Gateway Alt. IP address or fully-qualified name of the secondary SMTP Relay server. If the SMTP Relay server specified in the previous field fails or is unavailable, SL1 will use the secondary SMTP Relay server. Make sure you have configured your network to allow the Database Server or All-In-One Appliance to access this SMTP Relay server.
- **Escalation Notify Subject**. Default "Subject" text in emails generated by Ticket Escalation policies. This field can include any combination of variables and text. The field can include up to 64 characters, including one or more variables:

The **Escalation Notify Subject** field can include one or more of the following variables:

Variable	Source	Description	
%1 (one)	Event	Entity type.	
%2	Event	Sub-entity type.	
%3	Event Policy	Event policy ID.	
%4	Event	Text string of the user name that cleared the event.	
%5	Event	Timestamp of when event was deleted.	
%6	Event	Timestamp for event becoming active.	
%7	Event	Event severity (1-5), for compatibility with previous versions of the platform. 1=critical, 2=major, 3=minor, 4=notify, 5=healthy.	
%A	Account	Username.	
%a	Entity	IP address.	
%B	Organization	Organization billing ID.	
%b	Organization	Impacted organization.	
%C	Organization	Organization CRM ID.	
%с	Event	Event counter.	
%D	Event	Timestamp of first event occurrence.	
%d	Event	Timestamp of last event occurrence.	
%E	Event Policy	External ID from event policy.	
%e	Event	Event ID.	
%F	Dynamic Alert	Dynamic Application alert id.	
%f	Event Policy	Specifies whether event is stateful, that is, has an associated event that will clear the current event. 1 (one) = stateful; 0 (zero) = not stateful.	
%G	Event Policy	Event Category.	
%g	Asset	Asset serial.	

Variable	Source	Description	
%H	Event	URL link to event.	
%h	Asset	Device ID associated with the asset.	
%l (uppercase "eye")	Dynamic Alert	Table index for a Dynamic Application.	
%i (lowercase "eye")	Asset	Asset Location.	
%7	Ticket	Ticket subject.	
%K	Asset	Asset Floor.	
%k	Asset	Asset Room.	
%M	Event	Event message.	
%m	Automation	Automation policy note.	
%N	Action	Automation action name.	
%n	Automation	Automation policy name.	
%O (uppercase "oh")	Organization	Organization name.	
%o (lowercase "oh")	Organization	Organization ID.	
%P	Asset	Asset plate.	
%р	Asset	Asset panel.	
%Q	Asset	Asset punch.	
%q	Asset	Asset zone.	
%R	Event Policy	Event policy cause/action text.	
%r	System	Unique ID / name for the current SL1 system.	
%S	Event	Severity (Healthy - Critical).	
%s	Event	Severity (0 - 4). 0=healthy, 1=notify, 2=minor, 3=major, 4=critical.	
%T	Dynamic Alert	Dynamic Application alert threshold value.	
%t	Ticket	Ticket ID.	
%U	Asset	Asset rack.	
%u	Asset	Asset shelf.	
%V	Dynamic Alert	Dynamic Application alert result value.	
%v	Asset	Asset tag.	
%W	Asset	Asset make.	
%w	Asset	Asset model.	
%X	Event	Entity name.	
%x	Event	Entity ID.	
%Y	Event	Sub-entity name.	
%у	Event	Sub-entity ID.	
%Z	Event	Event source (1 - 8).	
%z	Event	Event source (Syslog - Group).	

Global Settings for Login Alert Messages

In SL1, administrators can add a customizable click-through alert message as a security measure at logon. Users will not be able to access the system until the user click the **[OK]** button to agree to the terms and conditions of use for that system.

To add a custom login alert message to SL1:

- 1. Go to the **Login Alert Editor** page (System > Settings > Login Alert Message).
- 2. In the Alert Message field, type the text of your login alert message.
- 3. After entering the login alert text, click the [Save] button.
- 4. When a user logs in, the alert message will display.

Global Settings for Password Reset Emails

The **Password Reset Email Editor** page (Password Reset Email Editor) allows ScienceLogic administrators to define the email message that is sent to ScienceLogic users who select the "I forgot my password" option from the **Login** page.

If the user enters a valid ScienceLogic username in the **Login** page and then selects the *I forgot my password* option, SL1 will check the account information for that user. If the user's account information includes an email address, SL1 will send the user an email message. The email message will include a link that allows the user to redefine their ScienceLogic password. The new password must meet the requirements defined in the **Password Strength** field and the **Password Shadowing** field for the user account. SL1 will prompt the user to meet these requirements and display a description of those requirements.

The user can select the *I forgot my* password option up to ten times without responding to the sent email (using the link in the email to reset the password). After ten times, SL1 will no longer send another email message to the user's email address. The user can continue to select the *I forgot my* password option, but SL1 will not resend an email.

If the user's account information does not include an email address, SL1 displays the message "Password recovery is not available for your account, please contact your system administrator".

If the user does not enter a valid ScienceLogic username in the **Login** page, the *I forgot my password* option is still displayed, but SL1 does not send an email. This prevents intruders from guessing ScienceLogic account names.

If the user exceeds the number of login tries (defined in the **Behavior Settings** page), the "I forgot my password" option is not displayed in the **Login** page.

Defining the Email Message for "I forgot my password"

In the **Password Reset Email Editor** page (System > Settings > Password Reset Email), you can define the email that is sent from SL1 when an end user selects the *I forgot my password* option from the **Login** page.

To define the email message sent by SL1:

1. Go to the **Password Reset Email Editor** page (System > Settings > Password Reset Email).

- 2. Supply a value in each of the following fields:
 - *Priority*. This will be the priority of the email message. Choices are:
 - ° High. Emails will be marked as high priority.
 - ° Normal. Emails will be marked as normal priority.
 - ° Low. Emails will be marked as low priority.
 - Subject. This will be the subject of the email message.
 - Message. This will be the body of the email message. The body must include the variable %L. This variable inserts the link to the page that allows the user to reset their ScienceLogic password.
- 3. You can include the following variables in the **Subject** field and the **Message** field:
 - %L (uppercase "el"). The link to the page that allows the user to reset their password.
 - %O (uppercase "oh"). The user's primary organization, as defined in the Account Permissions page for the user.
 - **%fn (lowercase "eff" "en")**. The user's first name, as defined in the **Account Permissions** page for the user
 - %In (lowercase "el "en". The user's last name, as defined in the Account Permissions page for the user.
- 4. Click the [Save] button to save the email template.
- 5. When a user follows the link in the email, SL1 displays the **Login** page, with the message "Your account has been reset. Please create a new password." The user must then enter their new password twice. The new password is recorded in SL1 and replaces the previous (forgotten) password.

For example, you could define the following:

Subject. ScienceLogic | %O (automated message)

Message. Hello %fn %ln,

Your password for account %A has been reset.

Please use the following link to log in and choose a new password:

%L.

For the user "Keyser Soze", who is a member of the System organization, the following email would be sent:

Subject: ScienceLogic | System (automated message).

Hello Keyser Soze,

Your password for account ksoze has been reset.

Please use the following link to login and choose a new password:

https://name or IP of EM7 Administration Portal/login.em7?prs=hash

Global Settings for Security

The **Security Settings** page (System > Settings > Security) allows you to define and view the status of global security settings for your SL1 system.

NOTE: The **Security Settings** page is available only in the classic SL1 user interface in SL1 version 12.2.1 and later.

You can define the following global security setting on this page:

• Verify TLS Certificates. When this settings is enabled, SL1 services will validate TLS certificates that are presented to them and reject self-signed certificates. To enable this setting, select the checkbox and click [Save].

On this page, you can also view the current status of the Enterprise Key Management Service (EKMS) for your SL1 system. This service provides strong encryption for SL1 credentials, and is enabled by default in versions 12.2.0 and later with no additional configuration required.

Global Settings for System Thresholds

The **System Threshold Defaults** page (System > Settings > Thresholds > System) allows you to define global thresholds for system latency, file system usage, counter rollovers, ICMP availability, number of component devices, interface inventory, and inbound messages.

These settings apply to all devices. However, you can override these system settings on a case-by-case basis. For example, you can define thresholds for a device's file systems in the [Thresholds] tab of the Device Investigator (or the Device Thresholds page in the classic SL1 user interface). The settings you define for the specific device override the settings in the System Threshold Defaults page.

To edit the global settings for system thresholds:

- 1. Go to the **System Threshold Defaults** page (System > Settings > Thresholds > System).
- 2. In the **System Threshold Defaults** page, you can drag sliders to change to value of each field or edit a field manually. You can edit the value for one or more of the following fields:

- **System Latency**. During polling, the platform initially pings monitored devices. The value in this field is the maximum number of milliseconds for the device to respond to SL1's ping (round-trip time divided by 2). The default value is 100 ms. When the latency threshold is exceeded, SL1 generates an event for that device.
- System Availability. During polling, SL1 monitors devices for availability. Availability means the device's ability to accept connections and data from the network. The value in this field is the percent availability required of each device. The default value is 99%. When a device falls below this level of availability, SL1 generates an event for that device.

During polling, a device has two possible availability values:

- ° 100%. Device is up and running.
- ° 0%. Device is not accepting connections and data from the network.

NOTE: Component devices use a Dynamic Application collection object to measure availability. SL1 polls component devices for availability at the frequency defined in the Dynamic Application. For details, see the chapter on Monitoring Device Availability and Latency in the **Monitoring Device**Infrastructure Health manual.

NOTE: The *Ping & Poll Timeout (Msec)* setting in the **Behavior Settings** page (System > Settings > Behavior) affects how SL1 monitors device availability. This field specifies the number of milliseconds the discovery tool and availability polls will wait for a response after pinging a device. After the specified number of milliseconds have elapsed, the poll will timeout.

- *File System Major*. Threshold that will trigger a "low disk space" event. The default threshold is 85%. When a device has used more disk space than the specified percentage, SL1 will generate a "file system usage exceeded threshold" event with a status of "major".
- *File System Critical*. Threshold that will trigger a "low disk space" event. The default threshold is 95%. When a device has used more disk-space than the specified percentage, SL1 will generate a "file system usage exceeded threshold" event with a status of "critical".

NOTE: If you hide a file system in the **Device Hardware** page (Devices > Hardware), SL1 does not generate events for that file system.

• Rollover Percent. For any collected data that uses a 32-bit counter, you can specify how SL1 determines that the counter has "rolled over", that is, has reached its maximum value, is reset to zero, and restarts counting. When this happens, the collected values go from the maximum value to a lower value. However, there are multiple circumstances under which a counter value can go from a higher value to a lower value:

- Maximum value has been exceeded and counter was reset to zero.
- Retrieved value was manually reset to zero on the external device.
- Data was collected out-of-order, that is, due to a slowdown somewhere in the network, two counter values were stored out of sequence.

NOTE: For 64-bit counters, when the counter values go from a higher value to a lower value, SL1 assumes that the counter has been manually reset or that the two values were collected out of order. SL1 does not assume that the counter has rolled over.

The *Rollover Percent* field allows you to specify a threshold that indicates that a 32-bit counter has reached its maximum value and restarted counting. The default value is 20%. When SL1 records a counter value that is lower than the previously collected value, the platform:

° Calculates the difference between the two counter values (the delta):

232 - Last Collected Value + Current Collected Value

- Examines the value of the Rollover Percent threshold. If the delta is less than the specified percentage of the maximum possible value (2³²), SL1 concludes that the 32-bit counter rolled over.
- For example, if you specified "25" in this field, SL1 would determine if the delta is less than 25% of the maximum possible value. If the delta is less than 25% of the maximum possible value, SL1 concludes that the 32-bit counter rolled over.
- When SL1 determines a counter has rolled over, SL1 uses the delta value when displaying the data point for this poll period.

NOTE: The *Rollover Percent* field applies only to 32-bit counters. If a 64-bit counter value goes from a higher value to a lower value, the change is treated as either a manual reset or an out-of-order collection.

- Out-of-order Percent. For any collected data that uses a counter, you can specify how SL1 determines that data has been collected out of order. When this data is collected out of order, the collected values go from a higher value to a lower value. However, there are multiple circumstances under which a counter value can go from a higher value to a lower value:
 - Maximum value has been exceeded and counter was reset to zero (for 32-bit counters only).
 - Data was collected out-of-order, that is, due to a slowdown somewhere in the network, two counter values were stored out of sequence.
 - ° Retrieved value was manually reset to zero on the external device.

The **Out-of-order Percent** field allows you to specify a threshold that indicates that data has been collected out of order. The default value is 50%. When SL1 records a counter value that is lower than the previously collected value and the platform has determined that the value is not a rollover, SL1:

- Compares the current value to the last collected value: current value / last collected value
- of the ratio of current value / last collected value is greater than the percent specified in the **Out-of-order Percent** field, SL1 concludes that the data was collected out of order.
- When SL1 determines a data point has been collected out of order, SL1 uses the following value as the current value of the data point:

last collected value - current collected value

NOTE: If a 32-bit counter value goes from the maximum value to a lower value, and the current collected value does not meet the criteria for a rollover AND the current collected value does not meet the criteria for out-of-order, SL1 concludes that the 32-bit counter was manually reset to zero (0). SL1 uses the current collected value for this data point.

NOTE: If a 64-bit counter value goes from a higher value to a lower value, and the current collected value does not meet the criteria for out-of-order, SL1 concludes that the 64-bit counter was manually reset to zero (0). SL1 uses the current collected value for this data point.

- Availability Ping Count. If you select ICMP in the Availability Port field in the Device Properties page (Devices > Device Manager > wrench icon) for a device, this field specifies the number of packets that should be sent during each availability check. The default value is "1".
- Avail Required Ping Percentage. If you select ICMP in the Availability Port field in the Device
 Properties page (Devices > Device Manager > wrench icon) for a device, this field specifies the
 percentage of packets that must be returned during an availability check for SL1 to consider the
 device available. The default value is "100%".
- Process Runtime Threshold Low. Threshold that will trigger a "process time exceeded" event. The
 default threshold is 80%. When a process has used more than 80% of its allowed Run Length, SL1
 will generate a "process time exceeded threshold" event with a status of "minor".
- Process Runtime Threshold High. Threshold that will trigger a "process time exceeded" event. The
 default threshold is 100%. When a process has used 100% of its allowed Run Length, SL1 will
 generate a "process time exceeded threshold" event with a status of "major".

NOTE: *Run Length* is defined in the **Process Manager** page (System > Settings > Admin Processes).

• Component Purge Timeout. This field specifies the number of hours a device can be set to "vanished" before SL1 purges the component device. When a device is purged, SL1 stops trying to collect data about the component device. The purged device will not appear in reports or views on in any pages in the user interface. When a device is purged, all of its configuration data and collected data is deleted from the Database Server. If you set this value to "0", component devices are never purged. You can override this threshold for a specific device in the [Thresholds] tab of the Device Investigator (or the Device Thresholds page in the classic SL1 user interface) for the device.

NOTE: When a device is set to "vanished", all children of that device are also set to "vanished". When a device is purged, all children of that device are also purged.

- Component Vanish Timeout Mins. If SL1 cannot retrieve information from a root device about a component device, this field specifies how many minutes to wait until putting the component device into "vanish" mode. When a device is set to "vanished", SL1 stops trying to collect data about the component device. The vanished device will not appear in reports or views. The vanished device will appear in the Vanished Device Manager page. If you set this value to "0", component devices are never set to "vanished". You can override this threshold for a specific device in the [Thresholds] tab of the Device Investigator (or the Device Thresholds page in the classic SL1 user interface) for the device.
- Interface Inventory Timeout. Specifies the maximum amount of time that the discovery processes will spend polling a device for the list of interfaces. After the specified time, SL1 will stop polling the device, will not model the device, and will continue with discovery. The default value is 600,000 ms (10 minutes).
 - During initial discovery, initiated from the Discovery Session Editor page (System > Manage > Classic Discovery > Create), SL1 uses the value in this field if there is no differing value specified in the **Discovery Session Editor** page.
 - During re-discovery (clicking the binocular icon () in the Device Properties page), SL1 will use the value in this field if there no value is specified in the [Thresholds] tab of the Device Investigator (or the Device Thresholds page in the classic SL1 user interface) for the device.
 - During *nightly auto-discovery* (run automatically by SL1 every night, to update device information), SL1 uses the value in this field if no differing value is specified in the **[Thresholds]** tab of the **Device Investigator** (or the **Device Thresholds** page in the classic SL1 user interface) for a device.
- Maximum Allowed Interfaces. Specifies the maximum number of interfaces per device. If a device exceeds this number of interfaces, SL1 will stop scanning the device, will not model the device, and will continue with discovery. The default value is 10,000.
 - During initial discovery, initiated from the Discovery Session Editor page (System > Manage > Classic Discovery > Create), SL1 uses the value in this field if there is no differing value specified in the Discovery Session Editor page.

- During re-discovery (clicking the binocular icon () in the Device Properties page), SL1 will use the value in this field if there is no differing value is specified in the [Thresholds] tab of the Device Investigator (or the Device Thresholds page in the classic SL1 user interface) for the device.
- During nightly auto-discovery (run automatically by SL1 every night, to update device information), SL1 uses the value in this field if no differing value is specified in the [Thresholds] tab of the Device Investigator (or the Device Thresholds page in the classic SL1 user interface) for a device.
- Inbound Message Throttle Thresholds. Specifies the maximum number of messages that can be received before SL1 will notify the system administrator and discard the current batch of messages. The default message threshold is 25.
 - Syslog per-IP. Specifies the threshold for incoming syslog messages from a given IP address.
 - Dynamic Alert per-device. Specifies the threshold for incoming alerts for a Dynamic Application on a given device.
 - ° SNMP Trap per-IP. Specifies the threshold for incoming SNMP traps from a given IP address.
- **SSL Certificate Purge Timeout**. Specifies the number of days after which SSL certificate data will be purged. The default value is 0 days.
- **Schedules Purge Timeout**. Specifies the number of days after which expired schedules will be deleted. The default value is 730 days.
- 3. Click the [Save] button to save changes in this page.
- 4. All changes to this page are logged in the audit logs.

Global Settings for Interface Thresholds

The **Interface Thresholds Defaults** page (System > Settings > Thresholds > Interface) allows you to define global thresholds for interfaces.

The settings in the **Interface Thresholds Defaults** page apply to all interfaces. However, you can override these system settings on a case-by-case basis for each interface in the **Thresholds** tab on the **Interface Properties** page (Registry > Networks > Interfaces > interface wrench icon).

If you have specified that SL1 should monitor an interface, SL1 will collect data about the interface and also monitor performance thresholds for the interface. SL1 will use either the default thresholds defined in the **Interface Thresholds Defaults** page (System > Settings > Thresholds > Interface or the custom threshold you define in the **Thresholds** tab on the **Interface Properties** page (Registry > Networks > Interfaces > interface wrench icon). When the values for an interface exceed one or more thresholds, SL1 will generate an event.

To define global thresholds for interfaces:

1. Go to Interface Thresholds Defaults page (System > Settings > Thresholds > Interface.

2. The following global thresholds are defined by default in the Interface Thresholds Defaults page:

NOTE: You can specify the unit of measure for all the metrics in **Bandwidth In** and **Bandwidth Out**. You can select **bps**, **kbps**, **Mbps** (the default), or **Gbps**.

Threshold	Default Value	Default Status
Utilization % In > Inbound Percent	65.000	Enabled
Utilization % Out > Outbound Percent	65.000	Enabled
Bandwidth In > Inbound Bandwidth	0.000	Disabled
Bandwidth Out > Outbound Bandwidth	0.000	Disabled
Errors % In > Inbound Error Percent	1.000	Enabled
Errors % Out > Outbound Error Percent	1.000	Enabled
Errors In > Inbound Errors	1000.000	Enabled
Errors Out > Outbound Errors	1000.000	Enabled
Discard % In > Inbound Discard Percent	1.000	Enabled
Discards % Out > Outbound Discard Percent	1.000	Enabled
Discards In > Inbound Discards	1000.000	Enabled
Discards Out > Outbound Discards	1000.000	Enabled
Multicast % In > Rising Medium	30.000	Disabled
Multicast % In > Rising Low	20.000	Disabled
Broadcast % Out > Rising Medium	30.000	Disabled
Broadcast % Out > Rising Low	20.000	Disabled

3. Selecting the **Show Hidden Thresholds** checkbox displays the following default thresholds:

NOTE: You can specify the unit of measure for all the metrics in **Bandwidth In** and **Bandwidth Out**. You can select **bps**, **kbps**, **Mbps** (the default), or **Gbps**.

Threshold	Default Value	Default Status
Utilization % In > Rising High	0.000	Hidden
Utilization % In > Rising Medium	0.000	Hidden
Utilization % In > Rising Low	0.000	Hidden

Threshold	Default Value	Default Status
Utilization % In > Falling Low	0.000	Hidden
Utilization % In > Falling Medium	0.000	Hidden
Utilization % In > Falling High	0.000	Hidden
Utilization % In > Inbound Percent	65.000	Enabled
Utilization % Out> Rising High	0.000	Hidden
Utilization % Out > Rising Medium	0.000	Hidden
Utilization % Out > Rising Low	0.000	Hidden
Utilization % Out > Falling Low	0.000	Hidden
Utilization % Out > Falling Medium	0.000	Hidden
Utilization % Out > Falling High	0.000	Hidden
Utilization % Out > Outbound Percent	65.000	Enabled
Bandwidth In > Rising High	0.000	Hidden
Bandwidth In > Rising Medium	0.000	Hidden
Bandwidth In > Rising Low	0.000	Hidden
Bandwidth In > Falling Low	0.000	Hidden
Bandwidth In > Falling Medium	0.000	Hidden
Bandwidth In > Falling High	0.000	Hidden
Bandwidth In > Inbound Bandwidth	0.000	Disabled
Bandwidth Out > Rising High	0.000	Hidden
Bandwidth Out > Rising Medium	0.000	Hidden
Bandwidth Out > Rising Low	0.000	Hidden
Bandwidth Out > Falling Low	0.000	Hidden
Bandwidth Out > Falling Medium	0.000	Hidden
Bandwidth Out > Falling High	0.000	Hidden
Bandwidth Out > Outbound Bandwidth	0.000	Disabled
Errors % In > Rising High	0.000	Hidden
Errors % In > Rising Medium	0.000	Hidden
Errors % In > Rising Low	0.000	Hidden
Errors % In > Falling Low	0.000	Hidden

Threshold	Default Value	Default Status
Errors % In > Falling Medium	0.000	Hidden
Errors % In > Falling High	0.000	Hidden
Errors % In > Inbound Error Percent	1.000	Enabled
Errors % Out > Rising High	0.000	Hidden
Errors % Out > Rising Medium	0.000	Hidden
Errors % Out > Rising Low	0.000	Hidden
Errors % Out > Falling Low	0.000	Hidden
Errors % Out > Falling Medium	0.000	Hidden
Errors % Out > Falling High	0.000	Hidden
Errors % Out > Outbound Error Percent	1.000	Enabled
Errors In > Rising High	0.000	Hidden
Errors In > Rising Medium	0.000	Hidden
Errors In > Rising Low	0.000	Hidden
Errors In > Falling Low	0.000	Hidden
Errors In > Falling Medium	0.000	Hidden
Errors In > Falling High	0.000	Hidden
Errors In > Inbound Errors	1000.000	Enabled
Errors Out > Rising High	0.000	Hidden
Errors Out > Rising Medium	0.000	Hidden
Errors Out > Rising Low	0.000	Hidden
Errors Out > Falling Low	0.000	Hidden
Errors Out > Falling Medium	0.000	Hidden
Errors Out > Falling High	0.000	Hidden
Errors Out > Outbound Errors	1000.000	Enabled
Discards % In > Rising High	0.000	Hidden
Discards % In > Rising Medium	0.000	Hidden
Discards % In > Rising Low	0.000	Hidden
Discards % In > Falling Low	0.000	Hidden
Discards % In > Falling Medium	0.000	Hidden

Threshold	Default Value	Default Status
Discards % In > Falling High	0.000	Hidden
Discards % In > Inbound Discard Percent	1.000	Enabled
Discards % Out > Rising High	0.000	Hidden
Discards % Out > Rising Medium	0.000	Hidden
Discards % Out > Rising Low	0.000	Hidden
Discards % Out > Falling Low	0.000	Hidden
Discards % Out > Falling Medium	0.000	Hidden
Discards % Out > Falling High	0.000	Hidden
Discards % Out > Outbound Discard Percent	1.000	Enabled
Discards In > Rising High	0.000	Hidden
Discards In > Rising Medium	0.000	Hidden
Discards In > Rising Low	0.000	Hidden
Discards In > Falling Low	0.000	Hidden
Discards In > Falling Medium	0.000	Hidden
Discards In > Falling High	0.000	Hidden
Discards In > Inbound Discards	1000.000	Enabled
Discards Out > Rising High	0.000	Hidden
Discards Out > Rising Medium	0.000	Hidden
Discards Out > Rising Low	0.000	Hidden
Discards Out > Falling Low	0.000	Hidden
Discards Out > Falling Medium	0.000	Hidden
Discards Out > Falling High	0.000	Hidden
Discards Out > Outbound Discards	1000.000	Enabled
Broadcast % In > Rising High	0.000	Hidden
Broadcast % In > Rising Medium	30.000	Disabled
Broadcast % In > Rising Low	20.000	Disabled
Broadcast % In > Falling Low	0.000	Hidden
Broadcast % In > Falling Medium	0.000	Hidden
Broadcast % In > Falling High	0.000	Hidden

Threshold	Default Value	Default Status
Broadcast % Out > Rising High	0.000	Hidden
Broadcast % Out > Rising Medium	30.000	Disabled
Broadcast % Out > Rising Low	20.000	Disabled
Broadcast % Out > Falling Low	0.000	Hidden
Broadcast % Out > Falling Medium	0.000	Hidden
Broadcast % Out > Falling High	0.000	Hidden
Broadcast In > Rising High	0.000	Hidden
Broadcast In > Rising Medium	0.000	Hidden
Broadcast In > Rising Low	0.000	Hidden
Broadcast In > Falling Low	0.000	Hidden
Broadcast In > Falling Medium	0.000	Hidden
Broadcast In > Falling High	0.000	Hidden
Broadcast Out > Rising High	0.000	Hidden
Broadcast Out > Rising Medium	0.000	Hidden
Broadcast Out > Rising Low	0.000	Hidden
Broadcast Out > Falling Low	0.000	Hidden
Broadcast Out > Falling Medium	0.000	Hidden
Broadcast Out > Falling High	0.000	Hidden
Multicast % In > Rising High	0.000	Hidden
Multicast % In > Rising Medium	00.000	Hidden
Multicast % In > Rising Low	00.000	Hidden
Multicast % In > Falling Low	0.000	Hidden
Multicast % In > Falling Medium	0.000	Hidden
Multicast % In > Falling High	0.000	Hidden
Multicast % Out > Rising High	0.000	Hidden
Multicast % Out > Rising Medium	00.000	Hidden
Multicast % Out > Rising Low	00.000	Hidden
Multicast % Out > Falling Low	0.000	Hidden
Multicast % Out > Falling Medium	0.000	Hidden

Threshold	Default Value	Default Status
Multicast % Out > Falling High	0.000	Hidden
Multicast In > Rising High	0.000	Hidden
Multicast In > Rising Medium	0.000	Hidden
Multicast In > Rising Low	0.000	Hidden
Multicast In > Falling Low	0.000	Hidden
Multicast In > Falling Medium	0.000	Hidden
Multicast In > Falling High	0.000	Hidden
Multicast Out > Rising High	0.000	Hidden
Multicast Out > Rising Medium	0.000	Hidden
Multicast Out > Rising Low	0.000	Hidden
Multicast Out > Falling Low	0.000	Hidden
Multicast Out > Falling Medium	0.000	Hidden
Multicast Out > Falling High	0.000	Hidden
Unicast % In > Rising High	0.000	Hidden
Unicast % In > Rising Medium	00.000	Hidden
Unicast % In > Rising Low	00.000	Hidden
Unicast % In > Falling Low	0.000	Hidden
Unicast % In > Falling Medium	0.000	Hidden
Unicast % In > Falling High	0.000	Hidden
Unicast % Out > Rising High	0.000	Hidden
Unicast % Out > Rising Medium	00.000	Hidden
Unicast % Out > Rising Low	00.000	Hidden
Unicast % Out > Falling Low	0.000	Hidden
Unicast % Out > Falling Medium	0.000	Hidden
Unicast % Out > Falling High	0.000	Hidden
Unicast In > Rising High	0.000	Hidden
Unicast In > Rising Medium	0.000	Hidden
Unicast In > Rising Low	0.000	Hidden
Unicast In > Falling Low	0.000	Hidden

Threshold	Default Value	Default Status
Unicast In > Falling Medium	0.000	Hidden
Unicast In > Falling High	0.000	Hidden
Unicast Out > Rising High	0.000	Hidden
Unicast Out > Rising Medium	0.000	Hidden
Unicast Out > Rising Low	0.000	Hidden
Unicast Out > Falling Low	0.000	Hidden
Unicast Out > Falling Medium	0.000	Hidden
Unicast Out > Falling High	0.000	Hidden

- 4. For each threshold, you can edit the following:
 - Value. The value at which the threshold will trigger an event.
 - For thresholds that include the word *Rising*, when a value exceeds the specified value, SL1 triggers an event.
 - ° For thresholds that include the word *Falling*, when a value falls below the specified value, SL1 triggers an event.
 - ^o For thresholds that do not include the word *Rising* or *Falling*, when a value exceeds the specified value, SL1 triggers an event.
 - Status. Specifies whether the threshold is active and whether the threshold will appear in the Thresholds tab on the Interface Properties page (Registry > Networks > Interfaces > interface wrench icon). Choices are:
 - Enabled. The threshold is applied to all interfaces and is monitored by SL1. The threshold appears in the Thresholds tab on the Interface Properties page (Registry > Networks > Interfaces > interface wrench icon). Users can edit the Value and Status of the threshold.
 - Disabled. The threshold is applied to all interfaces but is not monitored by SL1. The threshold appears in the Thresholds tab on the Interface Properties page (Registry > Networks > Interfaces > interface wrench icon) with a status of Disabled. In the Thresholds tab on the Interface Properties page, users can edit the Value and Status of the threshold.
 - Hidden. The threshold is not applied to all interfaces, and is not monitored by SL1. The threshold does not appear in the Thresholds tab on the Interface Properties page (Registry > Networks > Interfaces > interface wrench icon).
 - Unit of Measure. For all the metrics under Bandwidth In and Bandwidth Out, you can select the unit of measure. Choices are:
 - ° kbps
 - ° Mbps

Settings in Silo.Conf

Every SL1 appliance has a configuration file called **silo.conf**, which contains configuration information about the appliance itself, such as the IP address, licensing information, and directory locations. The default settings in **silo.conf** are configured automatically when the appliance is installed. The following section describes how you can add additional, non-default settings to **silo.conf**.

CAUTION: ScienceLogic recommends that you do not edit the values in these files without first consulting ScienceLogic. Incorrect values can severely disrupt platform operations.

NOTE: All settings in these .conf files are case-sensitive.

To edit the **silo.conf** file:

- 1. Either go to the console of the SL1 appliance or use SSH to access the SL1 appliance.
- 2. Open a shell session on the server.
- 3. Type the following at the command line:

sudo visilo

IMPORTANT: For ISO installs of SL1 version 11.3.0 and later, password information in the **silo.conf** file is automatically encrypted when the file is modified using visilo. Users can no longer decrypt passwords in the **silo.conf** file.

NOTE: You can use the *ap_user* and *ap_pass* fields to define usernames and passwords for the Administration Portal that differ from the usernames and passwords used for the Database Server.

- 4. You can add or edit one or more of the following settings:
 - **store_timeout**. You can edit this setting in the **silo.conf** file on each Database Server. When the Database Server pulls collected data back from Data Collectors and Message Collectors, each piece of data (called a storage object) must be stored within a set amount of time. The default timeout for a storage object is ten seconds. To change the timeout for all storage objects, add the following line to the silo.conf file on the Database Server:

store timeout=xx

where xx is the timeout in seconds.

If you change this setting (for example, change the value to 30 seconds), you must stop and restart the high frequency, medium frequency, and low frequency data pull processes for the change to be applied.

NOTE: The store timeout setting does not apply to All-In-One Appliances.

eventmanager. You can edit this setting in the silo.conf file on each SL1 appliance. You can
modify this default setting to allow API events to be processed on a Data Collector. The default
configuration is:

```
eventmanager = internal, dynamic, syslog, trap
```

To allow a Data Collector to process API events, change this line to

```
eventmanager = internal, dynamic, syslog, trap, api
```

WARNING: Do not make any other changes to this setting or modify this setting on a Database Server or Data Collector.

• report_memory_limit. You can edit this setting in the silo.conf file on each SL1 appliance that provides the user interface (an Administration Portal, Database Server, or All-In-One Appliance). If report_memory_limit is not defined in silo.conf, the default value is three gigabytes (3G). If reports are failing to be generated due to a lack of memory, you can increase this value.

To increase report memory, add the following line to the [LOCAL] section of silo.conf on each SL1 appliance the provides the user interface for your system. In most cases, this will be the Administration Portal (for distributed system) or the All-In-One Appliance:

```
report_memory_limit=XY
```

where:

- X is a positive integer
- ^o Y represents units. Value can be **K** (kilobytes), **M** (megabytes), or **G** (gigabytes),

For example, if reports are failing to be generated due to a lack of memory, you could add the following line to **silo.conf**:

```
report memory limit=4G
```

NOTE: You should add the *report_memory_limit* option to the **silo.conf** file on a Database Server only if there are no Administration Portals configured in your system.

NOTE: You must add the same *report_memory_limit* setting to every Administration Portal configured in your system.

- use_v1trap_envelope_addr. You can edit this setting in the silo.conf file on each Data Collectors, Data Collectors that perform message collection, and All-In-One Appliances. In environments where Network Address Translation is performed on SNMP v1 trap messages sent to SL1, you can configure the platform to read the envelope address (the address of the host sending the trap) instead of the agent address (the IP address variable sent as part of the trap). If use_v1trap_envelope_addr is not defined in silo.conf, SL1 will use the agent address for SNMP v1 trap messages.
 - To use the envelope address instead of the agent address for SNMP v1 trap messages, add the following line to the [LOCAL] section of silo.conf on Data Collectors, Data Collectors that perform message collection, and All-In-One Appliances

```
use v1trap envelope addr=1
```

To use the agent address for SNMP v1 trap messages, you can either omit the use_v1_trap_envelope_addr setting or add the following line to the [LOCAL] section of silo.conf on Data Collectors, Data Collectors that perform message collection, and All-In-One Appliances

```
use v1trap envelope addr=0
```

• disable_itil_compliance. You can edit this setting in the silo.conf file on each If you enable this setting on an appliance that provides the user interface (an Administration Portal, Database Server, or All-In-One Appliance), the Ticket Console page on that appliance will include an option to delete tickets. The option to delete tickets will appear only to users that have been granted the Ticket: Delete access hook and users of type "administrator".

To enable this setting, add the following line to the [LOCAL] section of silo.conf on the appliance that provides the user interface (Administration Portal, Database Server, or All-In-One Appliance):

```
disable itil compliance=1
```

suppress_ticket_link. You can edit this setting in the silo.conf file on each SL1 appliance that
provides the user interface (an Administration Portal, Database Server, or All-In-One Appliance). If
you enable this setting, automatic notifications that are generated when a ticket is created or
updated will not include a hyperlink to the ticket.

To enable this setting, add the following line to the [LOCAL] section of silo.conf on SL1 appliance that provides the user interface (Administration Portal, Database Server, or All-In-One Appliance):

```
suppress ticket link=1
```

• mailparse_interval. You can edit this setting in the silo.conf file on each Database Server or All-In-One Appliance. The mailparse_interval setting defines how frequently the mail parsing process reads email messages from the mailbox. If the mailparse_interval setting is not defined in silo.conf, the default value is 60 seconds. When an email is received by SL1, the mail parsing process on the primary Database Server or All-In-One Appliance reads the email message from the mailbox file

and sends it to one of the three processes responsible for acting on that email: the event engine (for events from email), the tickets from email process, or the round-trip email collection process.

To enable this setting, add the following line to the [LOCAL] section of silo.conf on each Database Server or All-In-One Appliance:

```
mailparse interval=X
```

where X is the frequency at which the mailbox will be read, in seconds. Valid values are 15 seconds to 60 seconds.

• dynamic_collect_num_chunk_workers. You can edit this setting in the silo.conf file on each Database Server or All-In-One Appliance. This setting represents the number of workers that handle collection requests. SL1 first sorts collection requests into groups by execution environment and sends each group of collection requests (called a chunk) to a worker process. This worker process is called a chunk worker. For each chunk, a chunk worker creates the execution environment and creates a pool of request workers to process the collection requests. The number of chunk workers generally represents the number of PowerPacks that can be processed in parallel. The default value for this parameter is "2".

To change this setting, add the following line to the [LOCAL] section of **silo.conf** on each Database Server or All-In-One Appliance:

```
dynamic_collect_num_chunk_workers = [X]
```

where X is the number of chunk workers

NOTE: For more information about using **dynamic_collect_num_chunk_workers**, see the section on **Tuning the Collector Load Balancing Process in the Silo.Conf File**.

• dynamic_collect_num_request_workers. You can edit this setting in the silo.conf file on each Database Server or All-In-One Appliance. This setting represents the maximum number of request workers in each worker pool and generally represents the number of collections within a PowerPack that can be processed in parallel. The default value for this parameter is "2" or the number of cores on the Data Collector, whichever is greater.

To change this setting, add the following line to the [LOCAL] section of silo.conf on each Database Server or All-In-One Appliance:

```
dynamic collect num request workers = [X]
```

where:

° X is the maximum number of request workers in each worker pool.

NOTE: For more information about using **dynamic_collect_num_request_workers**, see the section on **Tuning the Collector Load Balancing Process in the Silo.Conf File.**

dynamic_collect_request_chunk_size. You can edit this setting in the silo.conf file on each
Database Server or All-In-One Appliance. This setting represents the maximum number of
collection requests in a chunk and controls how many collections are processed by a single pool or
request workers. The default value for this parameter is "200".

To change this setting, add the following line to the [LOCAL] section of silo.conf on each Database Server or All-In-One Appliance:

```
dynamic collect request chunk size = [X]
```

where:

° X is the maximum number of collection requests in a chunk.

NOTE: For more information about using dynamic_collect_request_chunk_size, see the section on Tuning the Collector Load Balancing Process in the Silo.Conf File.

read_timeout. You can edit this setting in the silo.conf file on each Database Server. This setting
controls the client read timeout for database connections to the collectors. This setting applies only
to the Enterprise Database: Collector Config Push process (config_push.py) that runs on the
primary Database Server.

WARNING: Change this value only if you are instructed to do so by ScienceLogic.

To change this setting, add the following line to the [CONFIG_PUSH] section of silo.conf on all Database Servers in your system.

```
read_timeout=X
```

where:

° X is the read timeout, in seconds.

wait_timeout. You can edit this setting in the silo.conf file on each Database Server. This setting
controls the server wait timeout for database connections to the collectors. This setting applies only
to the Enterprise Database: Collector Config Push process (config_push.py) that runs on the
primary Database Server.

WARNING: Change this value only if you are instructed to do so by ScienceLogic.

To change this setting, add the following line to the [CONFIG_PUSH] section of silo.conf on all Database Servers in your system.

```
wait timeout=X
```

where:

- ° X is the write timeout, in seconds.
- write_timeout. You can edit this setting in the silo.conf file on each Database Server. This setting
 controls the client write timeout for database connections to the collectors. This setting applies only
 to the Enterprise Database: Collector Config Push process (config_push.py) that runs on the
 primary Database Server.

WARNING: Change this value only if you are instructed to do so by ScienceLogic.

```
write timeout=X
```

where:

- ° X is the write timeout, in seconds.
- memory_limit. You can edit this setting in the silo.conf file on each Database Server. This setting controls the memory limit for the Enterprise Database: Collector Config Push process. This setting applies only to the Enterprise Database: Collector Config Push process (config_push.py) that runs on the primary Database Server.

WARNING: Change this value only if you are instructed to do so by ScienceLogic.

To change this setting, add the following line to the [CONFIG_PUSH] section of silo.conf on all Database Servers in your system.

```
memory limit=XY
```

where:

- ° X is a positive integer.
- ° Y represents units. Value can be **KB** (kilobytes), **MB** (megabytes), or **GB** (gigabytes).
- result_wait_timeout. You can edit this setting in the silo.conf file on each Database Server. This setting controls the amount of time the parent Enterprise Database: Collector Config Push process will wait for a message from a child process before abandoning that process. This setting applies only to the Enterprise Database: Collector Config Push process (config_push.py) that runs on the primary Database Server

WARNING: Change this value only if you are instructed to do so by ScienceLogic.

To change this setting, add the following line to the [CONFIG_PUSH] section of silo.conf on all Database Servers in your system.

```
result_wait_timeout=X
```

where:

- ° X is the write timeout, in seconds.
- **shutdown_timeout**. You can edit this setting in the silo.conf file on each Database Server. If the **Enterprise Database: Collector Config Push** process is terminated, this setting controls the amount of time the parent configuration process will wait for its child processes to stop before terminating itself and allowing the child processes to be inherited by init. This setting applies only to the **Enterprise Database: Collector Config Push** process (config_push.py) that runs on the primary Database Server.

WARNING: Change this value only if you are instructed to do so by ScienceLogic.

To change this setting, add the following line to the [CONFIG_PUSH] section of silo.conf on all Database Servers in your system.

```
shutdown timeout=X
```

where:

° X is the write timeout, in seconds.

[PROC_VIRTUAL_MEM_LIMIT]. By default, processes in SL1 have a virtual memory limit of 1 GB.
 You can edit this section in the silo.conf file to overwrite the existing virtual memory limit for a given process in SL1 to ensure that it does not fail by crossing its virtual memory limit.

To change this setting, add the [PROC_VIRTUAL_MEM_LIMIT] section to the silo.conf file. Below that section heading, specify the process you want to update and the new virtual memory limit for that process. Use the following format for each setting:

[process ID]=X

where:

- ° [process ID] is the ID of the process you want to update, as found in master.system_settings_ procs.aid
- ° X is the new virtual memory limit, in bytes

For example, if you wanted to update a process with an ID of "12" with a new 2 GB memory limit, you would write the following under [PROC VIRTUAL MEM LIMIT]:

12=2147483648

• [ADHOC_REPORT_IN_BATCH]. ad hoc reports are processed in a batch process. You can edit this section in the silo.conf file to overwrite the default timing values for certain ad hoc reporting settings.

To change these settings, under the [ADHOC_REPORT_IN_BATCH] section heading in the silo.conf file, specify the time value (in seconds) for each setting. The following settings are included in the [ADHOC_REPORT_IN_BATCH] section:

- * report_execution_delay. This setting controls the amount of time between when a report is scheduled to start running and when it actually begins running. Its default value is 10.
- ° ajax_start_delay. This setting controls the amount of time elapsed before jQuery triggers the ajaxStart event. Its default value is 20.
- ajax_stop_time. This setting controls the amount of time elapsed before jQuery triggers the ajaxStop event after all AJAX requests have completed. Its default value is 1800.
- ° ajax_frequency. This setting controls the frequency with which jQuery fires AJAX requests. Its default value is 10.
- ajax_frequency_decreased_after. This setting controls the amount of time elapsed after which jQuery will fire AJAX requests less frequently than in the ajax_frequency setting. Its default value is 300.

- ajax_decreased_frequency. This setting controls the decreased frequency with which jQuery fires AJAX requests after the amount of time listed in the ajax_frequency_decreased_after setting has elapsed. Its default value is 60.
- report_fail_check_time. This setting controls the amount of time elapsed after which a running report will be considered to have failed. Its default value is 10800.
- auto_page_refresh. This setting controls the amount of time elapsed after which the **Scheduled Report Jobs** page (Report > Create Report > Scheduled Job / Report Archive) automatically refreshes. Its default value is 10.
- about_to_start_time_check. This setting controls the amount of time before a report job is scheduled to start that it will be labeled as "About to start" on the **Scheduled Report Jobs** page (Report > Create Report > Scheduled Job / Report Archive). Its default value is 30.
- * time_unit. This setting controls the unit of time measurement for the ad hoc report settings. Its default value is "second".
- " ui_php_timeout. This setting controls the amount of time elapsed after which an inactive SL1 reports session will time out. Its default value is 1800.
- 5. To save your changes, click **Save** and then close the modal window.

NOTE: All changes to the **silo.conf** file are logged in the SL1 Database Server.

Disabling the User Interface on a Database Server

Database Servers are automatically configured to provide the user interface. If your SL1 system includes an Administration Portal, you might want to disable the user interface capability on your Database Server(s). Perform the following steps to disable the user interface capability on a Database Server:

NOTE: To complete these steps, you must be familiar with how to edit a file using the vi text editor. If you need assistance with these steps, please contact ScienceLogic Support.

- 1. Log in to the console of the Database Server or use SSH to access the server as the **em7admin** user with the appropriate password.
- 2. Execute the following command to open the firewall rules file:

```
sudo vifirewalld
```

3. Add the following lines:

```
rule port port="443" protocol="tcp" reject
rule port port="80" protocol="tcp" reject
```

4. Save the file and exit the vi editor.

5.	Execute the	following	commands t	o undate a	ind restart th	e firewall:
J.	EXECUTE THE	TOTIOWING	Communa	o opadie d	iiid iesiaii iii	e ili ewali,

sudo /opt/em7/share/scripts/update-firewalld-conf.py

Chapter

3

Collector Groups

Overview

This chapter provides an overview of Collector Groups in SL1. A **Collector Group** is a group of SL1 Data Collectors that retrieve data from managed devices and applications so you can use that data in SL1.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon
- To view a page containing all of the menu options, click the Advanced menu icon (....).

This chapter covers the following topics:

What is a Collector Group?	76
Installing, Configuring, and Licensing Data Collectors	76
Technical Information About Data Collectors	77
Viewing the List of Collector Groups	78
Creating a Collector Group	79
Editing a Collector Group	84
Collector Groups and Load Balancing	85
Collector Affinity	88
Creating a Collector Group for Data Storage Only	90
Deleting a Collector Group	90
Assigning a Collector Group for a Single Device	91
Aligning the Collector Group in a Device Template	92
Changing the Collector Group for One or More Devices	92

Managing the Host Files for a Collector Group	92
Processes for Collector Groups	93
Enabling and Disabling Concurrent PowerShell for Collector Groups	94
Enabling and Disabling Concurrent SNMP for Collector Groups	96
Enabling Multi-tenancy for Collector Groups	98

What is a Collector Group?

A **Collector Group** is a group of SL1 Data Collectors. Data Collectors retrieve data from managed devices and applications. This collection occurs during initial discovery, during nightly updates, and in response to policies defined for each managed device. The collected data is used to trigger events, display data in the user interface, and generate graphs and reports.

You can group multiple Data Collectors into a Collector Group. Depending on the number of Data Collectors in your SL1 system, you can define one or more Collector Groups. Each Collector Group must include at least one Data Collector.

On the **Collector Groups** page (Manage > Collector Groups)—or the **Collector Group Management** page (System > Settings > Collector Groups) in the classic SL1 user interface—you can view a list of existing Collector Groups, add a Collector Group, and edit a Collector Group.

NOTE: System upgrades will only consider Data Collectors and Message Collectors that are members of a Collector Group.

Grouping multiple Data Collectors allows you to:

- Create a load-balanced collection system, where you can manage more devices without loss of
 performance. At any given time, the Data Collector with the lightest load manages the next discovered
 device.
- Optionally, create a redundant, high-availability system that minimizes downtime should a failure occur. If a
 Data Collector fails, one or more Collection servers in the Collector Group will handle collection until the
 problem is solved.

NOTE: If you are using a SL1 All-In-One Appliance, most of the sections in this chapter do not apply to your system. For an All-In-One Appliance, a single, default Collector Group is included with the appliance; you cannot create any additional Collector Groups. However, you can view information about the default Collector Group. You can also create a virtual Collector Group, for data storage only. However, the other tasks described in this section do not apply to an All-In-One Appliance.

Installing, Configuring, and Licensing Data Collectors

Before you can create a Collector Group, you must install and license at least one Data Collector. For details on installation and licensing of a Data Collector, see the *Installation* manual.

After you have successfully installed, configured, and licensed a Data Collector, the platform automatically adds information about the Data Collector to the Database Server.

NOTE: For more information on using external credential services that store, collect, and retrieve secret data, see the chapter on "Using External Credential Services" in the **Discovery and Credentials** manual.

Technical Information About Data Collectors

You might find the following technical information about Data Collectors helpful when creating Collector Groups.

Duplicate IP Addresses

A single Collector Group *cannot* include multiple devices that use the same Admin Primary IP Address (this is the IP address the platform uses to communicate with a device). If a single Collector Group includes multiple devices that use the same Primary IP Address or use the same Secondary IP Address, the platform will generate an event. Best practice is to ensure that within a single Collector Group, all IP addresses on all devices are unique.

- During initial discovery, if a device is discovered with the same Admin Primary IP Address as a previously
 discovered device in the Collector Group, the later discovered device will appear in the discovery log, but
 will not be modeled in the platform. That is, the device will not be assigned a device ID and will not be
 created in the platform. The platform will generate an event specifying that a duplicate Admin Primary IP
 was discovered within the Collector Group.
- If you try to assign a device to a Collector Group, and the device's Admin Primary IP Address already exists
 in the Collector Group, the platform will display an error message, and the device will not be aligned with
 the Collector Group.

Open Ports

By default, Data Collectors accept connections only to the following ports:

- TCP 22 (SSH)
- TCP 53 (DNS)
- TCP 123 (NTP)
- UDP 161 (SNMP)
- UDP 162 (Inbound SNMP Trap)
- UDP 514 (Inbound Syslog)
- TCP 7700 (Web Configuration Utility)
- TCP 7707 (one-way communication from the Database Server)

For increased security, all other ports are closed.

Viewing the List of Collector Groups

To view the list of Collector Groups:

- 1. Go to the **Collector Groups** page (Manage > Collector Groups.
- 2. The **Collector Groups** page displays a list of all Collector Groups in your SL1 system. For each Collector Group, the page displays the following:
 - ID. Unique numeric identifier automatically assigned by SL1 to each Collector Group.
 - Name. Name of the Collector Group.
 - Devices Count. Number of devices currently using the Collector Group for data collection.
 - Message Collector Count. Number of Message Collector(s) (if any) associated with the Collector Group.
 - Data Collector Count. Number of Data Collectors in the Collector Group.
 - Organization(s). The organization(s) to which the Collector Group is assigned.

NOTE: The Organization(s) column displays only if multi-tenancy is enabled for Collector Groups. For more information about editing a Collector Group's organizations, see the section on Aligning Collector Groups to Organizations.

TIP: If you do not see one of these columns on the Collector Groups page, click the Select Columns icon (
to add or remove columns. You can also drag columns to different locations on the page or click on
a column heading to sort the list of collector groups by that column's values. SL1 retains any changes you
make to the columns that appear on the Collector Groups page and will automatically recall those
changes the next time you visit the page.

TIP: You can filter the items on this inventory page by typing filter text or selecting filter options in one or more of the filters found above the columns on the page. For more information, see "Filtering Inventory Pages" in the *Introduction to SL1* manual.

Viewing the List of Collector Groups in the Classic SL1 User Interface

To view the list of Collector Groups in the classic SL1 user interface:

- 1. Go to the **Collector Group Management** page (System > Settings > Collector Groups).
- 2. The **Collector Group Registry** pane displays a list of all Collector Groups in your SL1 system. For each Collector Group, the **Collector Group Management** page displays the following:
 - Name. Name of the Collector Group.
 - ID. Unique numeric identifier automatically assigned by SL1 to each Collector Group.

• Organization. The organization(s) to which the Collector Group is assigned. Click the organization icon (1) to edit the Collector Group's organizations.

NOTE: The Organization column displays only if multi-tenancy is enabled for Collector Groups. For more information about editing a Collector Group's organizations, see the section on Aligning Collector Groups to Organizations in the Classic SL1 User Interface.

- # Collectors. Number of Data Collectors in the Collector Group.
- Msg Collector. Name of the Message Collector(s) (if any) associated with the Collector Group.
- # Devices. Number of devices currently using the Collector Group for data collection.
- Edit User. User who created or last edited the Collector Group.
- Edit Date. Date and time the Collector Group was created or last edited.

Creating a Collector Group

You can group multiple Data Collectors into a Collector Group. Depending on the number of Data Collectors in your SL1 system, you can define one or more Collector Groups. Each Collector Group must include at least one Data Collector.

Pre-Deployment Questions for a Collector Group

Consider the following questions before creating a new Collector Group. Your responses to these questions will help you determine how to create and name your new Collector Group:

- Will your Collector Group span regionally close data centers and be configured for maximum resilience?
- Will your users be required to know your Collector Group naming scheme, or will you provide a general Collector Group for them to use as a default (and use specialized Collector Groups for distinct use cases only)?
- Will your Collector Group be structured for minimum latency to the monitored endpoints?
- Consider the following questions about the resilience of your deployment:
 - ° What happens to the ability to monitor if a data center hosting an entire Collector Group goes offline?
 - ° Is the deployment resilient and will it perform well?
 - $^{\circ}$ What is your failure mode? 100% > 0% or !00% > 50% > 0%?

Capacity Planning for a Collector Group

In addition to deciding on your resiliency strategy, look at your failure mode and determine if you are allocating sufficient capacity to achieve a 100% > 50% capacity degradation on a data center failure before failing completely at 0%.

Consider the number of devices in your Collector Group and the number of Data Collectors in your Collector Group to determine if you have overloaded Data Collectors or underpowered Data Collectors.

Defining a Collector Group

To define a new Collector Group:

- 1. Go to the **Collector Groups** page (Manage > Collector Groups).
- 2. Click the [Add Collector Group] button. The Add Collector Group modal appears.
- 3. On the Add Collector Group modal, complete the following fields:
 - Collector Group Name. Type a name for the Collector Group.
 - Generate Alert on Collector Outage. Toggle this option on to specify that the platform should generate an event if a Data Collector has an outage, or toggle it off if the platform should not generate an event if a Data Collector has an outage.
 - All current and future organizations. Toggle this option on to align the Collector Group to all of your SL1 organizations, or toggle it off to specify the organizations to which you want to assign the Collector Group.
 - Limit access to specific organizations. If you toggled off the All current and future organizations option, select the organization(s) to which you want to assign the Collector Group.

NOTE: The All current and future organizations and Limit access to specific organizations fields display only if multi-tenancy is enabled for Collector Groups.

- 4. Click [Save].
- 5. To assign devices to the Collector Group, see the section on aligning single devices with a Collector Group and the section on aligning a device group with a Collector Group.

NOTE: If you need to specify additional Collector Group settings, you can alternatively define a Collector Group in the classic SL1 user interface using the Collector Group Managementpage (System > Settings > Collector Groups.

Defining a Collector Group in the Classic SL1 User Interface

To define a new Collector Group in the classic SL1 user interface:

- 1. Go to the **Collector Group Management** page (System > Settings > Collector Groups).
- 2. In the **Collector Group Management** page, click the **[Reset]** button to clear the values from the fields in the top pane.
- 3. Go to the top pane and enter values in the following fields:
 - Collector Group Name. Name of the Collector Group.

- Collector Failover. Specifies whether you want to maximize the number of devices to be managed or whether you want to maximize reliability. Your choices are:
 - Off (Maximize Manageable Devices). The Collector Group will be load-balanced only. At any given time, the Data Collector with the lightest load handles the next discovered device. If a Data Collector fails, no data will be collected from the devices aligned with the failed Data Collector until the failure is fixed.
 - On (Maximize Reliability). The Collector Group will be load-balanced and configured as a high-availability system that minimizes downtime. If one or more Data Collectors should fail, the tasks from the failed Data Collector will be distributed among the other Data Collectors in the Collector Group. ScienceLogic recommends that you use this setting.
- Generate Alert on Collector Outage. Specifies whether or not the platform should generate an event if a Data Collector has an outage. ScienceLogic recommends that you select Yes for this setting.
- Enable Concurrent SNMP Collection. Specifies whether you want to enable Concurrent SNMP Collection. Concurrent SNMP Collection uses asynchronous I/O for massive concurrency with lower system resource requirements. This means that Data Collectors can collect more data using fewer system resources. Concurrent SNMP Collection also prevents missed polls and data gaps because collection will execute more quickly. For the selected Collector Group, this field overrides the value in the Behavior Settings page (System > Settings > Behavior). Your choices are:
 - Use systemwide default. The Collector Group will use the global settings for Concurrent SNMP Collection configured in the **Behavior Settings** page (System > Settings > Behavior).
 - ° No. Concurrent SNMP Collection is disabled on this Collector Group regardless of the global setting on the **Behavior Settings** page.
 - Yes. Concurrent SNMP Collection is enabled on this Collector Group regardless of the global setting on the **Behavior Settings** page.

NOTE: If the "Data Collection: SNMP Collector" process is disabled on the **Process**Manager page (System > Settings > Admin Processes), the **Enable**Concurrent SNMP Collection option is disabled.

- Enable Concurrent PowerShell Collection. Specifies whether you want to enable Concurrent PowerShell Collection for this collector group. If you make no selection, the default behavior is to "Use systemwide default", which uses the global setting specified on the Behavior Settings page (System > Settings > Behavior). Your choices are:
 - Use systemwide default. The Collector Group will use the global setting for Concurrent PowerShell Collection as it is configured on the **Behavior Settings** page (System > Settings > Behavior).
 - No. Concurrent PowerShell Collection is disabled on this Collector Group regardless of the global setting on the **Behavior Settings** page.

Yes. Concurrent PowerShell Collection is enabled on this Collector Group regardless of the global setting on the **Behavior Settings** page.

NOTE: If the "Data Collection: PowerShell Collector" process is disabled on the Process Manager page (System > Settings > Admin Processes), the Enable Concurrent PowerShell Collection option is disabled.

- Enable Concurrent Network Interface Collection. Specifies whether you want to enable or disable Concurrent Network Interface Collection for this collector group. If you make no selection, the default behavior is to "Use systemwide default", which uses the global setting specified on the Behavior Settings page (System > Settings > Behavior). Your choices are:
 - Use systemwide default. The Collector Group will use the global setting for Concurrent Network Interface Collection as it is configured in the **Behavior Settings** page (System > Settings > Behavior).
 - ° No. Concurrent Network Interface Collection is disabled on this Collector Group regardless of the global setting on the **Behavior Settings** page.
 - ^o Yes. Concurrent Network Interface Collection is enabled on this Collector Group regardless of the global setting on the **Behavior Settings** page.
- Collector Selection. Displays a list of available Data Collectors.
 - To assign an available Data Collector server to the Collector Group, simply highlight it. You can assign one or more Data Collectors to a Collector Group.
 - ° To assign multiple Data Collectors to the Collector Group, hold down the **<Ctrl>** key and click multiple Data Collectors.
- Message Collector. Displays a list of available Message Collectors.
 - ^o To assign an available Message Collector to the Collector Group, simply highlight it. You can assign one or more Message Collectors to a Collector Group.
 - To assign multiple Message Collectors to the Collector Group, hold down the <Ctrl> key and click multiple Message Collectors.
 - Note that a single Message Collector can be used by multiple Collector Groups.

NOTE: When you align a single Message Collector with multiple Collector Groups, the single Message Collector might then be aligned with two devices (each in a separate Collector Group) that use the same primary IP address or the same secondary IP address. If this happens, SL1 will generate an event.

- Collectors Available for Failover. Applies only if you selected "On (Maximize Reliability)" in the Collector Failover field. Specifies the minimum number of Data Collectors that must be available (i.e. with a status of "Available [0]") before a Data Collector failover may occur.
 - For collector groups with only two Data Collectors, this field will contain the value "1 collector".
 - For collector groups with more than two Data Collectors, the field will contain values from a
 minimum of one half of the total number of Data Collectors up to a maximum of one less than
 the total number of Data Collectors.
 - For example, for a collector group with eight Data Collectors, the possible values in this field would be 4, 5, 6, and 7.
 - SL1 will never automatically increase the maximum number of Data Collectors that can fail in a Collector Group. For example, suppose you have a collector group with three Data Collectors. Suppose Collectors Available For Failover field is set to "2". If you add a fourth Data Collector to the collector group, SL1 will automatically set the Collectors Available For Failover field to "3" to maintain the maximum number of Data Collectors that can fail as "one". However, you can override this automatic setting by manually changing the value in the Collectors Available For Failover field.

NOTE: If you set this to half of your available Data Collectors and a 50% Data Collector outage occurs and the remaining Data Collectors are down by one, no rebalance will occur. If you specify one-third of the total number of Data Collectors, then a rebalance will be attempted until your overall capacity falls below one-third of your Data Collectors, thereby maximizing your resiliency but minimizing the opportunity for your system to enter an unproductive rebalancing loop.

CAUTION: If the number of available Data Collectors is less than the value in the Collectors Available For Failover field, SL1 will not failover within the Collector Group. SL1 will not collect any data from the devices aligned with the failed Data Collector(s) until the failure is fixed on enough Data Collector(s) to equal the value in the Collectors Available For Failover field. EM7 will generate a critical event.

- Failback Mode. Applies only if you selected On (Maximize Reliability) in the Collector Failover field. Specifies how you want collection to behave when the outage is fixed. You can specify one of the following:
 - * Automatic. After the failed Data Collector is restored, SL1 will automatically redistribute data-collection tasks among the Collector Group, including the previously failed Data Collector. ScienceLogic recommends that you use this setting.
 - Manual. After the failed Data Collector is restored, you will manually prompt Data Collector to redistribute data-collection tasks by clicking the lightning bolt icon () for the Collector Group.

- Failover Delay (minutes). Applies only if you selected On (Maximize Reliability) in the Collector
 Failover field. Specifies the number of minutes SL1 should wait after the outage of a Data Collector
 before redistributing the data-collection tasks among the other Data Collectors in the group. During
 this time, data will not be collected from the devices aligned with the failed Data Collector(s). The
 default minimum value for this field is 5 minutes. ScienceLogic recommends that you set this field to
 15 minutes.
- Failback Delay (minutes). Applies only if you selected On (Maximize Reliability) in the Collector Failover field and Automatic in the Failback Mode field. Specifies the number of minutes SL1 should wait after the failed Data Collector is restored before redistributing data-collection tasks among the Collector Group, including the previously failed Data Collector. The default minimum value for this field is 5 minutes. ScienceLogic recommends that you set this field to 15 minutes.
- 4. Click the [Save] button to save the new Collector Group.
- To assign devices to the Collector Group, see the section on aligning single devices with a Collector Group in the Classic SL1 User Interface and the section on aligning a device group with a Collector Group.

Editing a Collector Group

To edit a Collector Group:

- 1. Go to the **Collector Groups** page (Manage > Collector Groups).
- 2. Click the **Actions** icon (--) of the Collector Group you want to edit and then select *Edit*. The **Edit Collector Group** modal appears.
- The fields in the Edit Collector Group modal are populated with values from the selected Collector Group.
 You can edit one or more of the fields. For a description of each field, see the section on Defining a
 Collector Group.
- 4. Click [Save] to save any changes to the Collector Group.

Editing a Collector Group in the Classic SL1 User Interface

From the **Collector Group Management** page, you can edit an existing Collector Group. You can add or remove Data Collectors and change the configuration from load-balanced to failover (high availability).

To edit a Collector Group in the classic SL1 user interface:

- 1. Go to the **Collector Group Management** page (System > Settings > Collector Groups).
- 2. In the **Collector Group Management** page, go to the **Collector Group Registry** pane at the bottom of the page.
- 3. Find the Collector Group you want to edit. Click its wrench icon (🏲).
- 4. The fields in the top pane are populated with values from the selected Collector Group. You can edit one or more of the fields. For a description of each field, see the section on **Defining a Collector Group in the**Classic SL1 User Interface.
- 5. Click the [Save] button to save any changes to the Collector Group.

Collector Groups and Load Balancing

To perform initial discovery, SL1 uses a single, selected Data Collector from the Collector Group. This allows you to troubleshoot discovery if there are any problems.

After each discovered device is modeled (that is, after SL1 assigns a device ID and creates the device in the database), SL1 distributes devices among the Data Collectors in the Collector Group. The newest device is assigned to the Data Collector currently managing the lightest load.

This process is known as **Collector load balancing**, and it ensures that the work performed by the Dynamic Applications aligned to the devices is evenly distributed across the Data Collectors in the Collector Group.

SL1 performs Collector load balancing in the following circumstances:

- A new Data Collector is added to a Collector Group
- New devices are discovered
- Failover or failback occurs within a Collector Group (if failover is enabled)
- A user clicks the lightning bolt icon () for a Collector Group to manually force redistribution
- Devices in DCM or DCM-R trees will be loaded on the Data Collector currently assigned to the DCM or DCM-R tree rather than being distributed across the Collector Group. DCM or DCM-R trees will be rebalanced as an aggregate when rebalancing occurs to an available Data Collector with sufficient capacity to sustain the load.

NOTE: Whenever a device is load-balanced from one Data Collector to another, whether due to failover or regular load balancing, the device state information is not transferred to the new Data Collector.

NOTE: The lightning bolt icon () appears only for Collector Groups that contain more than one Data Collector. For Collector Groups with only one Data Collector, this icon is grayed out. This icon does not appear for All-In-One Appliances.

When all of the devices in a Collector Group are redistributed, SL1 will assign the devices to Data Collectors so that all Data Collectors in the collector group will spend approximately the same amount of time collecting data from devices.

Collector load balancing uses two metrics:

- Device Rating. A device's rating is the total elapsed time consumed by either 1) all of the Dynamic
 Applications aligned to the device, or 2) collecting metrics from the device's interfaces, whichever is greater.
 A Collector's load is the sum of the ratings of the devices assigned to the Collector. The balancer tries to
 evenly divide the work performed by Collectors by assigning devices to Collectors using the device ratings
 and Collector loads.
- Collector Load. The sum of the device ratings for all of the devices assigned to a collector.

SL1 performs the following steps during Collector load balancing:

- 1. Searches for all devices that are not yet assigned to a Collector Group.
- 2. Determines the load on each Data Collector by calculating the device rating for each device on a Data Collector and then summing the device ratings.
- 3. Determines the number of new devices (less than one day old) and old devices on each Data Collector.
- 4. On each Data Collector, calculates the average device rating for old devices (sum of the device ratings for all old devices divided by the number of old devices). If there are no old devices, sets the average device rating to "1" (one).
- 5. On each Data Collector, assigns the average device rating to all new devices (devices less than one day old).
- 6. Assigns each unassigned device (either devices that are not yet assigned or devices on a failed Data Collector) to the Data Collector with the lightest load. Add each newly assigned device rating to the total load for the Data Collector.

Tuning Collector Groups in the silo.conf File

With the addition of execution environments to SL1, SL1 sorts data collections in to a two-process-pool model.

SL1 sorts collection requests into groups by execution environment. These groups of collection requests are called "chunks". Each chunk contains a maximum of 200 collection requests, all of which use the same execution environment. SL1 sends each chunk to a chunk worker.

The chunk worker determines the appropriate execution environment for the chunk, deploys the execution environment, and starts a pool of request workers in the execution environment.

The request workers then process the actual collection requests contained in the chunks and perform the actual data collection.

NOTE: For more information about ScienceLogic Libraries and execution environments, see the manual *ScienceLogic Libraries and Execution Environments*.

The following settings are available in the master.system_settings_core database table for tuning globally in a stack, or *in the Silo.Conf file* for tuning locally on a single Data Collector:

Parameter Name	Description	Runtime Default
dynamic_ collect_num_ chunk_ workers	The number of chunk workers. In general, this value controls the number of PowerPacks that can be processed in parallel.	2
dynamic_ collect_num_ request_ workers	The maximum number of request workers in each worker pool. In general, this value controls the number of collections within a PowerPack that can be processed in parallel.	"2" or the number of cores on the Data Collector, whichever is greater

Parameter Name	Description	Runtime Default
dynamic_ collect_ request_ chunk_size	The maximum number of collection requests in a chunk. This value controls how many collections are processed by each pool of requests workers.	200

NOTE: The database values for these parameters are "Null" by default, which specifies that SL1 should use the runtime defaults.

The maximum total number of worker processes used during a scheduled collection is generally dynamic_collect_num_chunk_workers_X_dynamic_collect_num_request_workers.

There might be circumstances where adjustment is necessary to improve the performance of collection.

Example 1: Additional Environments Required

You might need to adjust the values of the collection processes when scheduled collection requires more than two environments.

Because the default number of chunk workers is "2", SL1 can simultaneously process chunks of collection requests for a maximum of two virtual environments. If the collection requests require more than two virtual environments, you can increase parallelism by setting dynamic_collect_num_chunk_workers to match the number of environments.

If you increase dynamic_collect_num_chunk_workers, you might want to decrease dynamic_collect_num_request workers to avoid performance problems caused by too many request workers.

If you cannot increase dynamic_collect_num_chunk_workers because doing so would result in too many request workers, you can decrease dynamic_collect_request_chunk_size to give collection requests for each environment a "fairer share" of the chunk workers.

NOTE: Smaller chunk sizes require more resources to establish the virtual environments and establish more polls of request workers to process the chunks. Conversely, if you want to use fewer resources for establishing virtual environments and creating pools of request worker pools, and you want to use more resources for collection itself, increasing dynamic_collect_request_chunk_size allows more collection requests to be processed by each pool of request workers.

Example 2: Input/Output Bound Collections

You might need to adjust the values of the collection processes when collection requests are input/output (I/O) bound with relatively large latencies.

In this scenario, you can increase dynamic_collect_num_request_workers to improve parallelism. If you increase dynamic_collect_num_request_workers, you might want to decrease dynamic_collect_num_chunk workers to avoid performance problems caused by too many request workers.

CAUTION: Increasing the number of collection processes will increase CPU and memory utilization on the Data Collector, so be careful when increasing the values dramatically.

Before adjusting dynamic_collect_num_request_workers, you need to know the following information:

- The number of CPU cores in the Data Collector
- The current CPU utilization of Data Collector
- The current memory utilization of Data Collector

Start by setting dynamic_collect_num_request_workers to equal the number of CPUs plus 50%. For example: with 8 cores, start by setting dynamic_collect_num_request_workers to 12. If that is insufficient, you can then try 16, 20, 24, and so forth.

If data collections are terminating early, it means that collections are not completed within the 15-minute limit. If this is the case, wait 30 minutes to see results after adjusting the collection values.

Load Balancing and Device State

It is important to note that, whenever a device is load-balanced from one Data Collector to another, whether due to failover or regular load balancing, the device state information is not transferred to the new Data Collector.

In the time immediately after load balancing, if an interface or another aspect of the device changes state at the same time as the device is load-balanced, then the new Data Collector might not register an event that triggers based on a device state change.

Also, if a Dynamic Application that depends on cached data being present attempts to collect data, but the cached data is not yet present on the new Data Collector, the Dynamic Application might initially fail to collect data.

Collector Affinity

Collector Affinity specifies the Data Collectors that are allowed to run collection for Dynamic Applications aligned to component devices. You can define Collector Affinity for each Dynamic Application. Choices are:

- **Default**. If the Dynamic Application is auto-aligned to a component device during discovery, then the Data Collector assigned to the root device will collect data for this Dynamic Application as well. For devices that are not component devices, the Data Collector assigned to the device running the Dynamic Application will collect data for the Dynamic Application.
- Root Device Collector. The Data Collector assigned to the root device will collect data for the Dynamic Application. This guarantees that Dynamic Applications for an entire DCM tree will be collected by a single Data Collector. You might select this option if:

Collector Affinity 88

- The Dynamic Application has a cache dependency with one or more other Dynamic Applications.
- You are unable to collect data for devices and Dynamic Applications within the same Device Component Map on multiple Data Collectors in a collector group.
- If the Dynamic Application will consume cache produced by a Dynamic Application aligned to a nonroot device (for instance, a cluster device).
- Assigned Collector. The Dynamic Application will use the Data Collector assigned to the device running
 the Dynamic Application. This allows Dynamic Applications that are auto-aligned to component devices
 during discovery to run on multiple Data Collectors. This is the default setting. You might select this option
 if:
 - The Dynamic Application has no cache dependencies with any other Dynamic Applications.
 - You want the Dynamic Application to be able to make parallel data requests across multiple Data Collectors in a collector group.
 - The Dynamic Application can be aligned using mechanisms other than auto-alignment during discovery (for instance, manual alignment or alignment via Device Class Templates or Run Book Actions).

Failover for Collector Groups for Component Devices

If you specified **Default** or **Root Device Collector** for Dynamic Applications, and the single Data Collector in the Collector Group for component devices fails, users must create a new Collector Group with a single Data Collector and manually move the devices from the failed Collector Group to the new Collector Group. For details on manually moving devices to a new Collector Group, see the section on **Changing the Collector Group for One or More Devices**.

Collector Groups for Merged Devices

You can merge a physical device and a component device. There are two ways to do this:

- From the Actions menu in the **Device Properties** page (Devices> Device Manager > wrench icon) for either the physical device or the component device.
- From the **Actions** menu in the **Device Manager** page (Devices > Device Manager), select Merge Devices to merge devices in bulk.

You can unmerge a component device from a physical device. You can do this in two ways:

- From the **Actions** menu in the **Device Properties** page (Devices > Device Manager > wrench icon) for either the physical device or the component device, select *Unmerge Devices* to unmerge devices.
- From the **Actions** menu in the **Device Manager** page Devices > Device Manager), select *Unmerge Devices* to unmerge devices in bulk.

When you merge a physical device and a component device, the device record for the component device is no longer displayed in the user interface; the device record for the physical device is displayed in user interface pages that previously displayed the component device. For example, the physical device is displayed instead of the component device in the **Device Components** page (Devices > Device Components) and the **Component**

89 Collector Affinity

Map page (Device Component Map). All existing and future data for both devices will be associated with the physical device.

If you manually merge a component device with a physical device, SL1 allows data for the merged component device and data from the physical device to be collected on different Data Collectors. Data that was aligned with the component device can be collected by the Collector Group for its root device. Data aligned with the physical device can be collected by a different Collector Group.

NOTE: You can merge a component device with only one physical device.

Creating a Collector Group for Data Storage Only

From the **Collector Group Management** page, you can create a **Virtual Collector Group** that serves as a storage area for all historical data from decommissioned devices.

The Virtual Collector Group will store all existing historical data from all aligned devices, but will not perform collection on those devices. The Virtual Collector Group will not contain any Data Collectors or any Message Collectors. **SL1** will stop collecting data from devices aligned with a Virtual Collector Group.

To define a Virtual Collector Group:

- 1. Go to the **Collector Group Management** page (System > Settings > Collector Groups).
- 2. In the **Collector Group Management** page, click the **[Reset]** button to clear values from the fields in the top pane.
- 3. Go to the top pane and enter a name for the virtual Collector Group in the Collector Group Name field.
- 4. Leave all other fields set to the default values. Do not include any Data Collectors or Message Collectors in the Collector Group.
- 5. Click the [Save] button to save the new Collector Group.
- To assign devices to the virtual Collector Group, see the section on aligning single devices with a
 Collector Group and the section on aligning a device group with a Collector Group.

Deleting a Collector Group

To delete a Collector Group:

- 1. Go to the **Collector Groups** page (Manage > Collector Groups).
- 2. Click the **Actions** icon (--) of the Collector Group you want to delete and then select *Delete*.

Deleting a Collector Group in the Classic SL1 User Interface

From the **Collector Group Management** page, you can delete a Collector Group. When you delete a Collector Group, those Data Collectors become available for use in other Collector Groups.

NOTE: Before you can delete a Collector Group, you must move all aligned devices to another Collector Group. For details on how to do this, see the section Changing the Collector Group for One or More Devices.

To delete a Collector Group in the classic SL1 user interface:

- 1. Go to the Collector Group Management page (System > Settings > Collector Groups).
- In the Collector Group Management page, go to the Collector Group Registry pane at the bottom of the page.
- 3. Find the Collector Group you want to delete. Click its bomb icon ().

Assigning a Collector Group for a Single Device

After you have defined a Collector Group, you can align devices with that Collector Group.

To assign a Collector Group to a device:

- 1. From the **Devices** page, click the name of the device that you want to assign to a Collector Group. The **Device Investigator** page opens for that device.
- 2. On the **Device Investigator** page, click the **[Settings]** tab.
- 3. Click the **[Edit]** button. This enables you to change your device settings.
- 4. In the **Collection Poller** field, select the name of the Collector Group that you want to use for collection on the device.
- 5. Click [Save].

Assigning a Collector Group for a Single Device in the Classic SL1 User Interface

After you have defined a Collector Group, you can align devices with that Collector Group.

To assign a Collector Group to a device in the classic SL1 user interface:

- 1. Go to the **Device Manager** page (Devices > Device Manager).
- 2. In the **Device Manager** page, find the device you want to edit. Click its wrench icon (). The **Device Properties** page appears.
- 3. On the **Device Properties** page, select a Collector Group from the **Collection** fields.
- 4. Click the [Save] button to save the change to the device.

Aligning the Collector Group in a Device Template

You can specify a Collector Group in a device template. Then, when you apply the device template to a device, either through discovery or when you apply the device template to a device group or selection of devices, the specified Collector Group is automatically associated with the device(s). Optionally, you can later edit the Collector Group for each device.

For more details on device templates and device groups, see the manual **Device Groups and Device Templates**.

Changing the Collector Group for One or More Devices

You can change the Collector Group for multiple devices simultaneously. This is helpful if you want to reorganize devices or Collector Groups. If you want to delete a Collector Group, you first must first move each aligned device to another Collector Group. In this situation, you might want to change the Collector Group for multiple devices simultaneously.

To change the Collector Group for multiple device simultaneously:

- 1. Go to the **Device Manager** page (Devices > Device Manager).
- 2. In the **Device Manager** page, click on the heading for the **Collection Group** column to sort the list of devices by Collector Group.
- 3. Select the checkbox for each device that you want to move to a different Collector Group.
- 4. In the **Select Action** field (in the lower right), go to **Change Collector Group** and select a Collector Group.
- 5. Click the [Go] button. The selected devices will now be aligned with the selected Collector Group.

Managing the Host Files for a Collector Group

The **Host File Entry Manager** page allows you to edit and manage host files for all of your Data Collectors from a single page in the SL1 system. When you create or edit an entry in the **Host File Entry Manager** page, SL1 automatically sends an update to every Data Collector in the specified Collector Group.

The Host File Entry Manager page is helpful when:

- The SL1 system does not reside in the end-customer's domain
- The SL1 system does not have line-of-sight to an end-customer's DNS service
- A customer's DNS service cannot resolve a host name for a device that the SL1 system monitors

For details, see the section on Managing Host Files.

Processes for Collector Groups

For troubleshooting and debugging purposes, you might find it helpful to understand the ScienceLogic processes that affect a Collector Group.

NOTE: You can view the list of all processes and details for each process in the **Process Manager** page (System > Settings > Admin Processes).

- The Enterprise Database: Collector Task Manager process (em7_ctaskman) process distributes
 devices between Data Collectors in a Collector Group, to load-balance the collection tasks. The process
 runs every 60 seconds and also checks the license on each Data Collector. The Enterprise Database:
 Collector Task Manager process (em7_ctaskman.py) redistributes devices between collectors when:
 - A Collector Group is created.
 - ° A new Data Collector is added to a Collector Group.
 - ° Failover or failback occurs within a Collector Group.
 - $^\circ$ A user clicks on the lightning bolt icon ($^{/\!\!\!/}$) for a Collector Group, to manually force redistribution.
- The Enterprise Database: Collector Data Pull processes retrieves information from each Data Collector in a Collector Group. The process pulls data from the in_storage tables on each Data Collector. The retrieved information is stored in the Database Server.
 - Enterprise Database: Collector Data Pull, High F (em7_hfpulld). Retrieves data from each Data Collector every 15 seconds (configurable).
 - Enterprise Database: Collector Data Pull, Low F (em7_lfpulld). Retrieves data from each Data Collector every five minutes.
 - Enterprise Database: Collector Data Pull, Medium (em7_mfpulld). Retrieves data from each Data Collector every 60 seconds.
- The Enterprise Database: Collector Config Push process (config_push.py) updates each Data Collector with information on system configuration, configuration of Dynamic Applications, and any new or changed policies. This process runs once every 60 seconds and checks for differences between the configuration tables on the Database Server and the configuration tables on each Data Collector. The list of tables to be synchronized is stored in master.definitions_collector_config_tables on the Database Server.
- Asynchronous Processes (for example, discovery or programs run from the Device Toolbox page).
 Asynchronous processes need to be run immediately and cannot wait until the Enterprise Database:
 Collector Config Push process (config_push.py) runs and tells the Data Collector to run the asynchronous process. Therefore, SL1 uses a stored procedure and the EM7 Core: Task Manager process (em7) to trigger asynchronous processes on both the Database Server and Data Collector.
 - If a user requests an asynchronous process, a stored procedure on the Database Server inserts a new row in the table master logs.spool process on the Database Server.

- Every three seconds, the EM7 Core: Task Manager process (proc_mgr.py) checks the table master_ logs.spool process on the Database Server for new rows.
- of the asynchronous process needs to be started on a Data Collector, a stored procedure on the Database Server inserts the same row into the table master_logs.spool_process on the Data Collector.
- Every three seconds, the EM7 Core: Task Manager process (em7) checks the table master_ logs.spool process on the Data Collector for new rows.
- of the EM7 Core: Task Manager process (em7) on the Data Collector finds a new row, the specified asynchronous process is executed on the Data Collector.

Enabling and Disabling Concurrent PowerShell for Collector Groups

To improve the process of collecting data via PowerShell, you can enable Concurrent PowerShell Collection. Concurrent PowerShell Collection allows multiple collection tasks to run at the same time with a reduced load on Data Collectors. Concurrent PowerShell Collection also prevents missed polls and data gaps because collection will execute more quickly. As a result, Data Collectors can collect more data using fewer system resources.

When you use the PowerShell Collector for Concurrent PowerShell Collection, the collection process can bypass failed or paused collections, reduce collection time, and reduce the number of early terminations (sigterms) that occur with data collection. The PowerShell Collector is an independent service running as a container on a Data Collector.

You can enable one or more Collector Groups to use concurrent PowerShell collection, and you can collect metrics for concurrent PowerShell collection.

NOTE: Concurrent PowerShell Collection is for PowerShell Performance and Performance Configuration Dynamic Application types and does not include Snippet Dynamic Applications which happen to run PowerShell commands.

NOTE: Concurrent PowerShell Collection is not available in military unique deployments (MUD) or STIG-compliant deployments.

For more details on concurrent PowerShell collection, see the manual *Monitoring Windows Systems with PowerShell*, the chapter on Concurrent PowerShell.

Enabling Concurrent PowerShell on All Collector Groups

To enable concurrent PowerShell collection service for all collector groups:

1. Go to the **Database Tool** page (System > Tools > DB Tool).

NOTE: The **Database Tool** page displays only for users that have sufficient permissions to access that page.

2. Enter the following in the **SQL Query** field:

```
INSERT INTO master.system_custom_config (`field`, `field_value`)
VALUES ('enable powershell service', '1');
```

Disabling Concurrent PowerShell on All Collector Groups

To disable concurrent PowerShell collection service for all collector groups:

1. Go to the **Database Tool** page (System > Tools > DB Tool).

NOTE: The **Database Tool** page displays only for users that have sufficient permissions to access that page.

2. Enter the following in the **SQL Query** field:

```
UPDATE master.system_custom_config SET field_value=0 where
field='enable powershell service';
```

Enabling Concurrent PowerShell on a Specific Collector Group

To enable concurrent PowerShell collection for a specific collector group:

1. Go to the **Database Tool** page (System > Tools > DB Tool).

NOTE: The **Database Tool** page displays only for users that have sufficient permissions to access that page.

2. Enter the following in the **SQL Query** field:

where:

collector_group_ID is the collector group ID. You can find this value in the **Collector Group Management** page (System > Settings > Collector Groups).

Disabling Concurrent PowerShell on a Specific Collector Group

To disable concurrent PowerShell collection for a specific collector group:

1. Go to the **Database Tool** page (System > Tools > DB Tool).

NOTE: The **Database Tool** page displays only for users that have sufficient permissions to access that page.

2. Enter the following in the **SQL Query** field:

```
UPDATE master.system_custom_config SET field_value=0 where
field='enable powershell service CUGx';
```

where:

collector_group_ID is the collector group ID. You can find this value in the **Collector Group Management** page (System > Settings > Collector Groups).

Enabling and Disabling Concurrent SNMP for Collector Groups

To increase the scale for SNMP collection, you can enable **Concurrent SNMP Collection**. Concurrent SNMP Collection uses the standalone container called the SL1 SNMP Collector.

The SNMP Collector is an independent service that runs as a container on a Data Collector. When you enable Concurrent SNMP Collection, each Data Collector will contain four (4) SNMP Collector containers.

NOTE: On each Data Collector, SL1 will restart each of the SNMP Collector containers periodically to ensure that each container remains healthy. When one SNMP Collector container is restarted, the other three SNMP Collector containers continue to handle the workload.

With Concurrent SNMP Collection, SNMP collection tasks can run in parallel. A single failed task will not prevent other tasks from completing.

Concurrent SNMP Collection provides:

- Improved throughput for SNMP Dynamic Applications
- Reduced use of resources on each Data Collector
- More dependable collection from high-latency Devices

NOTE: Concurrent SNMP Collection is not available in military unique deployments (MUD) or STIG-compliant deployments.

Enabling and Disabling Concurrent SNMP for All Collector Groups

This feature is disabled by default.

To enable Concurrent SNMP Collection in SL1:

- 1. Go to the **Behavior Settings** page (System > Settings > Behavior).
- 2. Check the Enable Concurrent SNMP Collection field.
- 3. Click [Save].

TIP: If you do not want all of your SL1 Collectors to use Concurrent SNMP Collection, you can specify which Collector Units should use it in *Enabling a Collector Group to Use Concurrent SNMP Collection*.

Enabling and Disabling Concurrent SNMP for Collector Groups

Depending on the needs of your SL1 environment, you can enable or prevent a Collector Group from using concurrent SNMP collection.

To enable Concurrent SNMP Collection with a SL1 Collector Group:

- 1. Go to the **Collector Group Management** Page (System > Settings > Collector Groups).
- 2. Click the wrench icon (🎤) for the Collector Group you want to edit. The fields at the top of the page are updated with the data for that Collector Group.
- 3. Select an option in the **Enable Concurrent SNMP Collection** drop-down field:
 - Use system-wide default. Select this option if you want this Collector Group to use or not use
 Concurrent SNMP Collection based on the Enable Concurrent SNMP Collection field on the
 Behavior Settings page. This is the default.
 - **Yes**. Select this option to enable Concurrent SNMP Collection for this Collector Group, even if you did not enable it on the **Behavior Settings** page.
 - **No**. Select this option to prevent this Collector Group from using Concurrent SNMP Collection, even if you did enable it on the **Behavior Settings** page.
- 4. Update the remaining fields as needed, and then click [Save].

Enabling Multi-tenancy for Collector Groups

To support multi-tenancy, SL1 allows you to align Collector Groups with one, multiple, or all organizations in SL1. When you align an organization to a Collector Group, you control who can view details about that Collector Group and who can apply the Collector Group in SL1.

By default, newly created Collector Groups are aligned to all organizations. However, you can update the organization setting for a Collector Group if you have multi-tenancy enabled for Collector Groups.

When multi-tenancy is enabled:

- An administrative user can update the organization alignment for all Collector Groups.
- Non-administrative users can update all Collector Groups that are aligned to all organizations or the
 organizations to which the user belongs.

NOTE: If you enable multi-tenancy for Collector Groups, you might encounter a situation where a device is not aligned to a Collector Group if they do not belong to the same organization.

CAUTION: If you enable multi-tenancy for Collector Groups, ScienceLogic strongly recommends that you do not disable it at a later date.

To enable multi-tenancy for Collector Groups:

1. Go to the **Database Tool** page (System > Tools > DB Tool).

NOTE: The **Database Tool** page displays only for users that have sufficient permissions to access that page.

- 2. Select "master" as the database.
- 3. Type the following in the **SQL Query** field:

```
UPDATE master.system settings core SET enable cug orgs=1
```

4. Click [Go].

Aligning Collector Groups to Organizations

To align existing Collector Groups to organizations:

- 1. Go to the **Collector Groups** page (Manage > Collector Groups).
- 2. Click the **Actions** icon (--) of the Collector Group you want to edit and then select *Edit*. The **Edit Collector Group** modal appears.
- 3. On the **Edit Collector Group** modal, complete the following fields:

- All current and future organizations. Toggle this option on to align the Collector Group to all of your SL1 organizations, or toggle it off to specify the organizations to which you want to assign the Collector Group.
- Limit access to specific organizations. If you toggled off the All current and future organizations option, select the organization(s) to which you want to assign the Collector Group.
- 4. Click [Save] to save any changes to the Collector Group.

Aligning Collector Groups to Organizations in the Classic SL1 User Interface

To align existing Collector Groups to organizations in the classic SL1 user interface:

- 1. Go to the **Collector Group Management** page (System > Settings > Collector Groups).
- 2. In the **Collector Group Registry** pane, click the Organization icon () of the Collector Group you want to align to an organization. The Align Organizations modal appears.
- 3. In the Align Organizations modal, complete the following fields:
 - Collector Group Availability. Select All Organizations to align the Collector Group to all of your SL1 organizations, or select Aligned Organizations Only to specify the organizations to which you want to assign the Collector Group.
 - Aligned Organizations. If you selected Aligned Organizations Only in the Collector Group Availability field, select the organization(s) to which you want to assign the Collector Group.
- 4. Click [Save].

Chapter

4

Daily Health Tasks

Overview

The tasks in this chapter help you monitor the health of your SL1 system. You should perform these tasks daily (or more frequently, if you require) to gather information about the overall status of your SL1 system and to maintain operational stability.

For more information about the daily maintenance process and how to troubleshoot common issues related to that process, watch this video: https://www.youtube.com/watch?v=mtwe 2HvOio.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon
- To view a page containing all of the menu options, click the Advanced menu icon (···).

This chapter covers the following topics:

What is a Healthy SL1 System?	101
SL1 Self-Healing	104
Monitoring System Events	104
Monitoring System Processes	107
Monitoring the Status of Each Appliance	110
Logging in SL1 Version 11.3.0 and Later	113
Monitoring User Actions and Events on the Audit Logs Page	120
Using auditd to Monitor Sensitive Files	123
Manitoring the Status of Data Collectors	125

What is a Healthy SL1 System?

The following table presents a broad list of focus areas for SL1 health that are important to track for all SL1 systems. Where a specific automated check is available, it is included in the table.

Focus Area	Check	Background	Specific Operation	Result
Patch level	Version has been updated within last 12 months	Software updates are released at least quarterly and include security and stability improvements.	Quarterly manual review of available and planned software updates from ScienceLogic	Plan to keep all SL1 platforms updated within 12 months of the latest release.
Response time	API response times for standard requests are within five seconds	API response times are highly dependent on the size of the response, however all SL1 systems should respond to a simple request without delay.	/api/organization/0	Returns a response set for the "system" organization (id 0).
Central storage capacity	At least 20% of local database storage is free and available for new data	The InnoDB database file will auto- expand but never shrink. When data is removed from the database, space is made available for future use.	Support PowerPack - Support: InnoDB Size	Built-in alerts for the Support PowerPack default to 80% used for major and 90% for critical.
CPU Consumption	System CPU utilization and load average	Both Collectors and Databases can become CPU constrained, leading to unhealthy performance characteristics.	Operating system measures of CPU utilization and load average	Load average should be at or below the system's available core count. CPU utilization of a 5 min collection should not be above 80%, 70% if hyperthreading is enabled.
Memory Consumption	Avoid swap usage	The MariaDB	Operating system measure of swap usage	Swap usage < 50%

Focus Area	Check	Background	Specific Operation	Result
		database will make use of available memory for caching purposes over time, but no SL1 system should require regular swapping, which can lead to extremely poor performance.		
Performance Data Processing	The central system is keeping up with all collection processing.	It is normal to have some backlog of "MF" data, a busy system may normally have 10,000 rows or more between each processing cycle, but they should be completely processed within each cycle (backlog should not build).	Built-in MF rows-behind compared with MF object processing rate	Backlog time < 1 processing cycle
Event Processing	The central system is keeping up with all event processing.	It is normal to have some backlog of "HF" data. A busy system may normally have 10,000 rows or more between each processing cycle, but these rows should be completely processed within each	Built-in HF rows-behind compared with HF object processing rate	Backlog time < 1 processing cycle

Focus Area	Check	Background	Specific Operation	Result
		cycle (backlog should not build)		
Run Book Automation (RBA)	The central system is keeping up with all RBA processing.		Built-in alerting in the RBA scheduler will notify if the system is falling behind.	No critical events starting with the following phrase: "The automation engine is still processing"
Performance Data Collection	Collection of data is completing as scheduled.	Collection that is unbalanced or overloaded, or target devices that are misconfigured or unresponsive can result in collection not completing successfully.	SL1 Operational Insights PowerPack	Check for occurrences of "sigterming" collection. The Operational Insights PowerPack makes this easy to navigate using a dashboard.
Asynchronous Message Processing	Message collection is keeping up with asynchronous syslog and SNMP trap messages.	Data Collectors, Message Collectors, and All-in-One appliances receive	Built-in alert for suppressing of messages from "spamming" devices	By default SL1 will suppress messages from devices generating at a rate of > 25/sec/device with a built-in alert.
System Maintenance	Daily maintenance tasks are completing normally	The primary daily maintenance task (scheduled nightly outside of core business hours) is to prune old data from the SL1 database, which is an essential activity for long term	Regular check of the system log	Daily maintenance tasks not being terminated due to an incomplete status.

Focus Area	Check	Background	Specific Operation	Result
		health.		
System Backup	Backups completing per schedule.	SL1 supports both configuration- only and full backups. Both should be used since they support different recovery models	Regular check of the system log	The system log will show reports of backup completion and duration.

SL1 Self-Healing

For the SL1 classic User Interface, SL1 provides three self-healing jobs that are performed on the Database Server or All-In-One Appliance. These jobs:


- automatically set "s-em7-core:s-em7-core" as the owner and group for the file "silo.log"
- automatically restart the process em7_patch_manager if it is stuck in deactivating mode
- automatically kill queries that have run for longer than 1 hour and logs each query

Monitoring System Events

To view the entries in the **System Logs**:

1. Go to the **System Logs** page (System > Monitor > System Logs).

SL1 Self-Healing



- 2. On the **System Logs** page, pay special attention to any log entry tagged as *Critical* or *Major*. These entries might require additional diagnostics.
- 3. For each log entry, the **System Logs** page displays:
 - Date. Date and time the log entry was generated.
 - Module. Name of the appliance that generated the log entry.
 - Severity. Specifies the severity assigned to the log entry. The choices are:
 - ° Healthy
 - ° Notice
 - ° Minor
 - ° Major
 - ° Critical
 - Message. Descriptive text included in the log entry.


Searching the System Logs

When viewing the **System Logs**, you might want to sort the entries by date or by log message. This is helpful when you want to view information about a specific occurrence of a system event.

You can also filter the list of logs by appliance, severity, and date.

To search the system logs:

1. Go to the **System Logs** page (System > Monitor > System Logs).



- The first two filters at the top of the System Logs page let you filter the list of logs by appliance, severity, and
 date. Select a sort type from the first filter (Appliance, Severity, or From Date) and then type or select filter
 criteria in the next filter to the right.
- 3. Click the [Search] button to see the results of the filters.
- 4. The next two search fields at the top of the **System Logs** page allow you to search for log entries by message, date, or module.
 - Search where. Specifies the parameter you want to search by. You can select from the following:
 - Search Message. Searches all log entries for those that match the text that you enter in the regular expression field.
 - ° Search Module ID. Searches all log entries for those that have the same module ID text as that entered in the regular expression field.
 - Search Date = (Y-m-d H:i:s). Searches all log entries for those that have a date and time that is equal to the date entered in the regular expression field.
 - Search Date > (Y-m-d H:i:s). Searches all log entries for those that have a date and time that is later than the date entered in the regular expression field.
 - Search Date Like (Y-m-d H:i:s). Searches all log entries for those that have a date and time that is similar to the date entered in the regular expression field.
 - Search Date Like != (Y-m-d H:i:s). Searches all log entries for those that have a date and time that is **not** similar to the date entered in the regular expression field.

- regular expression. In this field you manually enter the text to search for. You can use the following special characters in this field:
 - * Match zero or more characters preceding the asterisk. For example:

```
"dell*" would match "dell", "dell2650", "dell7250" and "dell1700N".
```

- % Match zero or more characters preceding the asterisk. This special character behaves in the same way as the asterisk.
- 5. When you click the **[Search]** button, the **System Logs** page will be refreshed and will display only the log entries that match the search parameters.

Deleting Entries from the System Logs

To save space, you might want to remove some or all log entries from the system log.

There are two ways to delete entries from the **System Logs** page:

- 1. Go to the **System Logs** page (System > Monitor > System Logs).
- 2. In the System Logs page, click the [Purge] button to delete all entries from the System Logs.

Or:

- 1. Go to the **System Logs** page (System > Monitor > System Logs).
- 2. In the **System Logs** page, highlight each entry you want to delete. To select multiple entries, right-click while holding down the [**<Ctrl>**] key.
- 3. Click the [Delete] button to delete all the selected entries from the System Logs.

Monitoring System Processes

The **System Processes** page (System > Monitor > Admin System Processes or System > Monitor > System Processes in the classic user interface) allows you to view read-only information about the execution of SL1's system processes. System Processes gather, manipulate, and publish the data used in SL1. These system processes can be configured and debugged in the **Process Manager** page (System > Settings > Admin Processes).

NOTE: If you work frequently with ScienceLogic Support, ensure that you verify periodically which processes are running in debug mode, and disable debug mode as soon as is reasonable. This will reduce the noise generated to your log files and will reduce load on the /var/log/em7 partition on the central database.

Viewing the List of System Processes

To view the list of system processes for all appliances:

[&]quot;*dell*" would match "mydell", "dell", "dell2650", "dell7250" and "dell1700N".

- 1. Go to the **System Processes** page (System > Monitor > Admin System Processes).
- 2. The **System Processes** page displays the following for each process:
 - **Appliance**. The appliance where the process ran or is currently running. This field will contain the device name of the appliance.
 - Process. Name of the process.
 - ID. Unique numeric ID automatically assigned to the process by SL1.
 - Start Time. Date and time at which the process started running.
 - End Time. Date and time at which the process stopped running.
 - Duration. Amount of time, in hours, minutes, and seconds, for which the process ran.
 - Frequency. Frequency with which SL1 launches the process. Possible values are:
 - Asynchronous. The process is launched in response to a system event or user request. Asynchronous events display a value of "-1" (negative one) in this column.
 - Always. The process always runs while SL1 is running. Always running processes display a value of "0" (zero) in this column.
 - The process runs at intervals in minutes ranging from 1 Minute to 1440 Minutes (Daily).
 - Percent. Percent of Run Length (defined in the Process Manager page) currently in use by the
 process.
 - Instances. This field is not currently in use.
 - Max Instances. Maximum number of instances of the process that have run in parallel.
 - **Processed**. Number of records processed by this run of the process.
 - Errors. Number of errors encountered by this run of the process.

Recommended System Maintenance

ScienceLogic recommends that you take the following actions on a regular basis to reduce outages as much as possible.

Daily:

- Review "SL1 Operational Insights: Database Performance" classic dashboard
- Review "SL1 Operational Insights: Collector Performance" classic dashboard
- Review "SL1 Operational Insights: System Log Summary" classic dashboard
- Review "SL1 Operational Insights: Backup History" classic dashboard

Weekly:

- Run the System Status Script and review
 - Address every error item in the report
 - ° Read Knowledge Base articles
 - Open tickets for issues when help from SL1 Support is needed

Monthly:

- Review capacity items
 - You must understand License Usage and how to project future capacity

Quarterly:

- Audit User Profile access to verify that it meets expected needs
- Audit DNS servers and Timeservers on all collectors

Searching and Filtering the List of System Processes

The **System Processes** page includes ten filters. You can filter the list of processes by one or multiple of the following parameters: appliance, process name, start time, end time, duration, frequency, percent, max instances, processed, and errors. Only processes that meet all the filter criteria will be displayed in the **System Processes** page.

You can filter by one or more of the following parameters. The list of system processes is dynamically updated as you select each filter.

- For eight of the filters, you must enter text to match against. The user interface will search for processes that match the text, including partial matches. Text matches are not case sensitive. You can use the following special characters in each filter:
 - °, Specifies an "or" operation. For example:
 - "dell, micro" would match all values that contain the string "dell" OR the string "micro".
 - ° ! Specifies a "not" operation. For example:
 - "!dell" would match all values that do not contain the string "dell".
- **Appliance**. You can enter text to match, including special characters, and the **System Processes** page will display only processes that have a matching appliance name.
- **Process**. You can enter text to match, including special characters, and the **System Processes** page will display only processes that have a matching process name.
- *ID*. You can enter text to match, and the **System Processes** page will display only processes that have a matching ID.
- **Start Time**. Only those processes that match all the previously selected fields and have the specified start date and time will be displayed. The choices are:
 - ° All. Display processes with all start dates and times.

- ^o Last Minute. Display only processes that started within the last minute.
- ^o Last Hour. Display only processes that started within the last hour.
- ^o Last Day. Display only processes that started within the last day.
- ^o Last Week. Display only processes that started within the last week.
- ^o Last Month. Display only processes that started within the last month.
- ^o Last Year. Display only processes that started within the last year.
- *End Time*. Only those processes that match all the previously selected fields and have the specified end date and time will be displayed. The choices are:
 - ° All. Display processes with all end dates and times.
 - ^o Last Minute. Display only processes that ended within the last minute.
 - Last Hour. Display only processes that ended within the last hour.
 - ^o Last Day. Display only processes that ended within the last day.
 - ^o Last Week. Display only processes that ended within the last week.
 - ^o Last Month. Display only processes that ended within the last month.
 - ^o Last Year. Display only processes that ended within the last year.
- **Duration**. You can enter text to match, including special characters, and the **System Processes** page will display only processes that have a matching duration.
- **Frequency**. You can enter text to match, including special characters, and the **System Processes** page will display only processes that have a matching frequency.
- **Percent**. You can enter text to match, including special characters, and the **System Processes** page will display only processes that have a matching percent.
- Instances. This field is not currently in use. It is not recommended to filter the System Processes by this field.
- Max Instances. You can enter text to match, including special characters, and the System Processes page will display only processes that have a matching number of Max Instances.
- **Processed**. You can enter text to match, including special characters, and the **System Processes** page will display only processes that have a matching number of records processed.
- *Errors*. You can enter text to match, including special characters, and the **System Processes** page will display only processes that have a matching number of errors.

Monitoring the Status of Each Appliance

The **Appliance Manager** page (System > Settings > Appliances) provides for global appliance configuration and management for your entire system or stack. This includes collector group and load distribution, version information, license status, and other items that are important when you upgrade.

From the **Appliance Manager** page, you can also access the Web Configuration Utility for each ScienceLogic appliance by clicking the toolbox icon(), or you can access the database administration tool for each Database Server or All-In-One Appliance by clicking the gear icon ().

For each Database Server, Data Collector, and Message Collector, you can click on the magnifying-glass icon (

i) to view the output of the system status script for that appliance.

During upgrade, table cells will highlight known, pending action items that must be done to successfully complete an upgrade, such as highlighting an SL1 appliance that is running a different version of SL1 than the Database Server.

This page is useful for ensuring that every Data Collector is assigned to a Collector Group before you begin an upgrade. In some cases, the Data Collector might be assigned to an empty Collector Group, if the collector is new

You can also use this page to ensure that Data Collector load is near or below the system requirements for each collector.

To edit and view information about an SL1 appliance:

- 1. Go to the **Appliance Manager** page (System > Settings > Appliances).
- 2. Locate the SL1 appliance you want to edit. Click its wrench icon (🎤). The fields in the top pane are populated with values from the selected SL1 appliance.
- 3. You can edit one or more of the following fields:
 - Host Name. Name of the appliance.
 - IP Address. Primary IP address for the appliance.
 - Model Type/Module Type. Type of appliance. If an appliance is added with the wrong appliance type, SL1 generates a critical error to notify the user. The types include:
 - All In One Server
 - ° Database
 - Administration Portal
 - Data Collection Unit
 - ^o Message Collection Unit

NOTE: The combination appliance with a Database Server and an Administration Portal on a single appliance will appear with *Module Type* of *Database*. The combination appliance with a Message Collection Unit and a Data Collection Unit will appear with *Module Type* of *Data Collection Unit*.

- Integration Server (SL1 PowerFlow)
- **Description**. Description of the appliance.

- 4. You can edit two optional fields for Data Collector or Message Collector.
 - DB User. User name that can access the MariaDB database on the Data Collector or Message Collector.
 - **DB Password**. Password that allows access the MariaDB database on the Data Collector or Message Collector.

If you are using AWS RDS with your SL1 System, you must define the **DB User** and **DB Password** for each Data Collector or Message Collector.

NOTE: ScienceLogic recommends that you vary the Data Collector and Message Collector database credentials for enhanced per-appliance security. This greatly enhances the security of your central database by disallowing a successful attack to go unnoticed on your Data Collector and then succeed without failure on the central database.

The Appliance Manager page also displays the following columns:

- ° **Collector Group**. For Data Collectors and All-In-One Appliances, specifies the Collector Group associated with the appliance.
- Build. Specifies the latest build installed on the appliance.

NOTE: If an SL1 appliance is running a different version of SL1 than the Database Server, the corresponding cell in the **Build** column will be highlighted.

- MariaDB. Specifies the version of MariaDB running on the All-In-One Appliance, Database Server, Data Collector, or Message Collector.
- Capacity. For Database Servers, specifies the licensed capacity of the appliance.
- ^o **Allocation**. For Data Collectors, specifies the number of devices aligned with the appliance.
- ID. Unique numeric ID, automatically assigned by the platform to each appliance in the Appliance Manager page.
- Validated. Specifies whether the license is valid.
- Endpoint. SL1 Agent endpoint for the Gen 1 Agent.
- Needs Reboot?. Specifies whether the appliance requires reboot to add latest kernel or security updates. This column is updated every 30 minutes. Hover your mouse to determine why the reboot is required and information about kernel version, packages, and last reboot.
- Task Manager Paused? . Specifies whether the task manager service (em7) is paused. This value is updated every two minutes.
- Edit Date. Date the appliance's information was discovered or last edited.

- Edit User. User who last edited the appliance's information.
- ° Create Date. Date and time the appliance was registered and licensed.
- 5. To view the Web Configuration Utility for an appliance, where you can track license data, interfaces, and other device settings, click the Appliance Manager icon (). Use the same login credentials that you used to log into SL1, and close the pop-up window for the Utility when you are done.
- 6. If an SL1 appliance is running a different version of SL1 than the Database Server, that appliance is highlighted in the **Appliance Manager** page. The version number, if known, is listed in the **Build** column.
- 7. For all SL1 appliances, SL1 runs the system status script every 15 minutes. You can click the logs icon ((a)) to view the results of the latest system status script.
- 8. If you are logging in to the "sl1admin" account on an appliance, you can click the padlock () icon for that appliance to get a one-time password. For more information, see "Using the sl1admin Account" in the Role-Based User Accounts chapter of the **Organizations and Users** manual.
- 9. For Database Servers, you can click the gear icon (*) to access the phpMyAdmin interface for the Database Server. In this interface, you can view all the database tables on the Database Server.
- For Data Collectors and Message Collectors, you can click the lightning bolt icon () to manually force
 the Database Server to send the latest configuration information.

NOTE: The bomb icon () does not appear for Database Servers that are not configured for High Availability or Disaster Recovery. The bomb icon does not appear for Database Servers that are configured as the primary database in a High Availability or Disaster Recovery configuration.

11. Click the **[Save]** button to save any changes. Click the **[Save As]** button to save your changes to a new appliance name.

Logging in SL1 Version 11.3.0 and Later

In SL1 version 11.3.0 and later, configuration files for Rsyslog were completely updated. This new configuration gives you the option of configuring TLS to send or receive syslog message, forwarding logs to a security information and event management (SIEM) tool, filtering inbound logs, and other features. These options are described in detail in the following sub-topics.

WARNING: Any existing modifications you made to your rsyslog configurations to support log forwarding, filtering, or TLS reception before SL1 version 11.3.0 will be removed. To re-configure any custom rules using the appropriate syntax, see the sub-topics below.

The following options are available:

- Configure TLS to send or receive syslog messages
- Forward locally generated syslogs to one or more external systems for auditing or processing
- Specify alternate inbound TCP or UDP ports for listening for syslog messages
- Adjust the priority filter for inbound messages
- Filter or discard inbound messages

Configuring TLS Certificates

You will need to configure the TLS certificates before you can send or receive syslogs using SSL/TLS.

Requirements:

- A PEM-encoded CA Certificate
- A PEM-encoded Certificate
- A PEM-encoded Private Key
- All three files uploaded to the /etc/pki/rsyslog/ directory

NOTE: A Require TLS Validation for Gen 0 Agent checkbox was added to the Behavior Settings page (System > Settings > Behavior). When this checkbox is selected, Gen 0 agents that operate outside of the Extended Architecture will require TLS validation to upload data. To enable the Require TLS Validation for Gen 0 Agent checkbox, all Data Collectors and Message Collectors that have agents uploading data to them must have a valid and signed certificate so that the TLS validation can complete the upload request.

To configure the TLS certificates:

1. Go to the console of the SL1 server or use SSH to access the server and log in as user **em7admin** with the password you configured during setup.

2. Locate the /etc/rsyslog.d/siteconfig.d/global_tls.conf file and edit the file to reference the CA Certificate, Certificate, and Private Key. Uncomment the global section if needed. For example:

TLS certificates must be defined here when using inbound TLS or TLS forwarding.

```
global(
```

```
DefaultNetstreamDriver="gtls"
```

DefaultNetstreamDriverCAFile="/etc/pki/rsyslog/exampleCA.crt"

DefaultNetstreamDriverCertFile="/etc/pki/rsyslog/mycert.crt"

DefaultNetstreamDriverKeyFile="/etc/pki/rsyslog/mycert.key"

)

3. Save the file and check the configuration syntax by running the following command:

```
sudo rsyslogd -N1
```

4. You can optionally restart the **rsyslog** service:

```
sudo service rsyslog restart
```

Forwarding Local Syslog Messages to Remote Systems

Requirements:

- One or more destinations that can accept syslog messages with either UDP, TCP or TCP w ith TLS
- The IP address or FQDN of each destination system; the FQDN must be resolvable from the sending appliance
- The port number for each destination system
- The protocol for each destination system

To forward local syslog messages to remote systems:

1. Go to the console of the SL1 server or use SSH to access the server and log in as user **em7admin** with the password you configured during setup.

2. Locate the /etc/rsyslog.d/siteconfig.d/log_forwarding.conf file and edit the file to add the destinations.

The file contains several examples in addition to the following examples:

Example 1: If you are forwarding to a server using UDP, add the following line to the bottom of the configuration file, substituting in your IP or FQDN for the Target and your port for the Port:

```
action(name="UDP_Forward" type="omfwd" Target="192.0.2.5" Port="514"
Protocol="udp")
```

Example 2: If you are forwarding a subset of high-priority messages using TCP with TLS, add the following line to the bottom of the configuration file, substituting in your IP/FQDN for the Target and your port for the Port.

```
if prifilt("*.err;*.emerg;*.alert;") then {
  action(name="TCP_Forward" type="omfwd" Target="192.0.2.200"
  Port="1514" Protocol="tcp" StreamDriver="gtls" StreamDriverMode="1"
  StreamDriverAuthMode="anon")
}
```

- 3. Repeat step 2 if you want to add multiple destinations. When adding multiple destinations you will need to alter the name property so it is unique. It can be as simple as TCP_Forward1, TCP_Forward2, etc... ScienceLogic strongly recommends using the UDP protocol and having no more than 2 destinations. Each destination increases the bandwidth usage and using TCP or TCP w/TLS will increase the processing overhead.
- 4. Save the file and check the configuration syntax by running the following command:

```
sudo rsyslogd -N1
```

5. You can optionally restart the **rsyslog** service:

```
sudo service rsyslog restart
```

Specifying Alternate Inbound TCP or UDP Ports

1. Go to the console of the SL1 server or use SSH to access the server and log in as user **em7admin** with the password you configured during setup.

2. Locate the /etc/rsyslog.d/siteconfig.d/inbound_alternates.conf file and edit the file to add the destinations. The file contains several examples in addition to the example here:

The file contains several examples in addition to the following examples:

Example 1: To accept TCP with TLS-encrypted inbound messages, add the following section (there should only be one module section in the configuration):

```
module(

load="imtcp"

StreamDriver.Name="gtls"

StreamDriver.Mode="1"

StreamDriver.Authmode="anon"
)
```

Add the input section below the module section to specify the network port you would like to use (the default 514 is already in use, and ScienceLogic does not support disabling it in rsyslog):

```
input(

type="imtcp"

port="1514"

ruleset="ruleset-networksocket"
)
```

Example 2: To accept TCP inbound messages on an alternate port, add the following section to specify the network port you would like to use (the default 514 is already in use, and ScienceLogic does not support disabling it in rsyslog):

```
input(

type="imptcp"

port="9514"

ruleset="ruleset-networksocket"
)
```

NOTE: The type is correct as imptcp.

- 3. When setting up alternate input ports, do not change the ruleset line. It should always read as ruleset="ruleset-networksocket". If it does not read this, inbound messages will not be processed properly.
- 4. When opening up additional inbound ports you will also be required to allow the ports through the local firewall as well.
- 5. Save the file and check the configuration syntax by running the following command:

```
sudo rsyslogd -N1
```

6. You can optionally restart rsyslog now or proceed to other sections to configure inbound or outbound messages:

```
sudo service rsyslog restart
```

Adjusting the Priority Filter for Inbound Messages

The following procedure lets you adjust the priority filter for Inbound messages from Message Collectors and Data Collectors:

- 1. Go to the console of the SL1 appliance or use SSH to access the appliance and log in as user **em7admin** with the password you configured during setup.
- Locate the /etc/rsyslog.d/siteconfig.d/inbound_message_filter.conf file and edit the file to include or uncomment the example line and adjust the priority filter to meet your needs. You can refer to the following examples, but there should only be one line to adjust the filter:

Example 1: To accept all messages, use the following line:

```
set $.priority filter = prifilt("*.*");
```

CAUTION: ScienceLogic does not recommend using this setting, as it can result in message floods.

Example 2: Accept "auth" messages regardless of severity, in addition to the default priorities:

```
set $.priority_filter = prifilt
("auth.*,*.err,*.emerg,*.alert,local7.*,local6.*,local5.*,local4.*,lo
cal3.*,local2.*,local1.*,local0.*");
```

3. Save the file and check the configuration syntax by running the following command:

```
sudo rsyslogd -N1
```

4. You can optionally restart rsyslog now or proceed to other sections to configure inbound or outbound messages:

```
sudo service rsyslog restart
```

Filtering or Discarding Inbound Messages

The following procedure lets you filter or discard inbound messages from Message Collectors and Data Collectors:

- 1. Go to the console of the SL1 appliance or use SSH to access the appliance and log in as user **em7admin** with the password you configured during setup.
- 2. Locate the /etc/rsyslog.d/siteconfig.d/inbound_message_filter.conf file and edit the file to include a block to match against the desired messages and a stop statement.

For example:

```
if ($programname startswith "noisy_program") then {
   stop
}
```

NOTE: This is not the recommended way to limit the inbound messages to the system. The prefered method is to alter the sending device to only send relevant syslog messages to the system. This functionality is provided for limited use, because sending large amounts of messages in to the system only to be discarded increases processing load and can impact performance. Always limit messages at the source if available.

NOTE: The matching syntax is fairly flexible. Please refer to the official Rsyslog documentation at https://www.rsyslog.com/doc/master/index.html for available variables and match logic.

3. Save the file and check the configuration syntax by running the following command:

```
sudo rsyslogd -N1
```

4. You can optionally restart rsyslog now or proceed to other sections to configure inbound or outbound messages:

```
sudo service rsyslog restart
```

Sending Logs via Syslog to a Remote Server in SL1 Version 11.2.x and Earlier

WARNING: This method of sending logs to a remote server was deprecated in SL1 version 11.3.0 and later. For more information on the new method of sending logs to a remote server, see *Logging in SL1 Version 11.3.0* and *Later*.

To send logs to a syslog server or a security information and event management (SIEM) tool in SL1 version 11.2.0 or earlier:

1. Edit the file /etc/rsyslog.conf and include the following text to send the audit.log to rsyslog:

```
#audit log

$ModLoad imfile

$InputFileName /var/log/audit/audit.log

$InputFileTag tag_audit_log:

$InputFileStateFile audit_log

$InputFileSeverity info

$InputFileFacility local6

$InputRunFileMonitor
```

- 2. If rsyslog is not already configured to send to a remote server, configure the remote server at this time.
- 3. Restart rsyslog for the changes to take effect:

```
[root@server ~]# systemctl restart rsyslog
```

Monitoring User Actions and Events on the Audit Logs Page

The **Audit Logs** page (System > Monitor > Audit) provides an audit trail for SL1. The **Audit Logs** page displays a record of actions in SL1 that are generated by **users** or by **managed elements**. These actions are organized by organization.

Some of the actions that are logged in the **Audit Logs** page include:

- User logins to SL1
- The slladmin user requests a one-time password
- Organization name changes
- The addition, editing, or deletion of elements in SL1

NOTE: Entries for the addition, editing, and deletion of elements includes the affected device ID, when applicable.

- The installation, editing, or uninstallation of PowerPacks, including when a PowerPack is imported or installed from Global Manager to a Stack
- Manually triggered discovery sessions


- Events and cleared events
- The creation, editing, or deletion of event policies
- Devices being set to maintenance mode or devices no longer being in maintenance mode
- The unalignment of Dynamic Applications from devices and the deletion of that data
- The creation, editing, or deletion of Dynamic Applications
- The creation, editing, or deletion of Run Book Automation policies
- The addition or deletion of Reports
- The situation where a user gets an "Access Denied" page as a result of attempting to access a page for which he or she does not have permission
- Asset Record changes
- User-defined changes to settings on the Data Retention Settings page (System > Settings > Data Retention)
- Changes to settings on the **System Threshold Defaults** page (System > Settings > Thresholds > System)
- API requests that use a PUT, POST, or DELETE method
- All actions that renew the SL1 session ID
- Updates to interface collection states

NOTE: By default, the Audit Logs page displays a list of actions associated with all organizations.

Viewing the List of Audit Logs

To view the list of log entries in the **Audit Logs** page:

1. Go to the **Audit Logs** page (System > Monitor > Audit Logs).



- 2. The **Audit Logs** page displays all actions that are performed by users or managed elements in SL1. For each action, the **Audit Logs** page displays:
 - Date/Time. Date and time the action occurred and the log entry was created.
 - **Source**. Source of the log entry. This usually describes where the action took place. For example, if you change the contact information for your account, an entry will be made in the audit log, and the source will be "Contact Information."
 - Organization. Organization associated with the action.
 - Message. Text of the log entry.

Searching and Filtering the List of Audit Logs

The Filter-While-You-Type fields appear as a row of blank fields at the top of the list. These fields let you filter the items that appear in the list.

The list is dynamically updated as you select each filter. For each filter, you must make a selection from a drop-down menu or type text to match against. SL1 will search for entries that match the text, including partial matches. Text matches are not case-sensitive, and you can use special characters in each text field.

By default, the cursor is placed in the first Filter-While-You-Type field. You can use the <Tab> key or your mouse to move your cursor through the fields.

You can filter by one or more of the following parameters. Only items that meet all of the filter criteria are displayed on the page.

The following describes each filter on the **Audit Logs** page:

- Date/Time. Only those audit logs that have the specified creation date will be displayed. The choices are:
 - ° All. Display all audit logs that match the other filters.
 - Last Minute. Display only audit logs that have been created within the last minute.
 - ^o Last Hour. Display only audit logs that have been created within the last hour.
 - ^o Last Day. Display only audit logs that have been created within the last day.
 - ^o Last Week. Display only audit logs that have been created within the last week.
 - Last Month. Display only audit logs that have been created within the last month.
 - ^o Last Year. Display only audit logs that have been created within the last year.
- **Source**. You can enter text to match, including special characters, and the Audit Logs page will display only audit logs that have a matching source.
- **Organization**. You can enter text to match, including special characters, and the Audit Logs page will display only audit logs that have a matching organization.
- **Message**. You can enter text to match, including special characters, and the Audit Logs page will display only audit logs that have a matching message.

Generating Reports on Audit Logs

You can export the entries on the Audit Logs page as one of the following report types:

- Acrobat document (.pdf)
- Web page (.html)
- Excel spreadsheet (.xlsx)
- OpenDocument Spreadsheet (.ods)
- Comma-separated values (.csv)

When you create a report in the **Audit Logs** page, SL1 includes only those logs that appear in the current view of the page. If you filter the entries on the **Audit Logs** page, only those logs that meet the filter criteria and currently appear on the page will appear in the report.

To generate an audit logs report:

- From the Audit Logs page, click the [Report] button. The Export current view as a report window appears.
- 2. In the **Output Format** field, select the report format type.
- 3. Click [Generate].

Using auditd to Monitor Sensitive Files

As an additional security measure, the ScienceLogic Security team monitors the SL1 SaaS environment with the Linux Auditing System (*audita*). The auditd system provides enhanced logging that identifies when changes are made to specific files and directories in SL1 that contain sensitive data. Starting with SL1 version 11.1.0, you can send audit logs externally to a security information and event management (SIEM) tool when needed.

The auditd logging at **/var/log/audit/audit** provides logging based on the configured rules that are shipped with SL1 version 11.1.0 or later. You can send syslog messages to a syslog server or a SIEM tool.

NOTE: Starting with SL1 version 12.1.0, audispd configuration options are part of **auditd.conf**. In addition, the **plugins.d** directory was moved under **/etc/audit**. You can now check the status of auditd and its plug-ins can now be checked by running the service auditd state command.

SL1 monitors specific files and directories for changes. The topics below describe what is logged by default, how to modify what is logged, and how to send logs externally.

Files Logged by Default

Starting in SL1 version 11.1.0, a file called **rules.d/70_silo_watchlist.rules** is created and added to the **/etc/audit** directory.

The following files are monitored:

```
-w /etc/silo.conf -p war -k silowatch
-w /etc/php.ini -p wa -k silowatch
-w /etc/yum.conf -p wa -k silowatch
-w /etc/postfix/main.cf -p wa -k silowatch
-w /etc/postfix/master.cf -p wa -k silowatch
-w /etc/nginx/nginx.conf -p wa -k silowatch
-w /etc/yum.conf -p wa -k silowatch
-w /etc/ntp.conf -p wa -k silowatch
-w /etc/my.cnf -p wa -k silowatch
-w /etc/my.cnf.d/ -p wa -k silowatch
-w /etc/php.d/ -p wa -k silowatch
-w /etc/skel/ -p wa -k silowatch
-w /etc/yum/ -p wa -k silowatch
-w /etc/yum.repos.d/ -p wa -k silowatch
-w /etc/ntp/ -p wa -k silowatch
-w /etc/chrony.d/ -p wa -k silowatch
-w /etc/chrony.keys -p wa -k silowatch
-w /etc/chrony.conf -p wa -k silowatch
```

Modifying the List of Files to be Logged

To add or change files that are monitored:

- 1. Log in to the SL1 appliance with the admin account and sudo to the root user.
- 2. Edit the file called /etc/audit/rules.d/70 silo watchlist.rules. Add the following line to the file.

```
-w /etc/.custom alignment.conf -p wa -k silowatch
```

NOTE: This file is not included in SL1 version 11.1.0 by default.

3. Run the following command to load the files into the audit.rules file:

```
[root@server ~] # augenrules --load
```

NOTE: You can add or remove specific files that you want to monitor from this list. Including the slash at the end of the monitored path (such as /etc/ntp/) will monitor the entire directory and everything stored within it.

Monitoring the Status of Data Collectors

The Collector Status page displays the status of each Data Collector and Message Collector in your system.

NOTE: This page does not appear in All-In-One Appliances.


Data Collectors retrieve data from managed devices and applications. This collection occurs during initial discovery, during nightly updates, and in response to policies defined for each managed device. The collected data is used to trigger events, display data in the user interface, and generate graphs and reports.

Message Collectors receive and process inbound, asynchronous syslog and trap messages from monitored devices. In most distributed systems, dedicated **Message Collector** appliances perform message collection. A single **Message Collector** can handle syslog and trap messages from devices that are monitored by multiple **Data Collectors**.

To perform collection, you must define a Collector Group and align it with at least one Data Collector. If your Collector Group includes multiple Data Collectors, you can configure the Collector Group for high-availability. For details, see the section on Collector Groups.

To ensure the health of your system, you should periodically check on the status of the Data Collectors and Message Collectors. To access the **Collector Status** page:

1. Go to the **Collector Status** page (System > Monitor > Collector Status).



- 2. For each Data Collector in your system, the Collector Status page displays the following:
 - Collector Name. Name of the Data Collector or Message Collector.
 - Collector ID. Unique numeric ID automatically assigned to the Data Collector or Message Collector by SL1.
 - Collector Address. IP address of the Data Collector or Message Collector.
 - Group ID. Unique numeric ID of the Collector Group associated with the Data Collector or Message Collector.
 - Group Name. Name of the Collector Group associated with the Data Collector or Message Collector.
 - Last State Change. Date and time the platform last polled the status of the Data Collector or Message Collector.
 - Collector State. Operating state of the Data Collector or Message Collector.

Chapter

5

Updating SL1

Overview

This chapter provides an overview of the **System Updates** page, detailed steps for performing an SL1 upgrade, and detailed steps on upgrading MariaDB, upgrading PowerPacks, and performing reboots.

CAUTION: As of 12.2.0, SL1 can be deployed *only* on Oracle Linux 8 (OL8) operating systems. If you are upgrading from a version of SL1 prior to 12.1.1 that does not already run on OL8, you *must* first upgrade to SL1 12.1.1 and then convert to OL8 before upgrading to SL1 12.2.0.

Depending on the version of SL1 that you are currently running, you might be required to upgrade to one or more earlier versions of SL1 before you can upgrade to 12.2.0.

For more information about supported upgrade paths, see the upgrade notes included in the *SL1 release* notes as well as the *OL8 Conversion Resource Center* on the ScienceLogic Support portal, which includes links to numerous resources such as the *Oracle Linux 8 Conversion Guide*. The conversion guide includes prerequisites, instructions for converting to *OL8* for all deployment types, FAQs, and other helpful information to walk you through the *OL8* conversion process.

If you take no action before October 31, 2024, all older SL1 systems with OL7 will continue to run, but ScienceLogic will not support them, and the systems might not be secure.

IMPORTANT: The SL1 system update process supports Python 3.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon
- To view a page containing all of the menu options, click the Advanced menu icon (· · ·).

This chapter covers the following topics:

The System Updates Page	128
The Workflow for Updating SL1	131
Planning the Update	132
Scheduling Maintenance Windows	132
Pre-Upgrade Best Practices for SL1	133
Backing Up SSL Certificates	133
Setting the Timeout for PhoneHome Watchdog	134
Adjusting the Timeout for Slow Connections	
Running the System Status Script Before Upgrading	135
Updating the SL1 Distributed Architecture	
Updating SL1 Extended Architecture	153
Automatically Upgrading MariaDB with a Script	153
Manually Upgrading MariaDB	157
Rebooting Appliances in the SL1 Distributed Stack	173
Restoring the SSL Certificates	179
Resetting the Timeout for PhoneHome Watchdog	179
Updating Default PowerPacks	180
Configuring Subscription Billing	181

The System Updates Page

The **System Updates** page (System > Tools > Updates) allows you to update the software on your SL1 appliances.

You must first download the update file to the local computer. You can then *import* the software update through the user interface.

After you import a software update to your SL1 system, the SL1 system can automatically *stage* the software update. Staging is when the software is copied to each ScienceLogic appliance. Staging allows SL1 to simultaneously apply the software changes to each ScienceLogic appliance, regardless of the speed of the connection to each ScienceLogic appliance. You can allow the SL1 system to automatically stage the software or you can manually stage the software.

After the software update is staged, you can run preupgrade checks and then deploy the software.

WARNING: To apply updates to an existing Data Collector, that Data Collector must be a member of a Collector Group. In some SL1 systems, users might have to create a Collector Group for a single Data Collector before applying updates.

NOTE: To conserve disk space on Data Collectors and Message Collectors, after an update, SL1 removes previous Docker images.

The **System Updates** page displays a list of deployed updates and the date and time each update was applied. The following information displays for each update in the list:

- *EM7 Version*. Displays the version number for each SL1 patch that has been imported (and optionally staged and deployed) to the SL1 system. SL1 releases include new features and address issues with previous releases.
- OS Version. Displays the version number for each platform patch that has been imported (and optionally staged and deployed) to the SL1 system. Platform patches include updates to the ScienceLogic operating system, including newer versions of industry-standard packages.
- **Update Signature**. Name of the entity that released the patch and type of patch. Usually "ScieneceLogic Official Release".
- Imported On. Date and time the software update was loaded onto the SL1 system.
- Imported By. SL1 user who loaded the software update onto the SL1 system.
- *Import Status*. Status of the import process. Clicking on the log icon displays the log file associated with importing the selected software. Possible values are:
 - ° In Progress. Software is currently being imported by the system.
 - ° Complete. Software has been imported successfully.
 - ° Failed. Software import has failed due to an unexpected condition. Contact ScienceLogic Support for assistance.

- **Staging Status**. Status of the staging process. Clicking on the log icon displays the log file associated with staging the selected software. Possible values are:
 - ° --. No staging request is active and software has not been staged on any SL1 appliances.
 - ° Scheduled. SL1 is aware of the staging request and is preparing for staging.
 - ° In Progress. Staging is in progress but has not completed.
 - ° Complete. Staging has completed, and all appliances are ready to deploy the software.
 - ° Incomplete. Staging has completed, and one or more appliances are ready to deploy the software.
 - ° Cancelled. User manually cancelled the staging process.
 - ° Outdated. The current update is not the latest or has already been installed.
 - ° Failed. An unexpected error occurred in the staging process. Contact ScienceLogic Support for assistance.

NOTE: If a software update has been set to manually stage, the Staging Status column will include an asterisk (*).

- Preupgrade Status. Status of the preupgrade checks. Possible values are:
 - ° --. No preupgrade checks are active.
 - ° Complete. Preupgrade checks have completed successfully.
 - ° Incomplete. Preupgrade checks have not yet completed.
 - Failed. An unexpected error occurred in the preupgrade checks. Contact ScienceLogic Support for assistance.
- Deployment Status. The current deployment state. Possible values are:
 - ° --. No deployment request is active and software has not been deployed on any SL1 appliances.
 - Scheduled. SL1 is aware of the deployment request and is preparing for deployment.
 - ° In Progress. Deployment is in progress but has not completed.
 - ° Complete. Deployment has completed, and all appliances are updated.
 - ° Incomplete. Deployment has completed, and one or more appliances are updated.
 - ° Cancelled. User manually canceled the deployment.
 - ° Outdated. The current update is not the latest or has already been installed.
 - Failed. An unexpected error occurred in the deployment process. Contact ScienceLogic Support for assistance.
- Deployment Status Date. Specifies the date and time the software update was last deployed.

From the **System Updates** page, you can also click the **[Appliance List]** button to view a list of appliances in your SL1 stack. The following information displays for each appliance in the list:

- Appliance Name. The name assigned to the SL1 appliance.
- IP. The appliance's IP address.
- mid. The appliance's module ID.
- Module Type. The SL1 appliance type.
- Build. The version of SL1 currently running on the appliance.
- MariaDB. The version of MariaDB currently running on the appliance.
- Task Manager Paused? Indicates whether the task manager service is paused.
- Patch Eligible. Indicates if the appliance is eligible for patching.
- Patch Enabled. Indicates if patching is enabled or disabled for the appliance.

NOTE: To enable or disable patching for an appliance, select the checkbox for that appliance on the **Appliance List** modal, select *Enable Selected Appliances* or *Disable Selected Appliances* from the **Select Action** menu, and then click **[Go]**.

The Workflow for Updating SL1

The following sections describe the steps to plan and deploy an SL1 update. If would like assistance planning an upgrade path that minimizes downtime, please contact your Customer Success Manager.

The workflow for updating SL1 is:

- 1. Plan the update.
- 2. Schedule maintenance windows.
- 3. Review pre-upgrade best practices for SL1.
- 4. Back up SSL certificates.
- 5. Set the timeout for PhoneHome Watchdog.
- 6. Adjust the timeout for slow connections.
- 7. Run the system status script on the Database Server or All-In-One before upgrading.
- 8. Update the SL1 Distributed Architecture using the System Update tool.
- 9. Upgrade MariaDB, if needed.
- 10. Reboot SL1 appliances, if needed.
- 11. Restore SSL Certificates.
- 12. Reset the timeout for PhoneHome Watchdog.
- 13. Update default PowerPacks.
- 14. Configure Subscription Billing (one time only).

NOTE: The option to enable a Military Unique Deployment (MUD) configuration is not available for SL1 12.1.x or 12.2.0 installations or upgrades.

Planning the Update

Before upgrading SL1, perform the following steps that are specific to your organization:

- 1. Read the release notes to determine:
 - · What is fixed?
 - What is new?
 - What has changed?
 - What has been deprecated?
- 2. Read the Known Issues for the release at https://support.sciencelogic.com/s/known-issues.
- 3. Identify all integrations and third-party applications that access the SL1 database or manipulate data on SL1. Determine how to disable these integrations during the deployment and re-enable after deployment.
- 4. Identify activities and customers that will be affected by maintenance windows and schedule and inform appropriately.
- 5. Identify custom work (PowerPacks, Run Book Automations, Event policies, Dashboard widgets) and ensure that it is backed up so you can restore it if necessary.

NOTE: Ensure that the each SL1 node or appliance has at least 4 GB of free space in the /var partition for pre-upgrade and deployment. Ensure that each SL1 node or appliance has at least 1 GB of free space in / (the root partition) to allow you to deploy the upgrade; however, depending on the appliance type and version you are upgrading from, you might need up to 3 GB of free space in / (the root partition).

NOTE: If you are upgrading from a version of SL1 prior to version 8.10.0, see *Updating SL1 Appliances to*Oracle Linux.

Scheduling Maintenance Windows

Upgrading SL1 includes a minimum of two and possibly four maintenance windows:

• Import and stage update and run the pre-upgrade script. These steps can take place prior to the day of upgrade and do not affect SL1 functionality. ScienceLogic suggest you perform these steps at least three days before the planned upgrade and ideally a week before the planned upgrade.

132 Planning the Update

- **Deploy update**. On the day of the upgrade, put all SL1 appliances in maintenance mode. The SL1 system will not be available during this procedure. Update the SL1 Distributed systems.
- **Update MariaDB** (if required). The SL1 system will not be available during this procedure. Refer to the release notes for your current release to determine if you must upgrade MariaDB.
- **Reboot Appliances (if required)**. Individual SL1 appliances will not be available during these procedures. Refer to the release notes for your current release to determine if you must reboot all SL1 appliances after upgrading.

Identify activities and users that will be affected by these maintenance windows, and schedule the maintenance windows appropriately. Be sure to communicate all downtime with users.

Pre-Upgrade Best Practices for SL1

Before you upgrade, check the following:

- Review the hardware specifications of all the appliances in your system to ensure they meet the requirements
 for the current usage of your system. For more details about sizing and capacity for your specific
 environment, contact your Customer Success Manager and see https://support.sciencelogic.com/s/system-requirements.
- Verify that recent backups are available for your system.
- Ensure that each SL1 appliance has a valid license.
- Ensure that a Data Collector is a member of a Collector Group if you are applying updates to an existing Data Collector. In some SL1 systems, users might have to create a Collector Group for a single Data Collector.
- Ensure that each Data Collector is listed as "Available" to the Database Server. To check, see the **Collector Status** page (System > Monitor > Collector Status).

Backing Up SSL Certificates

To back up your SSL Certificates:

- 1. Log in to the console of the Database Server or SSH to the Database Server.
- 2. Open a shell session and type the following commands at the shell prompt:
 - cp /etc/nginx/silossl.key /etc/nginx/silossl.key.bak
 - cp /etc/nginx/silossl.pem /etc/nginx/silossl.pem.bak
- 3. Repeat these steps on each Database Server in your SL1 system.

Setting the Timeout for PhoneHome Watchdog

NOTE: This section applies to users who are upgrading from SL1 11.1.x or earlier and have an existing PhoneHome configuration. If you are upgrading from SL1 11.2.0 or later or you do not have a pre-11.2.0 PhoneHome configuration, you can ignore this section.

You can manually adjust the settings for the PhoneHome Watchdog server to reduce CPU consumption during the upgrade process. To do this:

- 1. Log in to the console of the Data Collector as the root user or open an SSH session on the Data Collector.
- 2. At the command line, type the following:

```
phonehome watchdog view
```

You should see something like the following:

```
Current settings:
autosync: yes
interval: 20
state: enabled
autoreconnect: yes
timeoutcount: 2
check: default
```

- 4. Note the settings for interval and timeoutcount, so you can restore them after the upgrade.
- 5. To change the settings for SL1 upgrade, type the following at the command line:

```
sudo phonehome watchdog set interval=120;
sudo phonehome watchdog set timeoutcount=2;
systemctl stop em7_ph_watchdog;
systemctl start em7_ph_watchdog;
```

- 6. Repeat the steps in this section on each Data Collector.
- 7. Repeat the steps in this section on each Message Collector.
- 8. Repeat the steps in this section on each Database Server.

Adjusting the Timeout for Slow Connections

If you have slow connections between SL1 appliances, you can adjust the timeout values for staging and deploying upgrades.

To adjust the timeouts:

- 1. Log in to the console of the Database Server or SSH to the Database Server.
- 2. Open a shell session and type the following at the shell prompt:

```
sudo pcli set-patcher-param staging wait time <timeout in seconds>
```

where:

<ti>meout_in_seconds> is the timeout value, in seconds, for staging for each SL1 appliance. The default value is 1800 seconds (30 minutes). You can increase this value for slow connections.

3. Type the following at the shell prompt:

```
sudo pcli set-patcher-param deploy wait time < timeout in seconds>
```

where:

< timeout_in_seconds > is the timeout value, in seconds, for deploying to each SL1 appliance. The default value is 3600 seconds (1 hour). You can increase this value for slow connections.

NOTE: If you are upgrading from a version of SL1 prior to version 8.14.0, see Adjusting the Timeout for SL1 8.12 and Prior Releases.

Running the System Status Script Before Upgrading

SL1 includes a script, **system_status.sh**, that provides diagnostic data for each node or appliance in your SL1 system.

NOTE: On SL1 systems prior to 10.2.0, after running the system status script, you must ensure that the file /var/lob/em7/silo.log has the owner and group "s-em7-core".

Running the System Status Script

If you are running SL1 version SL 8.14.0 or later, SL1 automatically runs the system status script every 15 minutes on each node or appliance in your SL1 system.

ScienceLogic recommends that you view the output from the system status script before upgrading:

- 1. In SL1, go to the **Appliance Manager** page (System > Settings > Appliances).
- 2. Locate the SL1 appliance that you want to view diagnostic information about.
- 3. Click on its magnifying-glass icon () to view the output of the system status script for that appliance.
- 4. If the output includes errors and you need help fixing them, contact ScienceLogic Customer Support to fix the errors before upgrading.
- 5. Repeat for each node or appliance in your SL1 system.

TIP: To get the very latest status before upgrading, *manually run the system status script* on each Database Server or All-In-One Appliance.

NOTE: If you are upgrading from an SL1 8.12.x system, see Running the System Status Script on SL1 8.12.x Releases. If you are upgrading from an SL1 8.10.x or prior release, see Running the System Status Script on SL1 8.10 and Prior Releases.

Updating the SL1 Distributed Architecture

Any SL1 Distributed Architecture system running 8.6.0 or later can be upgraded by importing, staging, and deploying a single update file.

NOTE: Ensure that the each SL1 node or appliance has at least 4 GB of free space in the /var partition for pre-upgrade and deployment. Ensure that each SL1 node or appliance has at least 1 GB of free space in / (the root partition) to allow you to deploy the upgrade; however, depending on the appliance type and version you are upgrading from, you might need up to 3 GB of free space in / (the root partition).

Upgrading the SL1 Distributed Stack includes the following steps:

- Download the update.
- Import the update.
- Stage the Update.
- Run the pre-upgrade check.
- Place all SL1 appliances in Maintenance Mode.
- · Deploy the update.
- Remove all SL1 appliances from Maintenance Mode

NOTE: If you are upgrading from an SL1 system between 8.1.1 and 8.5.0, see *Upgrading the SL1*Distributed Architecture on SL1 Versions 8.5.0 and Earlier.

If you are currently running an SL1 version prior to 8.12.0, you must go to the System Updates page and disable automatic staging (System > Tools > Updates > Actions > Disable automatic staging).

If you have previously used manual staging, you must also perform these additional steps:

- 1. Select all updates in the EM7 Releases pane and select all updates in the ScienceLogic OS pane.
- 2. In the Select Action menu, select Unstage Update (remove staging policy override). Click [Go].

3. For software that was previously staged with automatic staging, *Unstage Update* (remove staging policy override) does not affect staging.

Downloading the Update

Before you can load a patch or update onto your instance of the SL1 system, you must first download the patch or update to your local computer.

NOTE: The following steps do not affect the performance of the SL1 system. ScienceLogic recommends that you perform these steps at least three days before upgrading.

To download the patch or update:

- 1. Log in to https://support.sciencelogic.com. Use your Sciencelogic customer account and password to access this site.
- 2. From the **SL1 Product Downloads** menu, select SL1 Platform. The **Platform Downloads** page appears.
- 3. Find the release you are interested in and click its name. The **Release Version** page appears.
- 4. Click the specific link for a release, if needed.
- 5. Click the link for the release image or release patch you want to download, and click the [**Download File**] button. The file is then downloaded to your local computer.

Importing the Update

To import a product update on to your SL1 system:

- 1. In the SL1 system, go to the **System Updates** page (System > Tools > Updates).
- 2. In the **System Updates** page, click the **[Import]** button.
- 3. In the Import a new update modal page, browse to the product update file and select it.
 - If you select the Auto Stage button, the SL1 system will begin staging as soon as the import is completed.
 - If you do not select the **Auto Stage** button, you must click the staging button(**2**) after import is completed. You can do so at any time after import has completed.
 - For more information on automatic staging and manual staging, see the section on "Staging" in the **System Administration** manual.
- 4. Click the [Import] button.
- 5. In the **System Updates** page, the *Import Status* column can have one of the following statuses:
 - ° In Progress. Software is currently being imported by the SL1 system.
 - ° Complete. Software has been imported successfully.
 - Failed. Software import has failed due to an unexpected condition. Contact ScienceLogic Support for assistance.

- Missing Base. The SL1 system cannot import this software until another software package has been imported. The dependency is for compression purposes. Check the log for a message stating which software package needs to be imported.
- 6. The update file or patch file is imported to SL1 system and appears in the **System Updates** page.

NOTE: For details on the import process, go to the **System Updates** page, find the entry for the software you are interested in, go to its *Import Status* column, and click the log icon ().

Staging the Update

After you import a software update to your SL1 system, you must **stage** the software update. During staging, the SL1 system copies the software update to each SL1 appliance. Staging allows SL1 to simultaneously apply the software changes to each SL1 appliance, regardless of the speed of the connection to each SL1 appliance. The SL1 system stages updates per import. You can choose to automatically stage imports or manually stage import.

For easiest troubleshooting, ScienceLogic recommends that you manually stage imports.

NOTE: A staging mode called "enhanced file upload" enables pre-staging operations and file upload operations to happen in separate worker processes, which does not count file upload time toward the "staging wait time" setting. This mode is enabled by default, and ScienceLogic recommends that you keep it enabled due to the large amount of data that needs to be pushed for SL1 updates. However, if you prefer to update this setting, you can make the following changes in the "master.system_settings_patcher" table:

• To change the number of file upload workers (12 by default), insert or update the following parameter:

```
param="num file upload workers" and value="<number of workers>"
```

• To change the number of pre-staging workers (25 by default), insert or update the following parameter:

```
param="pool size" and value="<number of workers>"
```

• To disable enhanced file upload mode, insert or update the following parameter:

```
param="use enhanced file upload" and value="0"
```

The Staging Status column on the System Updates page can have one of the following statuses:

- --. No staging request is active and software has not been staged on any SL1 appliances.
- Scheduled. The SL1 system is aware of the staging request and is preparing for staging.
- In Progress. Staging is in progress but has not completed. The page displays the percentage complete as staging progresses.
- Complete. Staging has completed, and all appliances are ready to deploy the software.
- Incomplete. Staging has completed, and one or more appliances are ready to deploy the software.
- Canceled. User manually canceled the staging process.

- Outdated. The current update is not the latest or has already been installed.
- Failed. An unexpected error occurred in the staging process. Contact ScienceLogic Support.

NOTE: For details on the staging process, go to the **System Updates** page, find the entry for the software you are interested in, go to its **Staging Status** column, and click the log icon (()).

After the software update is imported and staged, you can deploy the software.

Automatic Staging

To enable automatic staging:

- 1. In SL1, go to the **System Updates** page (System > Tools > Updates).
- 2. In the System Updates page, click the [Import] button.
- 3. In the **Import a new update** modal page, browse to the product update file and select it. If you select the **Auto Stage** button, the SL1 system will begin staging as soon as the import is completed.
- 4. After import, in the **System Updates** page, the *Staging Status* column will display the number of ScienceLogic appliances that have been successfully stage compared to the total number of ScienceLogic appliances

To disable automatic staging:

- 1. In SL1, go to the **System Updates** page (System > Tools > Updates).
- 2. In the **System Updates** page, click the **[Import]** button.
- 3. In the **Import a new update** modal page, browse to the product update file and select it.
- 4. If you **do not select** the **Auto Stage** button, you must click the staging button (**2**) after import is completed. You can do so at any time after import has completed.

Manually Staging an Update

You can manually stage a software update:

- If you imported an update but do not want to stage it immediately.
- If you add another ScienceLogic appliance to your SL1 system and need to apply software updates.
- If staging failed on one or more ScienceLogic appliances.
- If you want to ensure that a previous staging process was successful.

When you manually stage a software update, SL1 checks the status of the software updated on each ScienceLogic appliance. SL1 then stages the software update only to those SL1 appliances that have not yet been staged for this software update.

To manually stage a software update:

- 1. In SL1, go to the **System Updates** page (System > Tools > Updates).
- 2. Locate the software update you want to stage and click its staging icon (20). The software update will be copied to each ScienceLogic appliance that has not yet been staged.
- 3. The Staging Status column will display the number of ScienceLogic appliances that have been successfully stage compared to the total number of ScienceLogic appliances.


Monitoring Staging

For SL1 versions 8.12.0 and later, you can monitor the staging process:

- 1. Either go to the console of the Database Server or use SSH to access the Database Server.
- 2. Type the following at the shell prompt:

```
monitor_stage
```

You should see something like the following image:



3. In the monitor stage results, look for the following information:

- **System Update Vitals**. Displays the current status of the services that are required for System Update.
- Staging Process Stats. Displays status of staging on all SL1 appliances.

Running the Pre-Upgrade Check

After importing and staging an update, you can run a pre-upgrade check before deploying. The pre-upgrade check will ensure that all criteria are met before deploying.

NOTE: If you are upgrading from SL1 8.14 or earlier, see Running the Pre-Upgrade Check for SL1 8.14 or Earlier.

The pre-upgrade check examines the following:

- Is each SL1 Appliance eligible to be updated?
- Are updates enabled on each SL1 Appliance?
- Are any of the SL1 Appliances running CentOS 5?
- Is this hostfile on each SL1 Appliance correctly configured?
- Is each Data Collector and Message Collector in a Collector Group?
- Is there enough free space on the disk to perform the upgrade?
- Is the RPM database corrupted?
- Are the RPM packages corrupted?
- Does the patch hook directory have the correct owner assigned?
- Are the CRM templates on High Availability and Disaster Recovery systems out of date?
- Does /etc/init.d/mysql exist? (If it does not, it creates the file.)

NOTE: The pre-upgrade check skips any SL1 appliances that have been deleted since the last upgrade.

Running the Pre-Upgrade Check

To run a pre-upgrade check:

- 1. Go to the **System Updates** page (System > Tools > Updates.
- 2. Find the upgrade that you want to deploy.
- 3. Click the purple checkmark at the end of the row. The pre-upgrade check will run.
- 4. If a pre-upgrade criterion fails, the [Deploy] button will be disabled for the selected row.
- 5. To view the output from the pre-upgrade check, click on the on the magnifying-glass icon () in the selected row.

- 6. If the pre-upgrade check finds a failure, see the list below for possible causes.
- 7. Fix all failures before deploying the update.

Potential Issues to Address

CentOS 5 Failure

CentOS 5 is no longer supported by System Update. If one or more Data Collectors are running CentOS5, the pre-upgrade check will fail. Contact your Customer Success Manager to determine how to upgrade your Data Collectors.

Collector Group Membership

This test checks that each Data Collector and Message Collector is a member of a Collector Group.

If a Data Collector or Message Collector is not a member of a Collector Group, the pre-upgrade test will define the appliance as "not eligible for patching.

To fix this error, add the Data Collector or Message Collector to a Collector Group.

Eligibility Failure

The most common reasons for eligibility failure are:

- The SL1 appliance is not licensed or the license has expired
- The SL1 appliance cannot be reached over the network
- The Data Collector has failed over
- The SL1 appliance is not configured
- The Data Collector is waiting to be returned to service
- The Data Collector is not assigned to a Collector Group

Enabled Failure

By default, all SL1 appliances are enabled for patching.

However, if you have used a command-line tool to exclude an SL1 appliance from updates, the pre-upgrade check will fail. To fix this error, include the SL1 appliance for updates.

Free Disk-Space Failure

This test checks the root partition and requires 1GB of free disk space. If the root partition does not have 1GB of free disk space, the pre-upgrade check will fail.

If the root partition does not have 1GB of free disk space, you must archive or delete files that are no longer required or add a new empty disk and resize the filesystem.

Host File Failure

This test validates the /etc/hosts file for the presence of an IPv6 entry for localhost, which is required by System Update.

If /etc/hosts does not include an IPv6 entry for localhost, the pre-upgrade test automatically adds the required entry.

Check the following in case of failure:

- The /etc/hosts file exists
- The /etc/hosts can be edited by root

Patch-Hook Ownership Failure

If the owner of the patch hook directory ((/var/lib/em7/patch_hook) is incorrect, the pre-upgrade test automatically fixes the ownership. However, if this error occurs, check for the following:

- The patch hook directory (/var/lib/em7/patch hook) does not exist
- The s-em7-core user or the s-em7-core group does not exist

RPM Database Failure

If the RPM database fails the pre-upgrade test, the RPM database is corrupted.

To recover the RPM database:

- 1. Either go to the console of the Database Server or use SSH to access the Database Server. Log in with the credentials you defined when you installed the Database Server.
- 2. At the shell prompt, enter the following:

```
mkdir -p /tmp/rpm.bak

cp /var/lib/rpm/* /tmp/rpm.bak

rm -f /var/lib/rpm/__db*

rpm --rebuilddb -vv

rpm -q kernel
```

3. If the last command returns a value, you can delete the backup directory using the following command.

```
rm -Rf /tmp/rpm.bak
```

RPM Package Failure

If one or more RPM packages failed the pre-upgrade test, possible causes are:

- Packages are not staged, and hence some files are missing. This can be caused due to a failed staging or a timeout during staging. You can try to stage again. You can also adjust the timeout for staging.
- Duplicate packages
- Conflicting packages
- Unmet dependencies

Duplicate Packages:

- 1. Either go to the console of the Database Server or use SSH to access the Database Server. Log in with the credentials you defined when you installed the Database Server.
- 2. At the shell prompt, enter the following command:

```
sudo package-cleanup --dupes
```

3. If there are duplicate packages, use the following command to remove them:

sudo package-cleanup --cleandupes --removenewestdupes

Conflicting Packages

- 1. Look for conflicting packages in the staging log
- 2. Verify that the package is a part of SL1 ISO or patch bundle
- 3. If the package is not part of the SL1 ISO or patch bundle, uninstall the package.

Unmet dependencies

You will need to reset the staging status of the appliance and stage it again. Contact ScienceLogic Customer Success for help in resetting the staging status.

Putting All SL1 Appliances into Maintenance Mode

NOTE: ScienceLogic recommends that you perform these steps during a maintenance window.

Immediately before deploying a software update, ScienceLogic recommends that you put all SL1 appliances in maintenance mode. This will prevent spurious error messages and events during the deployment.

To enable user maintenance mode for all the SL1 appliances in your SL1 system:

- 1. Go to the **Appliance Manager** page (System > Settings > Appliances). Note the list of SL1 appliances in your system.
- 2. Go to the **Device Manager** page (Registry > Devices > Device Manager) and select the checkbox for each SL1 appliance in your SL1 system. This includes both primary and secondary Database Servers.
- 3. In the **Select Action** drop-down list, select Change User Maintenance Mode: Enabled without Collection. This option puts the selected devices into user maintenance mode with collection disabled. The devices will remain in this state until you or another user disables user maintenance mode.
- 4. Click the [Go] button.

Deploying the Update

During deployment, avoid the following tasks:

- Running integrations and third-party applications that access the SL1 database or manipulate data on SL1
- Running discovery sessions
- Running nightly discovery
- Bringing HA/DR out of maintenance mode
- Adding new SL1 Appliances
- Importing a new patch
- Adding Data Collectors to a Collector Group
- Removing Data Collectors from a Collector Group

- Rebalancing a Collector Group
- Killing processes related to patching and upgrading
- · Run reporting jobs
- Unpausing the proc_mgr process

When you deploy an update, the update is installed on all nodes or appliances that have already been staged.

When you deploy an update, SL1 checks to ensure that you have already deployed all required updates. If you have not, SL1 will generate an error message specifying the updates you must deploy before continuing with the current update.

During deployment, the **Deployment Status** column on the **System Updates** page can have one of the following statuses:

- --. No deployment request is active, and software has not been deployed on any SL1 appliances.
- Scheduled. The SL1 system is aware of the deployment request and is preparing for deployment.
- In Progress. Deployment is in progress but has not completed.
- Complete. Deployment has completed, and all appliances are updated.
- Incomplete. Deployment has completed, and one or more, but not all, appliances are updated.
- Canceled. User manually canceled the deployment.
- Outdated. The current update is not the latest or has already been installed.
- Failed. An unexpected error occurred in the deployment process. Contact ScienceLogic Support.

To deploy a software update on your nodes or appliances:

- 1. Make sure that you have imported and staged the update file.
- 2. Go to the **System Updates** page (System > Tools > Updates).
- 3. In the **System Updates** page, find the software update you want to deploy. Click the lightning bolt icon () to deploy the software. If SL1 is still staging the patch when you click the lightning-bolt icon (), SL1 will wait until staging has completed before deploying the updates to each ScienceLogic appliance.
- 4. The software update will be deployed to all appliances in your SL1 system that have already been staged. If one or more appliances in your SL1 system have been successfully staged, SL1 will deploy the update to those appliances.

NOTE: For details on the deployment process, go to the **System Updates** page, find the entry for the software you are interested in, go to its **Deployment Status** column, and click the log icon ().

Troubleshooting System Update

You can use the **sysuptb** troubleshooting tool to determine issues with System Update and to generate diagnostic information about the update. You can also use the **phtb** tool to troubleshoot issue with the PhoneHome configuration.

These tools can be useful when System Update does not work as expected, or if you have issues with the PhoneHome configuration or with communication between appliances and the Database Server. These tools are available on all SL1 appliances starting with SL1 version 10.2.0, and the tools are backwards-compatible to SL1 version 8.12.0.

Using the sysuptb Troubleshooting Tool

To use the **sysuptb** troubleshooting tool:

- 1. Either go to the console of any SL1 appliance or use SSH to access the appliance
- 2. Enter the following at the shell prompt:

```
sudo sysuptb -h
```

3. For more information about each argument, enter the following at the shell prompt:

```
sudo sysuptb <argument> -h
```

Available Commands

The following command executes all troubleshooting tests for System Update:

```
sudo sysuptb all <optionally -x name of test to exclude>
```

TIP: To learn more about a test run, use this command: sudo sysuptb help <test-name>

° Example:

sudo sysuptb all

```
Executing filestore tests
912 / 912 [-----
-] 100.00% 14 p/s
Filestore test summary: [Total: 912, Intact: 912, Incomplete: 0,
Corrupt: 01
Executing test for deleted appliances in patch history
No deleted appliances were found in the patch history
Executing test for invalid file id in patch schedules
No patch schedules were found to have invalid file id
Executing test for RPM database corruption
RPM database is intact
Executing test to check if filestore is empty
Filestore has 1026 files
Executing test for deactivating services
Service test summary: [Total: 1, Active: 1, Inactive: 0, Healed:
0, Skipped: 0, Failed (to heal): 0]
Executing test for free disk space
Free disk space test summary: [Total: 2, Pass: 2, Failed: 0]
Executing test for service errors
Service error test summary: [Total: 2, Without Errors: 2,
Restarted: 0, Failed: 0]
Executing hosts file check for IPV6 entry (::1) for localhost
An entry for :: 1 is already present in the hosts file
Proxy is not configured for yum.
Executing test for hung yum process
No yum processes found
Yum process summary: [Total: 0, Hung: 0]
```

• The following command searches the logs for errors that match a service name and restarts services if any errors are found

```
sudo sysuptb check-service-error <optionally -s name of service>
```

If you do not provide the name of a service, the command searches the logs for errors for siloupdate-pkgserver.service and siloupdate-spool.service.

° Example:

```
Executing test for service errors

Service error test summary: [Total: 2, Without Errors: 2,

Restarted: 0, Failed: 0]
```

• The following command removes deleted SL1 appliances from the history of system updates so that they SL1 does not search for them during update.

```
sudo sysuptb clear-mids
```

° Example:

```
sudo sysuptb clear-mids
```

Executing test for deleted appliances in patch history
No deleted appliances were found in the patch history

The following command cancels all schedule updates that include an invalid ID for the patch file.

```
sudo sysuptb clear-schedule
```

° Example:

```
sudo sysuptb clear-schedule
```

Executing test for invalid file id in patch schedules No patch schedules were found to have invalid file id

• The following command checks the filestore of downloaded packages for corrupt files and marks the corrupt files as incomplete.

```
sudo sysuptb filestore
```

° Example:

```
sudo sysuptb filestore
```

The following command checks the file system for available free space.

```
sudo sysuptb free-space <optionally, -d path_for_drive = minimum_
size>
```

If you do not provide the path and minimum size of the directory, the command examines /var to make sure it has 300MB of free space and / to make sure it has 1GB of free space.

° Example:

```
sudo sysuptb free-space --disk /var=300MB

Executing test for free disk space

Free disk space test summary: [Total: 1, Pass: 1, Failed: 0]
```

The command checks for update services that are stuck in a deactivating state and then heals them.

```
sudo sysuptb heal-service <optionally -s service name>
```

If you do not specify a service, the command examines the service siloupdate-manager.service. Starting with SL1 12.1.0, siloupdate-manager.service replaced em7 patch manager.service.

• Example:

```
sudo sysuptb heal-service

Executing test for deactivating services

Service test summary: [Total: 1, Active: 1, Inactive: 0, Healed: 0, Skipped: 0, Failed (to heal): 0]
```

• The following command checks the /etc/hosts file for an entry for IPv6 for the current server (like a loopback address). If no entry exists, the command adds ::1 to the /etc/hosts file.

```
sudo sysuptb hosts
```

° Example:

```
sudo sysuptb hosts

Executing hosts file check for IPV6 entry (::1) for localhost
An entry for ::1 is already present in the hosts file
```

The following command check is the filestore that holds the upgrade packages is empty.

```
sudo sysuptb is-filestore-empty
```

° Example:

```
sudo sysuptb is-filestore-empty

Executing test to check if filestore is empty
Filestore has 1026 files
```

• The following command checks the RPM database on /var/lib/rpm for corruption. If the command detects corruption, the output includes steps for remediation.

```
sudo sysuptb rpmdb
```

° Example:

```
sudo sysuptb rpmdb

Executing test for RPM database corruption

RPM database is intact
```

• The following command checks for a yum process which is hung.

```
sudo sysuptb yum-proc <optionally, -t timeout_in_minutes>
```

If you do not specify a running time, in minutes, the command searches for yum processes that have been running for more than 120 minutes.

° Example:

```
Executing test for hung yum process

No yum processes found

Yum process summary: [Total: 0, Hung: 0]
```

• The following command checks if yum is configured with proxy. If so, the command removes the proxy configuration.

```
sudo sysuptb yum-proxy
```

° Example:

```
sudo sysuptb yum-proxy
Proxy is not configured for yum.
```

Using the phtb Troubleshooting Tool

To use the **phtb** troubleshooting tool:

1. Either go to the console of an SL1 appliance using PhoneHome communication or use SSH to access the appliance.

2. Enter the following at the shell prompt:

```
sudo phtb -h
```

3. For more information about each argument, enter the following at the shell prompt:

```
sudo phtb <argument> -h
```

TIP: To learn more about a test run, use this command: sudo phtb help <test-name>

Available Commands

The following command checks destinations for SSH connectivity issues:

```
sudo phtb destination
```

• The following command checks the target host for SSH connectivity issues:

```
sudo phtb probe-host
```

• The following command checks connectivity to the proxy host, if configured:

sudo phtb proxy


Monitoring Deployment

For SL1 versions 8.12.0 and later, you can monitor deployment. To do so:

- 1. Either go to the console of the Database Server or use SSH to access the Database Server.
- 2. Enter the following command at the shell prompt:

monitor deploy

3. You should see something like the following figure:



- System Update Vitals. Displays the current status of the services that are required for System Update.
- Deployment Process Stats. Displays status of deployment on all SL1 appliances.
- Module Level Status. Displays the status of the three deployment steps.

Remove SL1 Appliances from Maintenance Mode

To disable user maintenance mode for all the SL1 appliances in your SL1 system:

- 1. Go to the **Appliance Manager** page. Note the list of SL1 appliances in your system.
- 2. Go to the **Device Manager** page (Registry > Devices > Device Manager) and select the checkbox for each SL1 appliance in your SL1 system.
- 3. In the Select Action drop-down list, select Change User Maintenance Mode: Disabled. This option disables

user maintenance mode for the selected devices.

4. Click the [Go] button.

CAUTION: Refer to the release notes for your current release to determine if you must **upgrade MariaDB** after upgrading.

CAUTION: Also refer to the release notes for your current release to determine if you must **reboot all SL1** appliances after upgrading.

Updating SL1 Extended Architecture

New installations of SL1 Extended Architecture are available only on SaaS deployments.

For existing on-premises deployments of SL1 Extended Architecture, see the section on *Upgrading SL1* Extended Architecture.

Automatically Upgrading MariaDB with a Script

TIP: To reduce spurious events, you can put the Database Server in maintenance mode while you upgrade MariaDB. For details, see the chapter on *Putting the Database Server into Maintenance Mode*

NOTE: Refer to the release notes for your current release to determine if you must upgrade MariaDB. Not every SL1 update requires an upgrade of for MariaDB.

SL1 will automatically update MariaDB-client, MariaDB-common, and MariaDB-shared RPMs but will not update the MariaDB Server RPM. You must update the MariaDB Server RPM after you install the SL1 update.

SL1 releases include the *module upgrade mariadb* script to automatically upgrade MariaDB server.

CAUTION: You should store all custom configuration settings for each MariaDB database in the file /etc/siteconfig/mysql.siteconfig. If you have added custom settings to the file /etc/my.cnf.d/silo_mysql.cnf, those changes will be overwritten each time you upgrade MariaDB. Before upgrading, copy any custom settings to the file /etc/siteconfig/mysql.siteconfig. SL1 will save these custom settings and apply them after you upgrade MariaDB.

The **module upgrade mariadb** script:

• Upgrades the following SL1 appliances:

- All Database Servers
- All-In-One Appliances
- Data Collectors
- Message Collectors
- Upgrades High Availability (HA) and Disaster Recovery (DR) systems
- Includes a "test only" option before executing upgrade
- Enforces upgrading the primary Database Server before upgrading secondary Database Server and the Data Collectors.
- Will skip SL1 appliances that have already been updated
- Logs entire sequence of commands and output for later analysis
- Stores log files in /data/logs/module_upgrade_mariadb.log and /data/logs/.upgrade_mariadb.log
- Checks for differences between current configuration and version you are about to install and spawns an alert. To skip this check, use the -s -s option

To upgrade MariaDB, perform the following:

- 1. Either go to the console of the Database Server or use SSH to access the Database Server.
- 2. At the shell prompt, enter the following command:

```
sudo /opt/em7/bin/module_upgrade_mariadb -m all
```

3. To see all the options for the **module_upgrade_mariadb** script, enter the following command at the shell prompt:

```
/opt/em7/bin/module_upgrade_mariadb -h
```

Usage:

```
module_upgrade_mariadb -m <module_id> [-t|--test] [-y|--assumeyes] [-
s|--skip_conf_file_error][-p|--pool size <number_of_modules>][-h|--
help]
```

- 4. The script includes these options:
 - -m parameter specifies the SL1 appliances that you want to upgrade. You can specify:
 - -m < mid1, mid2...midN > provides a comma-separated module IDs.
 - -m all: upgrade all appliances (Database Servers, All-In-One Appliances, Data Collectors, and Message Collectors).
 - ° -m all -db : upgrade all Database Servers.
 - ° -m all-cu : upgrade all Data Collectors and Message Collectors.
 - -t parameter specifies not to upgrade but instead to run a test of the upgrade script.
 - -y parameter specifies to automatically enter "yes" at all prompts.

- -s parameter specifies to ignore errors in the MySQL configuration files and proceed with the upgrade.
- -p parameter specifies the number of Data Collectors that you want to upgrade simultaneously. Database Servers will be upgraded one at a time. Possible values are 1 - 20. The default value is 1.
 - -p < number_of_modules > is the number of Data Collectors to upgrade simultaneously. Values are 1 20. The default value is 1.
- 5. To view the status of the automatic upgrade, enter the following command:

monitor upgrade mariadb

Additional Steps for MariaDB Upgrades in SL1 10.1.x

SL1 10.1.x included an upgrade to MariaDB. The upgrade did not include a tool, jemalloc, that helps manage memory usage.

NOTE: This section applies only to the following releases:

- 10.1.0
- 10.1.1
- 10.1.2
- 10.1.3
- 10.1.4
- 10.1.4.1
- 10.1.4.2
- 10.1.5
- 10.1.5.1

For SL1 versions later than 10.1.5.1, jemalloc is included with the platform. For SL1 versions prior to 10.1.0, jemalloc is included with the platform.

To avoid problems with memory usage on Database Servers, perform the following steps after upgrading MariaDB for 10.1.x.

NOTE: Perform these steps first on the active Database Server and then on each additional Database Server in your SL1 System.

- 1. Open an SSH session to the Database Server.
- 2. To verify that the Database Server is not currently running jemalloc, enter the following command at the shell prompt:

```
silo mysql -e 'show global variables like "version malloc library"'
```

If the Database Server is not currently running jemalloc, the shell will display the following:

Variable Name	Value
version_malloc_library	system

3. Search for the file /usr/lib64/**libjemalloc.so**. 1. If the file does not exist, contact ScienceLogic Customer Support to request the file jemalloc-3.6.0-1.el7.x86 64.rpm.

To install the RPM, use a file-transfer utility, copy the file to a directory on the SL1 appliance. Then enter the following commands at the shell prompt:

```
cd /usr/lib64 sudo yum install jemalloc-3.6.0-1.el7.x86_64.rpm
```

4. Create the file /etc/systemd/system/mariadb.service.d/jemalloc.conf, as follows:

```
vi /etc/systemd/system/mariadb.service.d/jemalloc.conf
```

5. Add the following lines to the file:

```
[Service]
Environment="LD PRELOAD=/usr/lib64/libjemalloc.so.1"
```

- 6. Save and close the file.
- 7. Reload the systemd config files with the following command:

```
sudo systemctl daemon-reload
```

8. Restart the Database Server:

To restart the **standalone Database Server** or the **primary Database Server in a cluster**, enter the following:

```
sudo systemctl restart mariadb
```

To restart each secondary Database Server in a cluster:

a. Open an SSH session to the secondary Database Server. At the shell prompt, enter:

```
coro config
```

- b. Select 1.
- c. When prompted to put the Database Server into maintenance, select **y**.
- d. Open an SSH session to the primary Database Server. To pause SL1, enter the following command at the shell prompt:

```
sudo touch /etc/.proc mgr pause
```

e. In the SSH session for the secondary Database Server, restart MariaDB:

```
crm resource restart mysql
```

f. After MariaDB has restarted successfully on the secondary Database Server, return to the SSH session on the primary Database Server. Remove the pause file for SL1 using the following command:

```
sudo rm /etc/.proc mgr pause
```

g. In the SSH session on the secondary Database Server, take the Database Server out of maintenance. At the shell prompt, enter:

- h. Select 1.
- i. When prompted to take the Database Server out of maintenance, select **y**.
- 9. To verify that jemalloc is running on the Database Server, enter the following command at the shell prompt:

If the Database Server is currently running jemalloc, the shell will display something like the following:

Variable Name	Value
,	jemalloc 3.6.0-0- g46c0af68bd248b04df75e4f92d5fb804c3d75340

10. Perform these steps on each Database Server in your SL1 system.

Manually Upgrading MariaDB

NOTE: Refer to the release notes for your current release to determine if you must upgrade MariaDB. Not every SL1 update requires an upgrade of MariaDB.

CAUTION: ScienceLogic strongly recommends that you upgrade MariaDB using the script described in **Automatically Upgrading MariaDB with a Script**.

TIP: To reduce spurious events, you can put the Database Server in maintenance mode while you upgrade MariaDB. For details, see the chapter on *Putting the Database Server into Maintenance Mode*

If you prefer to upgrade MariaDB manually, the following sections describe how to upgrade the MariaDB server for different SL1 appliance types and architectures.

When you update MariaDB, you must update the following SL1 appliances:

- All Database Servers
- All-In-One Appliances
- Data Collectors
- Message Collectors

CAUTION: You should store all custom configuration settings for each MariaDB database in the file /etc/siteconfig/mysql.siteconfig. If you have added custom settings to the file /etc/my.cnf.d/silo_mysql.cnf, those changes will be overwritten each time you upgrade MariaDB. Before upgrading, copy any custom settings to the file /etc/siteconfig/mysql.siteconfig. SL1 will save these custom settings and apply them after you upgrade MariaDB.

Download RPMs to SL1 Appliances

Before upgrading MariaDB, you must copy the RPMs from the primary Database Server to the Database Servers, All-In-One Appliances, Data Collectors, and Message Collectors in your SL1 system. To do this.

- 1. Open an SSH session to the Database Server.
- 2. To download the latest RPMs from the Database Server, enter the following at the shell prompt:

64.rpm http://localhost:10080/galera-4.rpm

For SL1 version 10.1.0 to 10.1.5:

```
wget --output-document /tmp/MariaDB-server-10.4.12-1.el7.centos.x86_
64.rpm http://localhost:10080/MariaDB-server.rpm
wget --output-document /tmp/galera-4-26.4.3-1.rhel7.el7.centos.x86
```

For SL1 version 10.1.6 and higher, download all of the packages listed when you enter the command:

```
cat /opt/em7/share/db_packages

wget --output-document /tmp/MariaDB-server.rpm
http://localhost:10080/<mariadb-server-pkg-from-db_packages>
wget --output-document /tmp/galera-4.rpm
http://localhost:10080/<galera-4-pkg-from-db_packages>
wget --output-document /tmp/socat.rpm http://localhost:10080/<socat-pkg-from-db packages>
```

3. Verify if the downloaded packages are valid (not corrupt or incomplete downloads) by entering the following commands:

```
rpm -qip /tmp/MariaDB-server.rpm
rpm -qip /tmp/galera-4.rpm
rpm -qip /tmp/socat.rpm
```

If any errors are reported, try restarting siloupdate-pkgserver, using the following command, and retry downloading and verifying the RPM files again.

```
systemctl restart siloupdate-pkgserver
```

- 4. Use SCP or another secure copy program to copy these files to the /tmp directory on each Database Server, All-In-One Appliance, Data Collector, and Message Collector:
 - MariaDDB-server.rpm
 - galera-4.rpm

CAUTION: To conserve disk space, ScienceLogic recommends you delete the RPMs from the /tmp directory the on the Database Servers, All-In-One Appliances, Data Collectors, and Message Collectors in your SL1 system after you successfully upgrade MariaDB.

Manually Upgrade Two Database Servers Configured for High Availability or Disaster Recovery

To upgrade a High Availability or Disaster Recovery cluster, perform the following steps:

WARNING: The system will be unavailable when performing these steps.

Step 1: On the Secondary Database Server

You must put the secondary Database Server in maintenance mode. To do this:

- 1. Open an SSH session to the Database Server.
- 2. At the shell prompt, assume root privileges:

```
sudo -s
```

3. When prompted, enter the administrator password.

4. At the shell prompt, enter the following command:

```
coro config
```

The following menu appears:

- 1) Enable Maintenance
- 2) Option Disabled
- 3) Promote DRBD
- 4) Stop Pacemaker
- 5) Resource Status
- 6) Quit
- 5. Enter "1".

Step 2: On the Primary Database Server

1. To determine the current installed version of the RPMs, enter the following command:

```
sudo rpm -qa ^MariaDB-*
```

2. To stop SL1 and MariaDB, enter the following commands at the shell prompt:

```
sudo systemctl stop em7
sudo systemctl stop mariadb.service
```

3. To stop the MySQL resource, enter the following command:

```
sudo crm resource stop mysql
```

4. To save the current enabled state for mariadb.service, enter the following command:

```
export MSRV=`sudo systemctl is-enabled mariadb.service`
```

5. Check the version of MariaDB-server that you are running.

```
rpm -q MariaDB-server
```

WARNING: You **must** follow the steps below that correspond to your version of MariaDB. Step 6 is specific to MariaDB-server version 10.1.x, while Step 7 is specific to MariaDB-server versions 10.4.12 and higher.

6. MariaDB-server version 10.1.x. If you are running MariaDB-server version 10.1.x:

WARNING: Do these steps in order. Doing the steps in any other order will result in unintended consequences.

a. Remove MariaDB-server by using the following commands:

```
sudo rpm --nodeps -ev MariaDB-server
```

b. Replace the Galera package and install the new MariaDB-server package by using the following commands:

```
sudo yum --disablerepo=* swap -- remove galera -- install
/tmp/galera-4.rpm
sudo yum --disablerepo=* install /tmp/MariaDB-server.rpm
```

7. MariaDB-server version 10.4.12 and higher. If you are running MariaDB-server version 10.4.12 or higher, upgrade the MariaDB-server package and dependent packages (galera-4 and socat) by using the following commands:

```
sudo yum --disablerepo=* install /tmp/galera-4.rpm /tmp/socat.rpm
sudo yum --disablerepo=* upgrade /tmp/MariaDB-server.rpm
```

8. To remove incompatible backup packages, enter the following command:

```
sudo yum remove percona-xtrabackup
```

NOTE: If the "yum remove" command fails, it means that the package does not exist on the SL1 appliance. You can ignore the error message.

9. To regenerate the configuration file for MariaDB, enter the following command:

```
sudo /opt/em7/share/scripts/generate-my-conf.py -f -o
/etc/my.cnf.d/silo mysql.cnf
```

10. To re-start MariaDB, enter the following command:

```
sudo systemctl daemon-reload
sudo systemctl start mariadb
```

11. To restart the MySQL resource, enter the following command:

```
sudo crm resource start mysql
```

12. To restore the mariadb.service enabled state, enter the following command:

```
sudo systemctl ${MSRV::-1} mariadb.service
```

13. To upgrade the internal configuration for the database, enter the following:

```
sudo mysql upgrade -u root -p
```

14. To restart the em7 service, enter the following commands:

```
sudo systemctl start em7
sudo rpm -qa ^MariaDB-*
```

Step 3: On the Secondary Database Server

1. Determine the current installed version of the RPMs using the following command:

```
sudo rpm -qa ^MariaDB-*
```

2. To save the current enabled state for mariadb.service, enter the following:

```
export MSRV=`sudo systemctl is-enabled mariadb.service`
```

3. Check the version of MariaDB-server that you are running.

```
rpm -q MariaDB-server
```

WARNING: You **must** follow the steps that correspond to your version of MariaDB. Step 4 is specific to MariaDB-server version 10.1.x, while Step 5 is specific to MariaDB-server versions 10.4.12 and higher.

4. MariaDB-server 10.1.x: If you are running MariaDB-server version 10.1.x:

WARNING: Do these steps in order. Doing the steps in any other order will result in unintended consequences.

a. Remove MariaDB-server by using the following command:

```
sudo rpm --nodeps -ev MariaDB-server
```

b. Replace the Galera package and install the new MariaDB-server package by using the following commands:

```
sudo yum --disablerepo=* swap -- remove galera -- install
/tmp/galera-4.rpm
sudo yum --disablerepo=* install /tmp/MariaDB-server.rpm
```

5. **MariaDB-server 10.4.12 or higher**: If you are running *MariaDB-server version 10.4.12* or higher, upgrade the MariaDB-server package and dependent packages (galera-4 and socat) by using the following commands:

```
sudo yum --disablerepo=* install /tmp/galera-4.rpm /tmp/socat.rpm
sudo yum --disablerepo=* upgrade /tmp/MariaDB-server.rpm
```

6. To remove incompatible backup packages, enter the following command:

```
sudo yum remove percona-xtrabackup
```

NOTE: If the "yum remove" command fails, it means that the package does not exist on the SL1 appliance. You can ignore the error message.

7. To regenerate the configuration file for MariaDB, enter the following command:

```
sudo /opt/em7/share/scripts/generate-my-conf.py -f -o
/etc/my.cnf.d/silo mysql.cnf
```

8. To restore the mariadb.service enabled state, enter the following command:

```
sudo systemctl ${MSRV::-1} mariadb.service
```

9. To take the secondary Database Server out of maintenance mode, enter the following command at the shell prompt:

```
sudo -s
```

- 10. When prompted, enter the administrator password.
- 11. At the shell prompt, enter the following command:

```
coro config
```

The following prompt appears:

- 1) Disable Maintenance
- 2) Option Disabled
- 3) Promote DRBD
- 4) Stop Pacemaker
- 5) Resource Status
- 6) Quit
- 12. Enter "1".

Manually Upgrade Three Database Servers Configured for High Availability and Disaster Recovery

To upgrade a High Availability/Disaster Recovery cluster, perform the following steps:

WARNING: The system will be unavailable when performing these steps.

Step 1: On the Secondary Database Server

You must put the secondary Database Server in maintenance mode. To do this:

- 1. Open an SSH session to the Database Server.
- 2. At the shell prompt, assume root privileges:

```
sudo -s
```

- 3. When prompted, enter the administrator password.
- 4. At the shell prompt, enter the following command:

```
coro config
```

- 5. The following prompt appears:
 - 1) Disable Maintenance
 - 2) Option Disabled
 - 3) Promote DRBD
 - 4) Stop Pacemaker
 - 5) Resource Status
 - 6) Quit
- 6. Enter "1".

Step 2: On the Primary Database Server

1. Determine the current installed version of the RPMs:

```
sudo rpm -qa ^MariaDB-*
```

2. Stop SL1 and MariaDB using the following commands:

```
sudo systemctl stop em7
sudo systemctl stop mariadb.service
```

3. Stop the MySQL resource:

```
sudo crm resource stop mysql
```

4. Save the current enabled state for the mariadb.service:

```
export MSRV=`sudo systemctl is-enabled mariadb.service`
```

5. Check the version of MariaDB-server that you are running:

```
rpm -q MariaDB-server
```

WARNING: You must follow the steps that correspond to your version of MariaDB.

6. MariaDB-server version 10.1.x. If you are running MariaDB-server version 10.1.x:

WARNING: Do these steps in order. Doing the steps in any other order will result in unintended consequences.

a. Remove MariaDB-server by using the following command:

```
sudo rpm --nodeps -ev MariaDB-server
```

b. Replace the Galera package and install the new MariaDB-server package by using the following commands:

```
sudo yum --disablerepo=* swap -- remove galera -- install
/tmp/galera-4.rpm
sudo yum --disablerepo=* install /tmp/MariaDB-server.rpm
```

7. **MariaDB-server version 10.4.12 and higher**. If you are running MariaDB-version 10.4.12 or higher, upgrade the MariaDB-server package and dependent packages (galera-4 and socat) by using the following commands:

```
sudo yum --disablerepo=* install /tmp/galera-4.rpm /tmp/socat.rpm
sudo yum --disablerepo=* upgrade /tmp/MariaDB-server.rpm
```

8. Remove incompatible backup packages:

```
sudo yum remove percona-xtrabackup
```

NOTE: If the "yum remove" command fails, it means that the package does not exist on the SL1 appliance. You can ignore the error message.

9. Regenerate the configuration file for MariaDB:

```
sudo /opt/em7/share/scripts/generate-my-conf.py -o -f
/etc/my.cnf.d/silo_mysql.cnf
```

10. Restart Maria DB:

```
sudo systemctl daemon-reload
sudo systemctl start mariadb
```

11. Restart the MySQL resource:

```
sudo crm resource start mysql
```

12. Restore the mariadb.service enabled state:

```
sudo systemctl ${MSRV::-1} mariadb.service
```

13. Upgrade the internal configuration for the database:

```
sudo mysql upgrade -u root -p
```

14. Restart the em7 service:

```
sudo systemctl start em7
```

Step 3: On the Secondary Database Server

1. Save the current enabled state for the mariadb.service:

```
export MSRV=`sudo systemctl is-enabled mariadb.service`
```

2. Check the version of MariaDB-server that you are running:

```
rpm -q MariaDB-server
```

WARNING: You must follow the steps that correspond to your version of MariaDB.

3. MariaDB-server version 10.1.x. If you are running MariaDB-server version 10.1.x.

WARNING: Do these steps in order. Doing the steps in any other order will result in unintended consequences.

a. Remove MariaDB-server:

```
sudo rpm --nodeps -ev MariaDB-server
```

b. Replace the Galera package and install the new MariaDB-server package by using the following commands:

```
sudo yum --disablerepo=* swap -- remove galera -- install
/tmp/galera-4.rpm
sudo yum --disablerepo=* install /tmp/MariaDB-server.rpm
```

4. **MariaDB-server version 10.4.12 and higher**. If you are running MariaDB-version 10.4.12 or higher, upgrade the MariaDB-server package and dependent packages (galera-4 and socat) by using the following commands:

```
sudo yum --disablerepo=* install /tmp/galera-4.rpm /tmp/socat.rpm
sudo yum --disablerepo=* upgrade /tmp/MariaDB-server.rpm
```

5. Remove incompatible backup packages:

```
sudo yum remove percona-xtrabackup
```

NOTE: If the "yum remove" command fails, it means that the package does not exist on the SL1 appliance. You can ignore the error message.

6. Regenerate the configuration file for MariaDB:

```
sudo /opt/em7/share/scripts/generate-my-conf.py -o -f
/etc/my.cnf.d/silo mysql.cnf
```

7. Restore the mariadb.service enabled state:

```
sudo systemctl ${MSRV::-1} mariadb.service
```

8. Assume root privileges:

```
sudo -s
```

- 9. When prompted, enter the administrator password.
- 10. At the shell prompt, enter the following command:

```
coro config
```

- 11. The following prompt appears:
 - 1) Disable Maintenance
 - 2) Option Disabled
 - 3) Promote DRBD
 - 4) Stop Pacemaker
 - 5) Resource Status
 - 6) Quit
- 12. Enter "1".

Step 4: On the Disaster Recovery Database Server

- 1. Open an SSH session to the Disaster Recovery Database Server.
- 2. Assume root privileges:

```
sudo -s
```

- 3. When prompted, enter the administrator password.
- 4. Save the current enabled state for the mariadb.service:

```
export MSRV=`sudo systemctl is-enabled mariadb.service`
```

5. Check the version of MariaDB-server that you are running:

```
rpm -q MariaDB-server
```

WARNING: You must follow the steps that correspond to your version of MariaDB.

6. MariaDB-server version 10.1.x. If you are running MariaDB-server version 10.1.x.

WARNING: Do these steps in order. Doing the steps in any other order will result in unintended consequences.

a. Remove Maria DB-server:

```
sudo rpm --nodeps -ev MariaDB-server
```

b. Replace the Galera package and install the new MariaDB-server package by using the following commands:

```
sudo yum --disablerepo=* swap -- remove galera -- install
/tmp/galera-4.rpm
sudo yum --disablerepo=* install /tmp/MariaDB-server.rpm
```

7. **MariaDB-server version 10.4.12 and higher**. If you are running MariaDB-version 10.4.12 or higher, upgrade the MariaDB-server package and dependent packages (galera-4 and socat) by using the following commands:

```
sudo yum --disablerepo=* install /tmp/galera-4.rpm /tmp/socat.rpm
sudo yum --disablerepo=* upgrade /tmp/MariaDB-server.rpm
```

8. Remove incompatible backup packages:

```
sudo yum remove percona-xtrabackup
```

NOTE: If the "yum remove" command fails, it means that the package does not exist on the SL1 appliance. You can ignore the error message.

9. Regenerate the configuration file for MariaDB:

```
sudo /opt/em7/share/scripts/generate-my-conf.py -o -f
/etc/my.cnf.d/silo_mysql.cnf
```

10. Restore the mariadb.service enabled state:

```
sudo systemctl ${MSRV::-1} mariadb.service
```

Manually Upgrading Standalone Database Servers, All-In-One Appliances, Data Collectors, and Message Collectors

To upgrade MariaDB on one or more Database Servers that are not configured for high availability or disaster recovery, a single All-In-One Appliance, one or more Data Collectors, or one or more Message Collectors, perform the following steps:

WARNING: The Database Server, All-In-One Appliance, Data Collector, or Message Collector will be unavailable when performing these steps.

- 1. Go to the console or open an SSH session to the SL1 appliance.
- 2. Stop SL1 and mariadb:

```
sudo systemctl stop em7
sudo systemctl stop mariadb.service
```

3. Save the current enabled state for the mariadb.service:

```
export MSRV=`sudo systemctl is-enabled mariadb.service`
```

4. Check the version of MariaDB-server that you are running:

```
rpm -q MariaDB-server
```

WARNING: You must follow the steps that correspond to your version of MariaDB.

5. MariaDB-server version 10.1.x. If you are running MariaDB-server version 10.1.x.

WARNING: Do these steps in order. Doing the steps in any other order will result in unintended consequences.

a. Remove MariaDB-server:

```
sudo rpm --nodeps -ev MariaDB-server
```

b. Replace the Galera package and install the new MariaDB-server package by using the following commands:

```
sudo yum --disablerepo=* swap -- remove galera -- install
/tmp/galera-4.rpm
sudo yum --disablerepo=* install /tmp/MariaDB-server.rpm
```

6. **MariaDB-server version 10.4.12 and higher**. If you are running MariaDB-version 10.4.12 or higher, upgrade the MariaDB-server package and dependent packages (galera-4 and socat) by using the following commands:

```
sudo yum --disablerepo=* install /tmp/galera-4.rpm /tmp/socat.rpm
sudo yum --disablerepo=* upgrade /tmp/MariaDB-server.rpm
```

7. Remove incompatible backup packages:

```
sudo yum remove percona-xtrabackup
```

NOTE: If the "yum remove" command fails, it means that the package does not exist on the SL1 appliance. You can ignore the error message.

8. Regenerate the configuration file for MariaDB:

```
sudo /opt/em7/share/scripts/generate-my-conf.py -o -f
/etc/my.cnf.d/silo_mysql.cnf
```

9. Restart Maria DB:

```
sudo systemctl daemon-reload
sudo systemctl start mariadb
```

10. Restore the mariadb.service enabled state:

```
sudo systemctl ${MSRV::-1} mariadb.service
```

11. Upgrade the internal configuration for the database:

```
sudo mysql upgrade -u root -p
```

12. Restart the em7 service:

```
sudo systemctl start em7
```

13. Repeat all the steps in this section on each non-HA/DR Database Server, All-In-One Appliance, Data Collector, and Message Collector.

Additional Steps for MariaDB Upgrades in 10.1.x

SL1 10.1.x included an upgrade to MariaDB. The upgrade did not include a tool, jemalloc, that helps manage memory usage.

NOTE: This section applies only to the following releases:

- 10.1.0
- 10.1.1
- 10.1.2
- 10.1.3
- 10.1.4
- 10.1.4.1
- 10.1.4.2
- 10.1.5
- 10.1.5.1

For SL1 versions later than 10.1.5.1, jemalloc is included with the platform. For SL1 versions prior to 10.1.0, jemalloc is included with the platform.

To avoid problems with memory usage on Database Servers, perform the following steps after upgrading MariaDB for 10.1.x.

NOTE: Perform these steps first on the active Database Server and then on each additional Database Server in your SL1 System.

- 1. Open an SSH session to the Database Server.
- 2. To verify that the Database Server is not currently running jemalloc, enter the following command at the shell prompt:

```
silo mysql -e 'show global variables like "version malloc library"'
```

If the Database Server is not currently running jemalloc, the shell will display the following:

Variable Name	Value
version_malloc_library	system

3. Search for the file /usr/lib64/**libjemalloc.so.1**. If the file does not exist, contact ScienceLogic Customer Support to request the file jemalloc-3.6.0-1.el7.x86 64.rpm.

To install the RPM, use a file-transfer utility, copy the file to a directory on the SL1 appliance. Then enter the following commands at the shell prompt:

```
cd /usr/lib64 sudo yum install jemalloc-3.6.0-1.el7.x86_64.rpm
```

4. Create the file /etc/systemd/system/mariadb.service.d/jemalloc.conf, as follows:

```
vi /etc/systemd/system/mariadb.service.d/jemalloc.conf
```

5. Add the following lines to the file:

```
[Service]
Environment="LD_PRELOAD=/usr/lib64/libjemalloc.so.1"
```

- 6. Save and close the file.
- 7. Reload the systemd config files with the following command:

```
sudo systemctl daemon-reload
```

8. Restart the Database Server:

To restart the **standalone Database Server** or the **primary Database Server in a cluster**, enter the following:

```
sudo systemctl restart mariadb
```

To restart each secondary Database Server in a cluster:

a. Open an SSH session to the secondary Database Server. At the shell prompt, enter:

- b. Select 1.
- c. When prompted to put the Database Server into maintenance, select **y**.
- d. Open an SSH session to the primary Database Server. To pause SL1, enter the following command at the shell prompt:

```
sudo touch /etc/.proc mgr pause
```

e. In the SSH session for the secondary Database Server, restart Maria DB:

```
crm resource restart mysql
```

f. After MariaDB has restarted successfully on the secondary Database Server, return to the SSH session on the primary Database Server. Remove the pause file for SL1 using the following command:

```
sudo rm /etc/.proc_mgr_pause
```

g. In the SSH session on the secondary Database Server, take the Database Server out of maintenance. At the shell prompt, enter:

```
coro config
```

- h. Select 1.
- i. When prompted to take the Database Server out of maintenance, select **y**.
- 9. To verify that jemalloc is running on the Database Server, enter the following command at the shell prompt:

```
silo_mysql -e 'show global variables like "version_malloc_library"'
```

If the Database Server is currently running jemalloc, the shell will display something like the following:

Variable Name	Value
,	jemalloc 3.6.0-0- g46c0af68bd248b04df75e4f92d5fb804c3d75340

10. Perform these steps on each Database Server in your SL1 system.

Rebooting Appliances in the SL1 Distributed Stack

NOTE: Refer to the release notes for your current release to determine if you must reboot all SL1 appliances. Not every SL1 update requires rebooting.

When an upgrade requires a reboot, use the steps listed in this section to reboot all SL1 appliances in the Distributed stack.

Rebooting the Administration Portal

You can reboot Administration Portals either from the user interface or from the command line.

Rebooting Multiple Administration Portals

If your SL1 system includes multiple Administration Portals, you can remotely reboot Administration Portals from another Administration Portal. To do so:

- 1. Go to the **Appliance Manager** page (System > Settings > Appliances).
- 2. Select the checkboxes for the SL1 appliances you want to reboot.
- 3. In the [Select Action] menu, select Reboot and click the [Go] button.
- 4. Click the **[OK]** button when the "Are you sure you want to reboot the selected appliances?" message is displayed.
- 5. During the reboot, the user interface for the affected Administration Portal unavailable.
- 6. When the reboot has completed, the **Audit Logs** page (System > Monitor > Audit Logs) will include an entry for each appliance that was rebooted.

Rebooting a Single Administration Portal

If your SL1 system include only a single Administration Portal, perform the following steps to reboot that Administration Portal:

- 1. Either go to the console of the Database Server or use SSH to access the Database Server.
- 2. Log in as **em7admin** with the appropriate password.
- 3. At the shell prompt, execute the following:

python -m silo_common.admin_toolbox <appliance_ID> "/usr/bin/sudo
/usr/sbin/shutdown -r +1"

where:

 appliance_ID is the appliance ID for the Data Collector, Message Collector, or Administration Portal

Rebooting Data Collectors and Message Collectors

You can reboot Data Collectors and Message Collectors either from the user interface or from the command line.

Rebooting Data Collectors and Message Collectors from the Appliance Manager page

From the SL1 user interface, perform the following steps to reboot a Data Collector or a Message Collector:

- 1. Go to the **Appliance Manager** page (Appliance Manager).
- 2. Select the checkbox for each SL1 appliance you want to reboot.
- 3. In the [Select Action] menu, select Reboot and click the [Go] button.
- 4. Click the **[OK]** button when the "Are you sure you want to reboot the selected appliances?" message is displayed.
- 5. During the reboot, go to the **System Logs** page (System > Monitor > System Logs). You should see this message:

```
Major: Could not connect to module (5) database USING SSL=TRUE: Error attempting to connect to database with SSL enabled True: (2003, 'Can't connect to MySQL server on '10.2.12.77' (113 "No route to host")')
```

6. When the reboot has completed, the **Audit Logs** page (System > Monitor > Audit Logs) will include an entry for each appliance that was rebooted.

Rebooting Data Collectors and Message Collectors from the Command Line

From the console of the Database Server or SSH to the Database Server, perform the following steps to reboot Data Collector or Message Collector:

- 1. Either go to the console of a Database Server or SSH to access the Database Server.
- 2. Log in as **em7admin** with the appropriate password.
- 3. At the shell prompt, execute the following:

```
python -m silo_common.admin_toolbox <appliance_ID> "/usr/bin/sudo
/usr/sbin/shutdown -r +1"
```

where:

appliance ID is the appliance ID for the Data Collector, Message Collector, or Administration Portal.

Rebooting Standalone All-In-One Appliance and Standalone Database Server

Perform the following steps to reboot a standalone All-In-One Appliance or a standalone Database Server:

- 1. Either go to the console or use SSH to access the SL1 appliance.
- 2. Log in as **em7admin** with the appropriate password.
- 3. On the SL1 appliance, pause the system and shutdown MariaDB.

```
sudo touch /tmp/.proc_mgr_pause
sudo systemctl stop mariadb
```

4. Reboot the SL1 appliance:

```
sudo reboot
```

- 5. After the SL1 appliance has rebooted, either go to the console or use SSH to access the SL1 appliance.
- 6. Log in as **em7admin** with the appropriate password.
- 7. Un-pause the SL1 Appliance:

```
sudo rm /tmp/.proc mgr pause
```

Rebooting Two Database Servers Configured for Disaster Recovery

Perform the following steps to reboot two Database Servers configured for Disaster Recovery:

- 1. Either go to the console of the **primary** Database Server or use SSH to access the primary Database Server.
- 2. Log in as **em7admin** with the appropriate password.
- 3. Check the status of both Database Servers. To do this, enter the following at the shell prompt:

```
cat /proc/drbd
```

Your output will look like this:

```
1: cs:Connected ro:Primary/Secondary ds:UpToDate/UpToDate C r---ns:17567744 al:0 bm:1072 lo:0 pe:0 ua:0 ap:0 ep:1 wo:b oos:12521012
```

4. Pause the system and shutdown MariaDB on the **primary** Database Server. Enter the password for the em7admin user when prompted:

```
sudo touch /tmp/.proc_mgr_pause
sudo systemctl stop pacemaker
sudo systemctl stop mariadb
```

5. Reboot the **primary** Database Server:

```
sudo reboot
```

- 6. After the **primary** appliance has rebooted, log in to the console of the **primary** Database Server again.
- 7. Execute the following command on the **primary** Database Server:

```
coro config
```

- 8. Select the [Promote DRBD] option.
- 9. Execute the following commands on the **primary** Database Server:

```
sudo rm /tmp/.proc mgr pause
```

- 10. Enter the password for the em7admin user and confirm the command when prompted.
- 11. Log in to the **secondary** Database Server as the em7admin user using the console or SSH.
- 12. Execute the following command on the **secondary** Database Server to reboot the appliance:

```
sudo reboot
```

13. Enter the password for the em7admin user when prompted.

Rebooting Two Database Servers in a High Availability Cluster

Perform the following steps to reboot two Database Servers in a high availability cluster:

- Either go to the console of the secondary Database Server or use SSH to access the secondary Database Server.
- 2. Log in as **em7admin** with the appropriate password.
- 3. Check the status of both Database Servers. To do this, enter the following at the shell prompt:

```
cat /proc/drbd
```

Your output will look like this:

```
1: cs:Connected ro:Secondary/Primary ds:UpToDate/UpToDate C r----
```

ns:17567744 al:0 bm:1072 lo:0 pe:0 ua:0 ap:0 ep:1 wo:b oos:12521012

NOTE: If your output includes "ro:Secondary/Primary", but does not include "UpToDate/UpToDate", data is being synchronized between the two appliances. You must wait until data synchronization has finished before rebooting.

4. Stop the cluster service on the **secondary** Database Server:

```
sudo systemctl stop pacemaker
```

- 5. Enter the password for the em7admin user when prompted.
- 6. Either go to the console of the **primary** Database Server or use SSH to access the **primary** Database Server.
- 7. Log in as **em7admin** with the appropriate password.
- 8. Pause the system and stop the cluster service on the **primary** Database Server. Enter the password for the em7admin user when prompted:

```
sudo touch /tmp/.proc_mgr_pause
sudo systemctl stop pacemaker
sudo systemctl stop mariadb
```

9. Reboot the **primary** Database Server:

```
sudo reboot
```

- After the **primary** Database Server has rebooted, either go to the console of the **primary** Database Server
 or use SSH to access the **primary** Database Server.
- 11. Log in as **em7admin** with the appropriate password.
- 12. Execute the following command on the **primary** Database Server:

```
sudo rm /tmp/.proc_mgr_pause
```

- 13. Enter the password for the em7admin user and confirm the command when prompted.
- 14. Either go to the console of the **secondary** Database Server or use SSH to access the **secondary** Database Server.
- 15. Log in as **em7admin** with the appropriate password.
- 16. Reboot the **secondary** Database Server:

```
sudo reboot
```

17. Enter the password for the em7admin user when prompted.

Rebooting Three Database Servers Configured for High Availability and Disaster Recovery

Perform the following steps to reboot three Database Servers configured for high availability and disaster recovery. In this configuration, two Database Servers are configured as a High Availability cluster and one Database Server is configured for Disaster Recovery.

- 1. Either go to the console of the **secondary** Database Server in the HA cluster or use SSH to access the **secondary** Database Server in the HA cluster,
- 2. Log in as **em7admin** with the appropriate password.

3. Check the status of both Database Servers in the HA cluster. To do this, enter the following at the shell prompt:

```
cat /proc/drbd
```

Your output will look like this:

```
10: cs:Connected ro:Secondary/Primary ds:UpToDate/UpToDate C r----
```

```
ns:17567744 al:0 bm:1072 lo:0 pe:0 ua:0 ap:0 ep:1 wo:b oos:12521012
```

NOTE: If your output includes "ro:Secondary/Primary", but does not include "UpToDate/UpToDate", data is being synchronized between the two appliances. You must wait until data synchronization has finished before rebooting.

4. Stop the cluster service with the following command on the **secondary** Database Server in the HA cluster:

```
sudo systemctl stop pacemaker
```

- 5. Enter the password for the em7admin user when prompted.
- 6. Either go to the console of the **primary** Database Server in the HA cluster or use SSH to access the **primary** Database Server in the HA cluster.
- 7. Log in as **em7admin** with the appropriate password.
- 8. Pause the system and stop the cluster service on the **primary** Database Server in the HA cluster:

```
sudo touch /tmp/.proc_mgr_pause
sudo systemctl stop pacemaker
```

- 9. Enter the password for the em7admin user when prompted
- 10. Reboot the **primary** Database Server in the HA cluster:

```
sudo reboot
```

- 11. After the **primary** Database Server in the HA cluster has rebooted, either go to the console of the **primary** Database Server in the HA cluster or use SSH to access the **primary** Database Server in the HA cluster.
- 12. Execute the following command on the **primary** Database Server in the HA cluster:

```
sudo rm /tmp/.proc_mgr_pause
```

- 13. Enter the password for the em7admin user and confirm the command when prompted.
- 14. Either go to the console of the **secondary** Database Server in the HA cluster or use SSH to access the **secondary** Database Server in the HA cluster.
- 15. Log in as **em7admin** with the appropriate password.
- 16. Reboot the **secondary** Database Server in the HA cluster:

```
sudo reboot
```

17. Enter the password for the em7admin user when prompted.

- 18. Either go to the console of the Database Server for Disaster Recovery or use SSH to access the Database Server for Disaster Recovery.
- 19. Log in as **em7admin** with the appropriate password.
- 20. Reboot the Database Server for Disaster Recovery:

sudo reboot

21. Enter the password for the em7admin user when prompted.

Restoring the SSL Certificates

To restore your SSL Certificates:

- 1. Login to the console of the Database Server or SSH to the Database Server.
- 2. Open a shell session.
- 3. Enter the following at the shell prompt:
 - cp /etc/nginx/silossl.key.bak /etc/nginx/silossl.key
 - cp /etc/nginx/silossl.pem.bak /etc/nginx/silossl.pem
- 4. Repeat these steps on each Database Server in your SL1 system.

Resetting the Timeout for PhoneHome Watchdog

NOTE: This section applies to users who are upgrading from SL1 11.1.x or earlier and have an existing PhoneHome configuration. If you are upgrading from SL1 11.2.0 or later or you do not have a pre-11.2.0 PhoneHome configuration, you can ignore this section.

You can manually reset the settings for the PhoneHome Watchdog server back to the settings you used before the upgrade.

To edit the settings for the watchdog service:

- 1. Log in to the console of the Data Collector as the root user or open an SSH session on the Data Collector.
- 2. View your PhoneHome Watchdog settings:

```
phonehome watchdog view
```

Your output will look like the following:

```
Current settings:
autosync: yes
interval: 120
state: enabled
autoreconnect: yes
timeoutcount: 1
check: default
```

Note the settings for *interval* and *timeoutcount*, so you can restore them after the upgrade.

3. To change the settings for SL1 upgrade, type the following at the command line:

```
sudo phonehome watchdog set interval=<previous setting>;
sudo phonehome watchdog set timeoutcount=<previous setting>;
systemctl stop em7_ph_watchdog;
systemctl start em7_ph_watchdog;
```

- 4. Repeat these steps on each Data Collector.
- 5. Repeat these steps on each Message Collector.
- 6. Repeat these steps on each Database Server.

Updating Default PowerPacks

Every time you install a software update on your appliances, ScienceLogic recommends that you also install the updates for all the PowerPacks that were included in the software update.

ScienceLogic includes multiple PowerPacks in the default installation of SL1. When you apply an update to your system, new versions of the default PowerPacks will be automatically imported in to your system. If a PowerPack is included in an update and is not currently installed on your system, SL1 will automatically install the PowerPack. If a PowerPack is included in an update and is currently installed on your system, SL1 will automatically import (but not install) the PowerPack.

If PowerPacks have been imported into your system but have not been installed, the **Update** column appears in the **PowerPack Manager** page (System > Manage > PowerPacks). For each PowerPack that has been imported to your system but has not been installed, the lightning bolt icon () appears in the **Update** field on the **PowerPack Manager** page.

To install the updates for multiple PowerPacks:

1. Go to the **PowerPack Manager** page (System > Manage > PowerPacks) and click the checkbox for each PowerPack you want to install.

- 2. In the **Select Action** drop-down field (in the lower right), choose *Update PowerPack(s)*. SL1 displays a warning message before updating the PowerPack(s).
- 3. Click the **[OK]** button to continue the installation.
- 4. Click the **[Go]** button. If you completed the update, updated information about the PowerPack will appear in the **PowerPack Manager** page. All the items in the PowerPack will be installed in your SL1 system.

NOTE: You can install multiple PowerPacks with the **Select Action** drop-down list only if each selected PowerPack includes an embedded Installation Key. PowerPacks that do not include embedded Installation Keys will fail to install.

NOTE: If the *Enable Selective PowerPack Field Protection* checkbox on the *Behavior Settings* page (System > Settings > Behavior) is selected, certain fields in Event Policies, Dynamic Applications, and Device Classes will **not** be updated.

Configuring Subscription Billing

If your SL1 system is configured to communicate with the ScienceLogic billing server, usage data will be sent automatically from your SL1 system to the ScienceLogic billing server once a day. After the ScienceLogic billing server receives the usage data, SL1 will automatically mark the license usage file as delivered.

Sending usage data to the ScienceLogic billing server ensures that your bill is accurate and that ScienceLogic can continue making improvements to the SL1 products.

To determine if you have correctly configured Subscription Billing:

- Go to the **System Usage** page (System > Monitor > System Usage) or (Manage > Subscription Usage). Click the **[Subscription]** button and choose **License Data Delivery Status**.
- For air-gapped SL1 systems, the value of **Summary Date** should be within the past 48 hours.
- For SL1 systems that connect to ScienceLogic, the value of **Summary Date** should be within the past 48 hours and the value of **Delivery Status** is 1.

For details on configuring subscription billing, see the **Subscription Billing** manual.

Chapter

6

Upgrading SL1 Extended Architecture

Overview

This chapter provides detailed steps for performing an upgrade on SL1 Extended Architecture.

NOTE: New installations of SL1 Extended Architecture are available only on SaaS deployments.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon
- To view a page containing all of the menu options, click the Advanced menu icon (...).

Workflow	183
Prerequisites	183
Resizing the Disks on the Compute Node	184
Installing ORAS	185
Obtaining Your Harbor Credentials	186
Upgrading to 12.2.x	186
Upgrading to 12.1.1	192
Upgrading to 12.1.0.x	204
Upgrading to 11.3.x	208
Upgrading to 11.2.x	219
Upgrading to 11.1.x	228

Workflow

The following sections describe the steps to plan and deploy an SL1 update.

If would like assistance planning an upgrade path that minimizes downtime, contact your Customer Success Manager.

The workflow for upgrading SL1 is:

- 1. Plan the update.
- 2. Schedule maintenance windows.
- 3. Review pre-upgrade best practices for SL1.
- 4. Back up SSL certificates.
- 5. Set the timeout for PhoneHome Watchdog.
- 6. Adjust the timeout for slow connections.
- 7. Run the system status script on the Database Server or All-In-One before upgrading.
- 8. Upgrade the SL1 Distributed Architecture using the System Update tool (System > Tools > Updates).
- 9. Remove SL1 appliances from maintenance mode.
- 10. Upgrade the Extended Architecture.
- 11. Upgrade MariaDB, if needed.
- 12. Reboot SL1 appliances, if needed.
- 13. Restore SSL certificates.
- 14. Reset the timeout for PhoneHome Watchdog.
- 15. Update the default PowerPacks.
- 16. Configure Subscription Billing (one time only). For details, see the **Subscription Billing** manual.

NOTE: For details on all steps in this list except step 10, see the section on Upgrading SL1.

Prerequisites

- ScienceLogic recommends that for production systems, each Compute Cluster contains six (6) Compute Nodes. Lab systems can continue to use Compute Clusters that include only three (3) Compute Nodes.
- The Storage Cluster requires a (possibly additional) node to act as the Storage Manager.
- Perform the installation steps in the Installation manual to install these additional nodes (for the Computer Cluster and the Storage Cluster) before upgrading your existing nodes.
- Ensure that all nodes in the SL1 Extended Architecture can access the internet.

183 Workflow

• You must use the same password for the em7admin account during ISO installation of the Database Server and ISO installation of the appliances in the SL1 Extended Architecture.

NOTE: To perform the upgrade, you must have a ScienceLogic customer account that allows you access to the Harbor repository page on the ScienceLogic Support Site. To verify your access, go to https://registry.scilo.tools/harbor/. For more information about obtaining Harbor login credentials, contact your Customer Success Manager.

Resizing the Disks on the Compute Node

The Kafka Messaging service requires additional disk space on each Compute Node. Before upgrading, ensure that each disk on each existing Compute Node in the Compute Node cluster is at least 350 GB.

If each disk on each existing Compute Node is not at least 350 GB, perform the following steps on each Compute Node:

- 1. Resize the hard disk via your hypervisor to at least 350 GB.
- 2. Note the name of the disk that you expanded in your hypervisor.
- 3. Power on the virtual machine.
- 4. Either go to the console of the Compute Node or use SSH to access the Compute Node.
- 5. Open a shell session on the server.
- 6. Log in with the system password for the Compute Node.
- 7. At the shell prompt, enter:

```
sudo lsblk | grep <disk size>
```

where:

disk size is your hard disk size from step #1.

- 8. Note the name of the disk that you expanded in your hypervisor.
- 9. At the shell prompt, enter:

```
sudo fdisk /dev/<disk name>
```

where:

disk name is the name of the disk you want to expand.

- 10. Enter \mathbf{p} to print the partition table.
- 11. Enter **n** to add a new partition.
- 12. Enter \mathbf{p} to make the new partition the primary partition.
- 13. Select the default values for partition number, first sector, and last sector.
- 14. Enter w to save these changes
- 15. Restart the VM.

16. At the shell prompt, enter:

```
sudo fdisk -l
```

- 17. Notice that now another partition is present.
- 18. To initialize the new partition as a physical volume, enter the following at the shell prompt:

```
sudo pvcreate <partition name>
```

19. To add the physical volume to the existing volume group, enter the following at the shell prompt:

```
sudo vgextend em7vg <partition name>
```

20. To verify and confirm that the volume group has grown to the expected size, enter the following at the shell prompt:

```
sudo vgdisplay | grep "VG Size
```

Installing ORAS

If you have not already installed OCI Registry as Storage (ORAS), you will need to do so before you can upgrade the SL1 Extended Architecture.

To do so:

- 1. Use SSH to access the Management Node. Open a shell session on the server. Log in with the System Password you defined in the ISO menu.
- 2. In the Management Node, navigate to the sl1x-deploy directory. To do this, enter the following at the shell prompt:

```
cd sl1x-deploy
```

3. Run the following commands:

```
sudo su

curl -LO https://github.com/oras-
project/oras/releases/download/v0.12.0/oras_0.12.0_linux_amd64.tar.gz

mkdir -p oras-install/

tar -zxf oras_0.12.0_*.tar.gz -C oras-install/

mv oras-install/oras /usr/bin/

rm -rf oras_0.12.0_*.tar.gz oras-install/

exit
```

185 Installing ORAS

Obtaining Your Harbor Credentials

You will need to know your Harbor username and CLI secret when you upgrade the SL1 Extended Architecture. To obtain these credentials:

- 1. Log in to Harbor at: https://registry.scilo.tools/harbor/sign-in?redirect_url=%2Fharbor%2Fprojects
- 2. Click [Login via OIDC Provider].
- 3. Click [Customer Login].
- 4. Log in with the username and credentials that you use to access the ScienceLogic Support site (support.sciencelogic.com).
- 5. Click the username in the upper right and select **User Profile**.
- 6. On the **User Profile** page:
 - Note the username.
 - Click the pages icon next to the CLI secret field to copy the CLI secret to cache.
- 7. Exit the browser session.

Upgrading to 12.2.x

IMPORTANT: Before upgrading to SL1 12.2.0 or later, you *must* already be running SL1 on Oracle Linux 8 (OL8). If you are on a version of SL1 prior to 12.1.1 and running on OL7, you must first upgrade to SL1 12.1.1 and then migrate to OL8 before you can upgrade to SL1 12.2.x. For an overview of potential upgrade paths and their required steps, see the appropriate 12.2.x SL1 release notes.

Upgrading from 12.1.1 to 12.2.x

To upgrade the SL1 Extended Architecture to 12.2.x from 12.1.1, follow these steps:

- If you have not already done so, you must install ORAS and obtain your Harbor credentials, which you
 will need for step 9.
- 2. Use SSH to access the Management Node. Open a shell session on the server. Log in with the system password you defined in the ISO menu.
- 3. In the Management Node, navigate to the sl1x-deploy directory. To do this, enter the following at the shell prompt:

cd sl1x-deploy

4. Back up the following files:

```
/home/em7admin/sl1x-deploy/sl1x-inv.yml
```

/home/em7admin/sl1x-deploy/output-files/cluster.yml

/home/em7admin/sl1x-deploy/output-files/cluster.rkestate

/home/em7admin/sl1x-deploy/output-files/kube config cluster.yml

NOTE: ScienceLogic recommends that you back up these files at regular intervals.

5. Run the following command to enter the Ansible shell on the Docker container:

```
docker-compose -f docker-compose.external.yml run --rm deploy shell
```

6. Delete any failed charts:

```
helm ls | awk '/FAILED/'
```

7. If the above command results in any output, run the following command:

```
helm delete $(helm ls | awk '/FAILED/ { print $1 }')
```

8. Exit the Ansible shell session:

exit

9. Log in to Harbor repository:

```
oras login registry.scilo.tools/sciencelogic/
```

- 10. Enter the username you used to log in to the browser-based session of Harbor.
- 11. Enter the password (CLI Secret) that you saved from the browser-based session of Harbor.
- 12. Download the deployment files:

```
cd /home/em7admin/
```

```
oras pull registry.scilo.tools/sciencelogic/sl1x-deploy:12.2
```

cd sl1x-deploy

13. Copy the inventory template file to the file named sl1x-inv.yml:

```
cp sllx-inv-template.yml sllx-inv.yml
```

14. Edit the file sl1x-inv.yml to match your SL1 Extended system:

```
vi sl1x-inv.yml
```

CAUTION: Do not remove colons when editing this file.

- Make sure that the **sl1_version** value is the latest service version for 12.2 code line.
- Supply values in all the fields that are applicable. For details on the sllx-inv.yml, see the manual Installing SL1 Extended Architecture, which can be obtained by contacting ScienceLogic Support.
- Save your changes and exit the file (:wq).
- 15. Pull the Docker image that is referenced in the docker-compose file:

```
docker-compose -f docker-compose.external.yml pull
```

16. Update credentials on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy ssh-
keys --ask-pass
```

17. Run the following deploy command at the shell prompt to upgrade RKE and Kubernetes on the Compute Nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy cn
```

18. Update the SL1 Extended system services:

```
docker-compose -f docker-compose.external.yml run --rm deploy app --
skip-tags maxconnections
```

19. Update the Storage Manager:

```
docker-compose -f docker-compose.external.yml run --rm deploy sm
```

20. Update security packages on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy
package-updates
```

21. Update your classic SL1 appliances. For more information, see the section on *Updating SL1*.

Upgrading from 12.1.0 (OL8) to 12.2.x

To upgrade the SL1 Extended Architecture to 12.2.x from 12.1.0 instances running on Oracle Linux 8 (OL8), follow these steps:

- 1. Complete preupgrade steps.
- 2. Upgrade with Scylla or disable Scylla.
- 3. Upgrade the SL1 Distributed Architecture.

Step 1: Preupgrade

- 1. If you have not already done so, you must *install ORAS* and *obtain your Harbor credentials*, which you will need for step 4.
- 2. Use SSH to access the Management Node. Open a shell session on the server. Log in with the system password you defined in the ISO menu.
- 3. In the Management Node, navigate to the sl1x-deploy directory. To do this, enter the following at the shell prompt:

```
cd sl1x-deploy
```

4. Log in to Harbor repository:

```
oras login registry.scilo.tools/sciencelogic/
```

- Enter the username you used to log in to the browser-based session of Harbor.
- Enter the password (CLI Secret) that you saved from the browser-based session of Harbor.
- 5. Exit out of the sllx-deploy directory and download the deployment files:

```
cd /home/em7admin/
oras pull registry.scilo.tools/sciencelogic/sl1x-deploy:12.2
cd sl1x-deploy
```

6. Copy the inventory template file to the sllx-inv.yml file:

```
cp sllx-inv-template.yml sllx-inv.yml
```

7. Edit the sllx-inv.yml file to match your SL1 Extended system:

```
vi sllx-inv.yml
```

CAUTION: Do not remove colons when editing this file.

- Make sure that the *sl1_version* value is set to the latest service version for the 12.2.x code line.
- Supply values in all the fields that are applicable. For details on the slix-inv.yml file, see the manual *Installing SL1 Extended Architecture*, which can be obtained by contacting ScienceLogic Support.
- Save your changes and exit the file (: wq).

8. Pull the Docker image that is referenced in the docker-compose file:

```
docker-compose -f docker-compose.external.yml pull
```

Step 2: Upgrade with Scylla or Disable the Scylla Cluster

On-premises SL1 users have the following options with regards to the Scylla cluster:

- Option 1: Upgrade with Scylla. This option upgrades RKE and Kubernetes on the Compute Nodes and updates the system services while continuing to utilize Scylla.
- Option 2: Disable Scylla. This option is available for users who do not utilize SL1's machine learning-based anomaly detection feature.

Option 1: Upgrade with Scylla

- 1. Use SSH to access the Management Node. Open a shell session on the server. Log in with the System Password you defined in the ISO menu.
- 2. To upgrade RKE and Kubernetes on the Compute Nodes, run the following command:

```
docker-compose -f docker-compose.external.yml run --rm deploy cn
```

3. To update the SL1 Extended Architecture system services, run the following command:

```
docker-compose -f docker-compose.external.yml run --rm deploy app
```

Option 2: Disable Scylla

If you do not utilize SL1's machine learning-based anomaly detection service, you have the option to remove existing Scylla databases from your Storage Nodes. This serves to lower resource utilization and cost. After disabling Scylla from a Storage Node, you can then opt to delete that Storage Node.

- Use SSH to access the Management Node. Open a shell session on the server. Log in with the System Password you defined in the ISO menu.
- 2. Open a text editor for the sllx-inv.yml file:

```
vi /home/em7admin/sl1x-deploy/sl1x-inv.yml
```

3. Edit the file:

```
all:
vars:
install_aiml: false
enableNonScyllaPipeline: true
enableLegacyScyllaPipeline: false
```

4. In that same file, remove the Storage Node and Storage Manager IP addresses from the list. For example, you would remove the following lines:

```
hosts:

#10.2.253.90: # ip of storage node 1

#10.2.253.91: # ip of storage node 2

#10.2.253.92: # ip of storage node 3

vars:

# roles/sn-scylla

scylla_admin_username: em7admin # scylla admin username

scylla_admin_password: <password> # scylla admin password

sm:
hosts:

#10.2.253.82: # ip of sm
```

- 5. Save your changes and exit the file (:wq).
- 6. To upgrade RKE and Kubernetes on the Compute Nodes, run the following command:

```
docker-compose -f docker-compose.external.yml run --rm deploy cn
```

7. To remove services, run the following command:

```
docker-compose -f docker-compose.external.yml run --rm deploy app-
purge
```

8. To deploy the updated services with the non-Scylla configuration, run the following command:

```
docker-compose -f docker-compose.external.yml run --rm deploy app
```

Step 3: Upgrade the SL1 Distributed Architecture

Update your classic SL1 appliances. For more information, see the section on Updating SL1.

Upgrading to 12.1.1

Upgrading from 11.2.x, 11.3.x, or 12.1.0.x (OL7) to 12.1.1 (OL8)

To upgrade the SL1 Extended Architecture to 12.1.1 running on Oracle Linux 8 (OL8) from 11.2.x, 11.3.x, or 12.1.0.x instances running on Oracle Linux 7 (OL7), follow these steps:

- 1. Complete preupgrade steps.
- 2. Upgrade or disable the Scylla cluster.
- 3. Upgrade the SL1 Distributed Architecture.
- 4. Upgrade the Compute Node clusters.
- 5. Upgrade the Management Node.

Step 1: Preupgrade

- 1. If you have not already done so, you must *install ORAS* and *obtain your Harbor credentials*, which you will need for step 4.
- 2. Use SSH to access the Management Node. Open a shell session on the server. Log in with the System Password you defined in the ISO menu.
- 3. In the Management Node, navigate to the sl1x-deploy directory. To do this, enter the following at the shell prompt:

```
cd sl1x-deploy
```

4. Log in to Harbor repository:

```
oras login registry.scilo.tools/sciencelogic/
```

- Enter the username you used to log in to the browser-based session of Harbor.
- Enter the password (CLI Secret) that you saved from the browser-based session of Harbor.
- 5. Set the SL1 version to 12.1.1 in the sl1x-inv.yml file:

```
vi /home/em7admin/sl1x-deploy/sl1x-inv.yml
```

```
change sl1 version to 12.1.1
```

CAUTION: Do not remove colons when editing this file.

6. Set the docker-compose image to iac-sl1x:12.1.1:

```
vi /home/em7admin/sl1x-deploy/docker-compose.external.yml
image: registry.scilo.tools/sciencelogic/iac-sl1x:12.1.1
```

- 7. Save your changes and exit the file (:wq).
- 8. Pull the Docker image that is referenced in the docker-compose file:

```
docker-compose -f docker-compose.external.yml pull
```

Step 2: Upgrade or Disable the Scylla Cluster

On-premises SL1 users have two options for upgrading the Scylla cluster or the option to disable Scylla:

- Option 1: Rolling upgrade. This option is recommended for most deployments.
- Option 2: Backup and restore. This option requires AWS S3 access and is recommended for smaller deployments and lab environments.
- Option 3: Disable Scylla. This option is available for users who do not utilize SL1's machine learning-based anomaly detection feature.

Procedures for these options are described in this section.

Option 1: Rolling Upgrade

This option for upgrading Scylla is recommended for most SL1 deployments.

- Use SSH to access the Management Node. Open a shell session on the server. Log in with the System Password you defined in the ISO menu.
- 2. Remove the first Scylla node from the cluster:

```
docker-compose -f docker-compose.external.yml run --rm deploy sn-
remove --limit sn[0]
```

Re-ISO the first Scylla node with the SL1 12.1.1 OL8 ISO. These Scylla node IPs can be found in the sl1x-inv.yml file. The following is an example:

```
sn:
     hosts:
       10.2.253.90: # ip of storage node 1
       10.2.253.91: # ip of storage node 2
       10.2.253.92: # ip of storage node 3
     vars:
       # roles/sn-scylla
       scylla_admin_username: em7admin # scylla admin username
       scylla admin password: <password> # scylla admin password
   sm:
     hosts:
       10.2.253.82: # ip of sm
Re-add the first Scylla node to the cluster:
   docker-compose -f docker-compose.external.yml run --rm deploy ssh-
```

restore --limit sn[0]

```
keys --ask-pass --limit sn[0]
docker-compose -f docker-compose.external.yml run --rm deploy sn-
```

5. Confirm that the node was added successfully:

```
docker-compose -f docker-compose.external.yml run --rm deploy sn-
cluster-check --limit sn[0]
```

NOTE: If you receive a message informing you that the task has failed because the new node has not yet joined the cluster, wait at least 15 minutes for the node to join and then run the command again. Larger clusters might require additional time. Continue checking every 15 minutes until the command is successful.

6. Remove the second and third Scylla nodes from the cluster:

```
docker-compose -f docker-compose.external.yml run --rm deploy sn-
remove --limit sn[1]

docker-compose -f docker-compose.external.yml run --rm deploy sn-
remove --limit sn[2]
```

NOTE: For large amounts of data, remove the nodes one at a time.

- 7. Re-ISO the second and third Scylla nodes with the SL1 12.1.1 OL8 ISO.
- 8. Re-ISO the Storage Manager node with the SL1 12.1.1 OL8 ISO.
- 9. Re-add the second and third Scylla nodes to the cluster:

```
docker-compose -f docker-compose.external.yml run --rm deploy ssh-
keys --ask-pass --limit sn[1],sn[2]

docker-compose -f docker-compose.external.yml run --rm deploy sn-
restore --limit sn[1],sn[2]
```

10. Confirm that the nodes were added correctly:

```
docker-compose -f docker-compose.external.yml run --rm deploy sn-
cluster-check --limit sn[1]

docker-compose -f docker-compose.external.yml run --rm deploy sn-
cluster-check --limit sn[2]
```

11. Deploy the Storage Manager:

```
docker-compose -f docker-compose.external.yml run --rm deploy ssh-
keys --ask-pass --limit sm

docker-compose -f docker-compose.external.yml run --rm deploy sm
```

Option 2: Backup and Restore

This option requires AWS S3 access and is recommended for smaller deployments and lab environments.

Before beginning this procedure, you will need the following:

• A Scylla AWS S3 bucket

NOTE: You will need an IAM role to access the bucket. For more information on configuring this role, see Scylla's documentation.

- An active Scylla cluster
- The Terraform state (tfstate) of the previous deployment
- 1. Disable the Streamer service.
- 2. Scale down the service so SL1 agents can collect data and store it locally until the Storage Node/Storage Manager upgrade process completes. To do so, use SSH to access the Management Node and run the following command in an Ansible shell session:

```
kubectl scale --replicas=0 deployment.apps/streamer
```

3. Exit the Ansible shell session and edit the sllx-inv.yml file to include variables for the S3 bucket:

```
scylla_backup_bucket: scilo-scylla-backup
scylla_backup_bucket_region: scilo-scylla-backup
access_key: #######
secret key: ########
```

4. Back up Scylla data:

```
cd /home/ec2-user/
docker-compose -f docker-compose.external.yml run --rm deploy backup-
scylla-o18
```

5. During the execution, take note of the output of this task:

```
TASK [sciencelogic.sllx sn.sn-scylla : Output Host IDs]
*****
changed: [10.152.1.250]
TASK [sciencelogic.sllx sn.sn-scylla : debug]
********
ok: [10.152.1.250] => {
 "host ids.stdout lines": [
   "Datacenter: dc",
   "=======",
   "Status=Up/Down",
   "|/ State=Normal/Leaving/Joining/Moving",
   "-- Address Load Tokens Owns Host ID Rack",
   "UN 10.152.5.250 9.05 MB 256 ? a6a4758a-5eb4-4382-99fb-
   b30e8841e68c r2",
   "UN 10.152.3.250 9.09 MB 256 ? d73d1ebb-acdb-47ad-81dc-
   b675a1ac5234 r1",
   "UN 10.152.1.250 9.08 MB 256 ? 10de9ae4-4c39-42c2-9ee0-
   6864244a4240 r0",
   "",
   "Note: Non-system keyspaces don't have the same replication
   settings, effective ownership information is meaningless"
```

6. SSH into the first Storage Node and get a snapshot tag:

scylla-manager-agent download-files -L s3:scilo-scylla-backup --list-snapshots

sm 20230214123551UTC

7. Re-ISO the Storage Node/Storage Manager nodes with the SL1 12.1.1 OL8 ISO:

```
docker-compose -f docker-compose.external.yml run --rm deploy ssh-
keys --ask-pass --limit sn,sm
```

8. SSH into the Management Node and finish the Storage Node/Storage Manager deployment:

```
cd /home/ec2-user/
```

```
docker-compose -f docker-compose.external.yml run --rm deploy sn
```

docker-compose -f docker-compose.external.yml run --rm deploy sm

9. Edit the sllx-inv.yml file to add the following variables, based on steps 5 and 6:

```
all:
  vars:
    #scylla backup and restore config
   scylla backup bucket: scilo-scylla-backup
   scylla backup bucket region: us-east-1
   access key: ********
   secret key: ********
    # snapshot tag specifies the Scylla Manager snapshot tag you want
    to restore.
   snapshot tag: sm 20230214123551UTC
    # host id specifies a mapping from the clone cluster node IP to
    the source cluster host IDs.
    # cluster host IDs.
   host id:
     10.152.1.250: 10de9ae4-4c39-42c2-9ee0-6864244a4240
      10.152.3.250: d73d1ebb-acdb-47ad-81dc-b675a1ac5234
```

10. Run the restore playbook:

```
docker-compose -f docker-compose.external.yml run --rm deploy
restore-scylla-ol8
```

10.152.5.250: a6a4758a-5eb4-4382-99fb-b30e8841e68c

- 11. Re-enable the Streamer service.
- 12. After upgrading the Storage Node/Storage Manager, you can increase the scale for the Streamer service:

```
kubectl scale --replicas=3 deployment.apps/streamer
```

Option 3: Disable Scylla

If you do not utilize SL1's machine learning-based anomaly detection service, you have the option to remove existing Scylla databases from your Storage Nodes. This serves to lower resource utilization and cost. After

disabling Scylla from a Storage Node, you can then opt to delete that Storage Node.

- 1. Use SSH to access the Management Node. Open a shell session on the server. Log in with the System Password you defined in the ISO menu.
- 2. Open a text editor for the sllx-inv.yml file:

```
vi /home/em7admin/sl1x-deploy/sl1x-inv.yml
```

3. Edit the file:

```
all:
    vars:
    install_aiml: false
    enableNonScyllaPipeline: true
    enableLegacyScyllaPipeline: false
```

4. In that same file, remove the Storage Node and Storage Manager IP addresses from the list. For example, you would remove the following lines:

```
hosts:

#10.2.253.90: # ip of storage node 1

#10.2.253.91: # ip of storage node 2

#10.2.253.92: # ip of storage node 3

vars:

# roles/sn-scylla

scylla_admin_username: em7admin # scylla admin username

scylla_admin_password: <password> # scylla admin password

sm:
hosts:
```

```
#10.2.253.82: # ip of sm
```

5. Save your changes and exit the file (:wq).

Step 3. Upgrade the SL1 Distributed Architecture

Update your classic SL1 appliances. For more information, see the section on Updating SL1.

Step 4. Upgrade the Compute Node Cluster

The process for upgrading your Compute Node (CN) cluster varies slightly based on whether you have a six-node cluster or a three-node cluster. Both options are described in this section.

Option 1: Six-node Clusters

- 1. Use SSH to access the Management Node. Open a shell session on the server. Log in with the System Password you defined in the ISO menu.
- 2. Run the backup procedure:

```
docker-compose -f docker-compose.external.yml run --rm deploy rke-backup --tags 6+nodes
```

3. Re-ISO the CN worker nodes to the SL1 12.1.1 OL8 ISO.

TIP: You can find the IP addresses for the worker nodes in the sllx-inv.yml file.

4. Set up SSH keys to the worker nodes and restore their data:

```
rm -rf /home/em7admin/.ssh/known_hosts

docker-compose -f docker-compose.external.yml run --rm deploy ssh-
keys --ask-pass --limit worker

docker-compose -f docker-compose.external.yml run --rm deploy rke-
restore --tags 6+nodes
```

5. Re-ISO the CN master nodes to the SL1 12.1.1 OL8 ISO.

TIP: You can find the IP addresses for the master nodes in the slix-inv.yml file.

6. If configured, re-ISO the load balancers to the SL1 12.1.1 OL8 ISO.

7. Set up SSH keys to the master nodes and redeploy the cluster:

```
docker-compose -f docker-compose.external.yml run --rm deploy ssh-
keys --ask-pass --limit master,lb
docker-compose -f docker-compose.external.yml run --rm deploy cn
docker-compose -f docker-compose.external.yml run --rm deploy app
```

8. Check for publisher/subscriptions .yml inside the input files. These are used if you have Publisher services enabled. Once .yml files are deployed, Publisher pods should be deployed as well.

```
ls /home/em7admin/sl1x-deploy/input-files/subscriptions

Apply datamodel first then subscriptions
```

Option 2: Three-node Clusters

- 1. Use SSH to access the Management Node. Open a shell session on the server. Log in with the System Password you defined in the ISO menu.
- 2. Run the backup procedure:

```
docker-compose -f docker-compose.external.yml run --rm deploy rke-backup --tags 3nodes
```

- 3. Re-ISO the first two master nodes listed in the sllx-inv.yml file to the SL1 12.1.1 OL8 ISO.
- 4. Set up SSH keys to the two master nodes and restore their data:

```
echo > ~/.ssh/known_hosts

docker-compose -f docker-compose.external.yml run --rm deploy ssh-
keys --ask-pass --limit master[0], master[1]

docker-compose -f docker-compose.external.yml run --rm deploy rke-
restore --tags 3nodes
```

- 5. Re-ISO the last master node listed in the sllx-inv.yml file to the SL1 12.1.1 OL8 ISO.
- 6. If configured, re-ISO the load balancers to the SL1 12.1.1 OL8 ISO.

7. Set up SSH keys to the last master node and redeploy the cluster:

```
echo > ~/.ssh/known_hosts

docker-compose -f docker-compose.external.yml run --rm deploy ssh-
keys --ask-pass --limit master[2],lb

docker-compose -f docker-compose.external.yml run --rm deploy cn

docker-compose -f docker-compose.external.yml run --rm deploy app --
skip-tags maxconnections
```

8. Ensure pods are running:

```
docker-compose -f docker-compose.external.yml run --rm deploy shell kubectl get pods
```

9. Check for publisher/subscriptions .yml inside the input files. These are used if you have Publisher services enabled. Once .yml files are deployed, Publisher pods should be deployed as well.

```
ls /home/em7admin/sl1x-deploy/input-files/subscriptions

Apply datamodel first then subscriptions
```

Step 5. Upgrade the Management Node

CAUTION: Do not upgrade the Management Node until your SL1 Database Server, Administration Portal, Storage Node, Storage Manager, Compute Node, and load balancers are upgraded to 12.1.1 OL8.

- 1. Use SSH to access the Management Node. Open a shell session on the server. Log in with the System Password you defined in the ISO menu.
- 2. Run the backup procedure:

```
cd /home/em7admin/
cp .bash_history sl1x-deploy/input-files/
tar cvf sl1x-deploy.tgz sl1x-deploy
```

3. Copy the compressed file to a secure machine. For example:

```
scp em7admin@<MN IP>:sllx-deploy.tgz sllx-deploy.tgz
```

4. Re-ISO the Management Node to the SL1 12.1.1 OL8 ISO.

5. Log in to Harbor repository:

```
oras login registry.scilo.tools/sciencelogic/
```

- Enter the username you used to log in to the browser-based session of Harbor.
- Enter the password (CLI Secret) that you saved from the browser-based session of Harbor.
- 6. Pull and run the mn-transformation.sh script, then exit the SSH session to apply the script changes:

```
oras pull registry.scilo.tools/sciencelogic/mn-transformation:MN-Trans-OL8
```

```
mv mn-transformation.sh /tmp/
```

```
sudo sh /tmp/mn-transformation.sh
```

exit

7. Copy the compressed file back to the Management Node. For example:

```
scp sl1x-deploy.tgz em7admin@<MN IP>:/home/em7admin/sl1x-deploy.tgz
```

8. SSH back into your Management Node and restore the sl1x-deploy folder and the bash history file:

```
cd /home/em7admin/
```

```
tar xf sl1x-deploy.tgz -C ./
```

```
cp /home/em7admin/sl1x-deploy/input-files/.bash_history
/home/em7admin/
```

9. Your management node is now configured and can manage the cluster. To test, run the following command to see the kubectl pod output:

```
docker-compose -f docker-compose.external.yml run --rm deploy shell
```

```
INFO:__main__:Running with Parameters: Namespace(ansible_args=[],
command='shell', force root=False)
```

```
ansible@74c0d0905aa7:/ansible$ kubectl get pods
```

Upgrading to 12.1.0.x

Upgrading from 11.2.x or 11.3.x to 12.1.0.x:

To upgrade the SL1 Extended Architecture to 12.1.0.x from 11.2.x or 11.3.x:

- 1. If you have not already done so, you must *install ORAS* and *obtain your Harbor credentials*, which you will need for step 4.
- 2. Use SSH to access the Management Node. Open a shell session on the server. Log in with the System Password you defined in the ISO menu.
- 3. In the Management Node, navigate to the sl1x-deploy directory. To do this, enter the following at the shell prompt:

```
cd sl1x-deploy
```

4. Log in to Harbor repository:

```
oras login registry.scilo.tools/sciencelogic/
```

- Enter the username you used to log in to the browser-based session of Harbor.
- Enter the password (CLI Secret) that you saved from the browser-based session of Harbor.
- 5. Download the deployment files:

```
cd /home/em7admin/
oras pull registry.scilo.tools/sciencelogic/sl1x-deploy:12.1
cd sl1x-deploy
```

6. Copy the inventory template file to the file named sl1x-inv.yml:

```
cp sl1x-inv-template.yml sl1x-inv.yml
```

7. Edit the file sl1x-inv.yml to match your SL1 Extended system:

```
vi sl1x-inv.yml
```

CAUTION: Do not remove colons when editing this file.

- Make sure that the sl1 version value is set to the latest service version for the 12.1.0 code line.
- Supply values in all the fields that are applicable. For details on the sllx-inv.yml, see the manual *Installing SL1 Extended Architecture*, which can be obtained by contacting ScienceLogic Support.
- Save your changes and exit the file (:wq).
- 8. Pull the Docker image that is referenced in the docker-compose file:

```
docker-compose -f docker-compose.external.yml pull
```

9. Complete the upgrade by running the full deployment:

```
docker-compose -f docker-compose.external.yml run --rm deploy sl1x --
skip-tags maxconnections
```

NOTE: Alternatively, you can deploy each platform node individually by running the following commands in series:

```
docker-compose -f docker-compose.external.yml run --rm deploy sn

docker-compose -f docker-compose.external.yml run --rm deploy cn

docker-compose -f docker-compose.external.yml run --rm deploy app --
skip-tags maxconnections

docker-compose -f docker-compose.external.yml run --rm deploy sm
```

10. Update security packages on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy package-
updates
```

11. Update your classic SL1 appliances. For more information, see the section on *Updating SL1*.

Upgrading from 11.1.x to 12.1.0.x

To upgrade the SL1 Extended Architecture from 11.1.x to 12.1.0.x:

- 1. If you have not already done so, you must *install ORAS* and *obtain your Harbor credentials*, which you will need for step 4.
- 2. Use SSH to access the Management Node. Open a shell session on the server. Log in with the System Password you defined in the ISO menu.
- 3. In the Management Node, navigate to the sl1x-deploy directory. To do this, enter the following at the shell prompt:

```
cd sl1x-deploy
```

4. Log in to Harbor repository:

```
oras login registry.scilo.tools/sciencelogic/
```

- Enter the username you used to log in to the browser-based session of Harbor.
- Enter the password (CLI Secret) that you saved from the browser-based session of Harbor.
- 5. Download the deployment files:

```
cd /home/em7admin/
```

```
oras pull registry.scilo.tools/sciencelogic/sl1x-deploy:12.1
cd sl1x-deploy
```

6. Pull the Docker image that is referenced in the docker-compose file

```
docker-compose -f docker-compose.external.yml pull
```

7. Update credentials on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy ssh-keys
--ask-pass
```

8. Download the deployment files:

```
cd /home/em7admin/
oras pull registry.scilo.tools/sciencelogic/sl1x-deploy:12.1
cd sl1x-deploy
```

9. Copy the inventory template file to the file named sl1x-inv.yml:

```
cp sl1x-inv-template.yml sl1x-inv.yml
```

10. Edit the file sl1x-inv.yml to match your SL1 Extended system:

```
vi sl1x-inv.yml
```

CAUTION: Do not remove colons when editing this file.

- Make sure that the sl1 version value is set to the latest service version for 12.1.0.x code line.
- Add the variable deployment: onprem.
- Supply values in all the fields that are applicable. For details on the sl1x-inv.yml, see the manual *Installing SL1 Extended Architecture*, which can be obtained by contacting ScienceLogic Support.
- Save your changes and exit the file (:wq).
- 11. Pull the Docker image that is referenced in the docker-compose file

```
docker-compose -f docker-compose.external.yml pull
```

12. Complete the upgrade by running the full deployment:

```
docker-compose -f docker-compose.external.yml run --rm deploy sl1x --
skip-tags maxconnections
```

NOTE: Alternatively, you can deploy each platform node individually by running the following commands in series:

```
docker-compose -f docker-compose.external.yml run --rm deploy sn

docker-compose -f docker-compose.external.yml run --rm deploy cn

docker-compose -f docker-compose.external.yml run --rm deploy app --
skip-tags maxconnections

docker-compose -f docker-compose.external.yml run --rm deploy sm
```

13. Update security packages on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy package-
updates
```

14. Update your classic SL1 appliances. For more information, see the section on *Updating SL1*.

Upgrading to 11.3.x

Upgrading from 11.3.x to the Latest Version of 11.3.x

To upgrade the SL1 Extended Architecture from 11.3.0 to 11.3.1:

- 1. Use SSH to access the Management Node. Open a shell session on the server. Log in with the System Password you defined in the ISO menu.
- 2. In the Management Node, navigate to the sl1x-deploy directory. To do this, enter the following at the shell prompt:

```
cd sl1x-deploy
```

- 3. Back up the following files:
 - /home/em7admin/sl1x-deploy/sl1x-inv.yml
 - /home/em7admin/sl1x-deploy/output-files/cluster.yml
 - /home/em7admin/sl1x-deploy/output-files/cluster.rkestate
 - /home/em7admin/sl1x-deploy/output-files/kube config cluster.yml

NOTE: ScienceLogic recommends that you back up these files at regular intervals.

4. Run the following command to enter the Ansible shell on the Docker container:

```
docker-compose -f docker-compose.external.yml run --rm deploy shell
```

5. Delete any failed charts:

```
helm ls | awk '/FAILED/'
```

6. If the above command results in any output, run the following command:

```
helm delete $(helm ls | awk '/FAILED/ { print $1 }')
```

7. Exit the Ansible shell session:

exit

- 8. If you have not already done so, you must *install ORAS* and *obtain your Harbor credentials*, which you will need for step 10.
- 9. If needed, use SSH to access the Management Node again. Open a shell session on the server. Log in with the system password you defined in the ISO menu.
- 10. Log in to Harbor repository:

```
oras login registry.scilo.tools/sciencelogic/
```

- Enter the username you used to log in to the browser-based session of Harbor.
- Enter the password (CLI Secret) that you saved from the browser-based session of Harbor.
- 11. Download the deployment files:

```
cd /home/em7admin/
oras pull registry.scilo.tools/sciencelogic/sl1x-deploy:11.3
cd sl1x-deploy
```

12. Copy the inventory template file to the file named sl1x-inv.yml:

```
cp sl1x-inv-template.yml sl1x-inv.yml
```

13. Edit the file sl1x-inv.yml to match your SL1 Extended system:

```
vi sllx-inv.yml
```

CAUTION: Do not remove colons when editing this file.

- Make sure that the sl1 version value is the latest service version for 11.3 code line.
- Supply values in all the fields that are applicable. For details on the sllx-inv.yml, see the manual
 Installing SL1 Extended Architecture, which can be obtained by contacting ScienceLogic Support.
- Save your changes and exit the file (:wq).
- 14. Pull the Docker image that is referenced in the docker-compose file

```
docker-compose -f docker-compose.external.yml pull
```

15. Update credentials on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy ssh-keys
--ask-pass
```

16. Run the following deploy command at the shell prompt to upgrade RKE and Kubernetes on the Compute Nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy cn
```

17. Update the SL1 Extended system services:

```
docker-compose -f docker-compose.external.yml run --rm deploy app --
skip-tags maxconnections
```

18. Update security packages on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy package-
updates
```

Upgrading from 11.2.x to 11.3.x

To upgrade the SL1 Extended Architecture from the 11.2.x line to 11.3.x:

- 1. Use SSH to access the Management Node. Open a shell session on the server. Log in with the System Password you defined in the ISO menu.
- 2. In the Management Node, navigate to the sl1x-deploy directory. To do this, enter the following at the shell prompt:

```
cd sl1x-deploy
```

- 3. Back up the following files:
 - /home/em7admin/sl1x-deploy/sl1x-inv.yml
 - /home/em7admin/sl1x-deploy/output-files/cluster.yml
 - /home/em7admin/sl1x-deploy/output-files/cluster.rkestate
 - /home/em7admin/sl1x-deploy/output-files/kube config cluster.yml

NOTE: ScienceLogic recommends that you back up these files at regular intervals.

4. Run the following command to enter the Ansible shell on the Docker container:

```
docker-compose -f docker-compose.external.yml run --rm deploy shell
```

5. Delete any failed charts:

```
helm ls | awk '/FAILED/'
```

6. If the above command results in any output, run the following command:

```
helm delete $(helm ls | awk '/FAILED/ { print $1 }')
```

7. Exit the Ansible shell session:

exit

- 8. If you have not already done so, you must *install ORAS* and *obtain your Harbor credentials*, which you will need for step 10.
- 9. If needed, use SSH to access the Management Node again. Open a shell session on the server. Log in with the system password you defined in the ISO menu.
- 10. Log in to Harbor repository:

```
oras login registry.scilo.tools/sciencelogic/
```

- Enter the username you used to log in to the browser-based session of Harbor.
- Enter the password (CLI Secret) that you saved from the browser-based session of Harbor.
- 11. Download the deployment files:

```
cd /home/em7admin/
oras pull registry.scilo.tools/sciencelogic/sl1x-deploy:11.3
cd sl1x-deploy
```

12. Copy the inventory template file to the file named sl1x-inv.yml:

```
cp sl1x-inv-template.yml sl1x-inv.yml
```

13. Edit the file sl1x-inv.yml to match your SL1 Extended system:

```
vi sl1x-inv.yml
```

CAUTION: Do not remove colons when editing this file.

- Make sure that the **sl1** version value is set to the latest version in the 11.3 code line.
- Supply values in all the fields that are applicable. For details on the sllx-inv.yml, see the manual *Installing SL1 Extended Architecture*, which can be obtained by contacting ScienceLogic Support.
- Save your changes and exit the file (: wq).
- 14. Pull the Docker image that is referenced in the docker-compose file

```
docker-compose -f docker-compose.external.yml pull
```

15. Update credentials on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy ssh-keys
--ask-pass
```

16. Run the following deploy commands at the shell prompt to upgrade RKE and Kubernetes on the Compute Nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy rke-preupgrade
```

docker-compose -f docker-compose.external.yml run --rm deploy apppurge

docker-compose -f docker-compose.external.yml run --rm deploy rkeupgrade

docker-compose -f docker-compose.external.yml run --rm deploy rkepostupgrade --skip-tags ten

NOTE: You can run the deploy rke-upgrade and deploy rke-postupgrade commands only once.

17. Re-enter the Ansible shell on the Docker container:

```
docker-compose -f docker-compose.external.yml run --rm deploy shell
```

18. Run the following command:

```
kubectl get nodes
```

- 19. Verify that all node versions listed are upgraded to RKE2 and Kubernetes v1.22. For example, you might see v1.22.9+rke2r2 listed as the version.
- 20. Exit out of the Ansible shell session:

exit

21. Update the SL1 Extended system services:

```
docker-compose -f docker-compose.external.yml run --rm deploy app --
skip-tags maxconnections
```

22. Update security packages on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy package-
updates
```

23. Re-enter the Ansible shell and run the following command:

```
kubectl --kubeconfig=/ansible/output-files/kube_config_cluster.yml
delete deployment rke2-ingress-nginx-defaultbackend -n kube-system
```

NOTE: This command ensures that all old resources are deleted. The output can be resource delete/Error from server (NotFound).

Upgrading from 11.1.x to 11.3.x

To upgrade the SL1 Extended Architecture from the 11.1.x line to 11.3.x:

- 1. Use SSH to access the Management Node. Open a shell session on the server. Log in with the system password you defined in the ISO menu.
- 2. In the Management Node, navigate to the sl1x-deploy directory. To do this, enter the following at the shell prompt:

cd sl1x-deploy

- 3. Back up the following files:
 - /home/em7admin/sl1x-deploy/sl1x-inv.yml
 - /home/em7admin/sl1x-deploy/output-files/cluster.yml
 - /home/em7admin/sl1x-deploy/output-files/cluster.rkestate
 - /home/em7admin/sl1x-deploy/output-files/kube config cluster.yml

NOTE: ScienceLogic recommends that you back up these files at regular intervals.

4. Run the following command to enter the Ansible shell on the Docker container:

```
docker-compose -f docker-compose.external.yml run --rm deploy shell
```

5. Delete any failed charts:

```
helm ls | awk '/FAILED/'
```

6. If the above command results in any output, run the following command:

```
helm delete $(helm ls | awk '/FAILED/ { print $1 }')
```

7. Exit the Ansible shell session:

exit

- 8. If you have not already done so, you must *install ORAS* and *obtain your Harbor credentials*, which you will need for step 10.
- 9. If needed, use SSH to access the Management Node again. Open a shell session on the server. Log in with the system password you defined in the ISO menu.
- 10. Log in to Harbor repository:

```
oras login registry.scilo.tools/sciencelogic/
```

- Enter the username you used to log in to the browser-based session of Harbor.
- Enter the password (CLI Secret) that you saved from the browser-based session of Harbor.
- 11. Download the deployment files:

```
cd /home/em7admin/
oras pull registry.scilo.tools/sciencelogic/sl1x-deploy:11.3
cd sl1x-deploy
```

12. Copy the inventory template file to the file named sl1x-inv.yml:

```
cp sl1x-inv-template.yml sl1x-inv.yml
```

13. Edit the file sl1x-inv.yml to match your SL1 Extended system:

```
vi sl1x-inv.yml
```

CAUTION: Do not remove colons when editing this file.

- Make sure that the *sl1 version* value is set to the latest version in the 11.3 code line.
- Make sure that the **deployment** value is: deployment: on-prem.
- Supply values in all the fields that are applicable. For details on the sl1x-inv.yml, see the manual *Installing SL1 Extended Architecture*, which can be obtained by contacting ScienceLogic Support.
- Save your changes and exit the file (:wq).
- 14. Pull the Docker image that is referenced in the docker-compose file

```
docker-compose -f docker-compose.external.yml pull
```

15. Update credentials on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy ssh-keys
--ask-pass
```

16. Run the following deploy commands at the shell prompt to upgrade RKE and Kubernetes on the Compute Nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy rke-
preupgrade
```

```
docker-compose -f docker-compose.external.yml run --rm deploy app-
purge
```

docker-compose -f docker-compose.external.yml run --rm deploy rkeupgrade

```
docker-compose -f docker-compose.external.yml run --rm deploy rke-
postupgrade --skip-tags ten
```

NOTE: You can run the deploy rke-upgrade and deploy rke-postupgrade commands only once.

17. Re-enter the Ansible shell on the Docker container:

```
docker-compose -f docker-compose.external.yml run --rm deploy shell
```

18. Run the following command:

```
kubectl get nodes
```

- 19. Verify that all node versions listed are upgraded to RKE2 and Kubernetes v1.22. For example, you might see v1.22.9+rke2r2 listed as the version.
- 20. Exit out of the Ansible shell session:

exit

21. At the shell prompt, run the following deploy commands to update the SL1 Extended system services:

```
docker-compose -f docker-compose.external.yml run --rm deploy sn

docker-compose -f docker-compose.external.yml run --rm deploy sm

docker-compose -f docker-compose.external.yml run --rm deploy app --
skip-tags maxconnections
```

22. Update security packages on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy package-
updates
```

23. Re-enter the Ansible shell and run the following command:

```
kubectl --kubeconfig=/ansible/output-files/kube_config_cluster.yml
delete deployment rke2-ingress-nginx-defaultbackend -n kube-system
```

NOTE: This command ensures that all old resources are deleted. The output can be resource delete/Error from server (NotFound).

Upgrading from 10.2.x to 11.3.x

To upgrade the SL1 Extended Architecture from the 10.2.x line to 11.3.x:

- 1. Use SSH to access the Management Node. Open a shell session on the server. Log in with the System Password you defined in the ISO menu.
- 2. In the Management Node, navigate to the sl1x-deploy directory. To do this, enter the following at the shell prompt:

```
cd sl1x-deploy
```

- 3. Back up the following files:
 - /home/em7admin/sl1x-deploy/sl1x-inv.yml
 - /home/em7admin/sl1x-deploy/output-files/cluster.yml
 - /home/em7admin/sl1x-deploy/output-files/cluster.rkestate
 - /home/em7admin/sl1x-deploy/output-files/kube config cluster.yml

NOTE: ScienceLogic recommends that you back up these files at regular intervals.

4. Run the following command to enter the Ansible shell on the Docker container:

```
docker-compose -f docker-compose.external.yml run --rm deploy shell
```

5. Delete any failed charts:

```
helm ls | awk '/FAILED/'
```

6. If the above command results in any output, run the following command:

```
helm delete $(helm ls | awk '/FAILED/ { print $1 }')
```

7. Exit the Ansible shell session:

exit

- 8. If you have not already done so, you must *install ORAS* and *obtain your Harbor credentials*, which you will need for step 10.
- 9. If needed, use SSH to access the Management Node again. Open a shell session on the server. Log in with the system password you defined in the ISO menu.
- 10. Log in to Harbor repository:

```
oras login registry.scilo.tools/sciencelogic/
```

- Enter the username you used to log in to the browser-based session of Harbor.
- Enter the password (CLI Secret) that you saved from the browser-based session of Harbor.
- 11. Download the deployment files:

```
cd /home/em7admin/
oras pull registry.scilo.tools/sciencelogic/sl1x-deploy:11.3
cd sl1x-deploy
```

12. Copy the inventory template file to the file named sl1x-inv.yml:

```
cp sl1x-inv-template.yml sl1x-inv.yml
```

13. Edit the file sl1x-inv.yml to match your SL1 Extended system:

```
vi sl1x-inv.yml
```

CAUTION: Do not remove colons when editing this file.

- Make sure that the *sl1 version* value is set to the latest version in the 11.3 code line.
- Make sure that the **deployment** value is: deployment: on-prem.
- Supply values in all the fields that are applicable. For details on the sl1x-inv.yml, see the manual *Installing SL1 Extended Architecture*, which can be obtained by contacting ScienceLogic Support.
- Save your changes and exit the file (:wq).
- 14. Pull the Docker image that is referenced in the docker-compose file

```
docker-compose -f docker-compose.external.yml pull
```

15. Update credentials on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy ssh-keys
--ask-pass
```

When prompted, enter the System Password that you entered on the ISO menu.

16. Run the cn-helm-upgrade service:

```
docker-compose -f docker-compose.external.yml run --rm deploy cn-helm-upgrade
```

17. Run the following deploy commands at the shell prompt to upgrade RKE and Kubernetes on the Compute Nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy rke-
preupgrade
```

```
docker-compose -f docker-compose.external.yml run --rm deploy app-
purge
```

```
docker-compose -f docker-compose.external.yml run --rm deploy rke-
upgrade
```

```
docker-compose -f docker-compose.external.yml run --rm deploy rke-postupgrade --skip-tags eleven
```

NOTE: You can run the deploy rke-upgrade and deploy rke-postupgrade commands only once.

18. Re-enter the Ansible shell on the Docker container:

```
docker-compose -f docker-compose.external.yml run --rm deploy shell
```

19. Run the following command:

```
kubectl get nodes
```

- 20. Verify that all node versions listed are upgraded to RKE2 and Kubernetes v1.22. For example, you might see v1.22.9+rke2r2 listed as the version.
- 21. Exit out of the Ansible shell session:

exit

22. At the shell prompt, run the following deploy commands to update the SL1 Extended system services:

```
docker-compose -f docker-compose.external.yml run --rm deploy sn

docker-compose -f docker-compose.external.yml run --rm deploy sm

docker-compose -f docker-compose.external.yml run --rm deploy app --
skip-tags maxconnections
```

23. Update security packages on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy package-
updates
```

24. Re-enter the Ansible shell and run the following commands:

```
kubectl --kubeconfig=/ansible/output-files/kube_config_cluster.yml
delete deployment rke2-ingress-nginx-defaultbackend -n kube-system
kubectl patch job migration-agent-addons-remove --type=strategic --
patch '{"spec":{"suspend":true}}' -n kube-system
```

NOTE: These commands ensure that all old resources are deleted. The output can be resource delete/Error from server (NotFound).

Upgrading to 11.2.x

Upgrading from 11.2.x to the Latest Version of 11.2.x

To upgrade the SL1 Extended Architecture from the 11.2.x line to a later release in the 11.2.x line:

- 1. Use SSH to access the Management Node. Open a shell session on the server. Log in with the System Password you defined in the ISO menu.
- 2. In the Management Node, navigate to the sl1x-deploy directory. To do this, enter the following at the shell prompt:

```
cd sl1x-deploy
```

- 3. Back up the following files:
 - /home/em7admin/sl1x-deploy/sl1x-inv.yml
 - /home/em7admin/sl1x-deploy/output-files/cluster.yml
 - /home/em7admin/sl1x-deploy/output-files/cluster.rkestate
 - /home/em7admin/sl1x-deploy/output-files/kube config cluster.yml

NOTE: : ScienceLogic recommends that you back up these files at regular intervals.

4. Run the following command to enter the Ansible shell on the Docker container:

```
docker-compose -f docker-compose.external.yml run --rm deploy shell
```

5. Delete any failed charts:

```
helm ls | awk '/FAILED/'
```

6. If the above command results in any output, run the following command:

```
helm delete $(helm ls | awk '/FAILED/ { print $1 }')
```

7 Exit the Ansible shell session:

exit

- 8. If you have not already done so, you must *install ORAS* and *obtain your Harbor credentials*, which you will need for step 10.
- 9. If needed, use SSH to access the Management Node again. Open a shell session on the server. Log in with the system password you defined in the ISO menu.
- 10. Log in to Harbor repository:

```
oras login registry.scilo.tools/sciencelogic/
```

- Enter the username you used to log in to the browser-based session of Harbor.
- Enter the password (CLI Secret) that you saved from the browser-based session of Harbor.
- 11. Download the deployment files:

```
cd /home/em7admin/
oras pull registry.scilo.tools/sciencelogic/sl1x-deploy:11.2
cd sl1x-deploy
```

12. Copy the inventory template file to the file named sl1x-inv.yml:

```
cp sl1x-inv-template.yml sl1x-inv.yml
```

13. Edit the file sl1x-inv.yml to match your SL1 Extended system:

```
vi sl1x-inv.yml
```

CAUTION: Do not remove colons when editing this file.

- Make sure that the sl1 version value is set to the latest version in the 11.2 code line.
- Supply values in all the fields that are applicable. For details on the sl1x-inv.yml, see the manual **Installing SL1 Extended Architecture**, which can be obtained by contacting ScienceLogic Support.
- Save your changes and exit the file (:wq).
- 14. Pull the docker image that is referenced in the docker-compose file:

```
docker-compose -f docker-compose.external.yml pull
```

15. Update credentials on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy ssh-
keys --ask-pass
```

When prompted, enter the System Password that you entered in the ISO menu.

16. Run the deploy commands at the shell prompt:

```
docker-compose -f docker-compose.external.yml run --rm deploy cn
docker-compose -f docker-compose.external.yml run --rm deploy app
```

17. Update security packages on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy
package-updates
```

Upgrading from 11.1.x to 11.2.x

To upgrade the SL1 Extended Architecture from the 11.1.x line to the 11.2.x line:

- 1. Use SSH to access the Management Node. Open a shell session on the server. Log in with the System Password you defined in the ISO menu.
- 2. In the Management Node, navigate to the sl1x-deploy directory. To do this, enter the following at the shell prompt:

```
cd sl1x-deploy
```

- 3. Back up the following files:
 - /home/em7admin/sl1x-deploy/sl1x-inv.yml
 - /home/em7admin/sl1x-deploy/output-files/cluster.yml

- /home/em7admin/sl1x-deploy/output-files/cluster.rkestate
- /home/em7admin/sl1x-deploy/output-files/kube config cluster.yml

NOTE: : ScienceLogic recommends that you back up these files at regular intervals.

4. Run the following command to enter the Ansible shell on the Docker container:

```
docker-compose -f docker-compose.external.yml run --rm deploy shell
```

5. Delete any failed charts:

```
helm ls | awk '/FAILED/'
```

6. If the above command results in any output, run the following command:

```
helm delete $(helm ls | awk '/FAILED/ { print $1 }')
```

7. Exit the Ansible shell session:

exit

- 8. If you have not already done so, you must *install ORAS* and *obtain your Harbor credentials*, which you will need for step 10.
- 9. If needed, use SSH to access the Management Node again. Open a shell session on the server. Log in with the system password you defined in the ISO menu.
- 10. Log in to Harbor repository:

```
oras login registry.scilo.tools/sciencelogic/
```

- Enter the username you used to log in to the browser-based session of Harbor.
- Enter the password (CLI Secret) that you saved from the browser-based session of Harbor.
- 11. Download the deployment files:

```
cd /home/em7admin/
oras pull registry.scilo.tools/sciencelogic/sl1x-deploy:11.2
cd sl1x-deploy
```

12. Copy the inventory template file to the file named sl1x-inv.yml:

```
cp sl1x-inv-template.yml sl1x-inv.yml
```

13. Edit the file sl1x-inv.yml to match your SL1 Extended system:

```
vi sl1x-inv.yml
```

CAUTION: Do not remove colons when editing this file.

- Make sure that the sl1 version value is set to the latest version in the 11.2 code line.
- Supply values in all the fields that are applicable. For details on the sl1x-inv.yml, see the manual **Installing SL1 Extended Architecture**, which can be obtained by contacting ScienceLogic Support.
- Save your changes and exit the file (:wq).
- 14. Pull the docker image that is referenced in the docker-compose file:

```
docker-compose -f docker-compose.external.yml pull
```

15. Update credentials on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy ssh-
keys --ask-pass
```

When prompted, enter the System Password that you entered in the ISO menu.

16. Run the deploy commands at the shell prompt:

```
docker-compose -f docker-compose.external.yml run --rm deploy sl1x
```

17. Update security packages on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy
package-updates
```

Upgrading from 10.2.x to 11.2.x

To upgrade the SL1 Extended Architecture from the 10.2.x line to the 11.2.x line:

- 1. Use SSH to access the Management Node. Open a shell session on the server. Log in with the System Password you defined in the ISO menu.
- 2. In the Management Node, navigate to the sl1x-deploy directory. To do this, enter the following at the shell prompt:

```
cd sl1x-deploy
```

- 3. Back up the following files:
 - /home/em7admin/sl1x-deploy/sl1x-inv.yml
 - /home/em7admin/sl1x-deploy/output-files/cluster.yml
 - /home/em7admin/sl1x-deploy/output-files/cluster.rkestate
 - /home/em7admin/sl1x-deploy/output-files/kube config cluster.yml

NOTE: ScienceLogic recommends that you back up these files at regular intervals.

4. Run the following command to enter the Ansible shell on the docker container:

```
docker-compose -f docker-compose.external.yml run --rm deploy shell
```

5. Delete any failed charts:

```
helm ls | awk '/FAILED/'
```

6. If the above command results in any output, run the following command:

```
helm delete --purge $(helm ls | awk '/FAILED/ { print $1 }')
```

7. Exit the Ansible shell session:

exit

- 8. If you have not already done so, you must *install ORAS* and *obtain your Harbor credentials*, which you will need for step 10.
- 9. If needed, use SSH to access the Management Node again. Open a shell session on the server. Log in with the system password you defined in the ISO menu.
- 10. Log in to Harbor repository:

```
oras login registry.scilo.tools/sciencelogic/
```

- Enter the username you used to log in to the browser-based session of Harbor.
- Enter the password (CLI Secret) that you saved from the browser-based session of Harbor.
- 11. Download the deployment files:

```
cd /home/em7admin/
oras pull registry.scilo.tools/sciencelogic/sl1x-deploy:11.2
cd sl1x-deploy
```

12. Copy the inventory template file to the file named sl1x-inv.yml:

```
cp sllx-inv-template.yml sllx-inv.yml
```

13. Edit the file sl1x-inv.yml to match your SL1 Extended system:

```
vi sl1x-inv.yml
```

CAUTION: Do not remove colons when editing this file.

- Make sure that the **sl1_version** value is set to the latest version in the 11.2 code line.
- Supply values in all the fields that are applicable. For details on the sl1x-inv.yml, see the manual *Installing SL1 Extended Architecture*.
- Save your changes and exit the file (: wq).
- 14. Pull the docker image that is referenced in the docker-compose file:

```
docker-compose -f docker-compose.external.yml pull
```

15. Update credentials on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy ssh-keys --ask-pass
```

When prompted, enter the System Password that you entered in the ISO menu.

16. Run the cn-helm-upgrade service and the app-purge service:

```
docker-compose -f docker-compose.external.yml run --rm deploy cn-helm-upgrade
```

```
docker-compose -f docker-compose.external.yml run --rm deploy app-
purge
```

17. Run the deploy commands at the shell prompt:

```
docker-compose -f docker-compose.external.yml run --rm deploy sl1x
```

18. Update security packages on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy
package-updates
```

Upgrading from 10.1.x to 11.2.x

To upgrade the SL1 Extended Architecture from the 10.1.x line to the 11.2.x line:

- 1. Use SSH to access the Management Node. Open a shell session on the server. Log in with the System Password you defined in the ISO menu.
- 2. In the Management Node, navigate to the sl1x-deploy directory. To do this, enter the following at the shell prompt:

```
cd sl1x-deploy
```

- 3. Back up the following files:
 - /home/em7admin/sl1x-deploy/sl1x-inv.yml
 - /home/em7admin/sl1x-deploy/output-files/cluster.yml

- /home/em7admin/sl1x-deploy/output-files/cluster.rkestate
- /home/em7admin/sl1x-deploy/output-files/kube config cluster.yml

NOTE: ScienceLogic recommends that you back up these files at regular intervals.

4. Run the following command to enter the Ansible shell on the docker container:

```
docker-compose -f docker-compose.external.yml run --rm deploy shell
```

5. Delete the following Helm charts:

```
helm delete --purge sl1-cn-registration

helm delete --purge model-registry

helm delete --purge aiml-redis-inputcache

kubectl patch pvc redis-data-model-registry-redis-master-0 -p '
{"metadata":{"finalizers":null}}'

kubectl patch pvc redis-data-aiml-redis-inputcache-master-0 -p '
{"metadata":{"finalizers":null}}'

kubectl delete pvc redis-data-model-registry-redis-master-0 --force --cascade=true

kubectl delete pvc redis-data-aiml-redis-inputcache-master-0 --force --cascade=true
```

6. Delete any failed charts:

```
helm ls | awk '/FAILED/'
```

7. If the above command results in any output, run the following command:

```
helm delete --purge $(helm ls | awk '/FAILED/ { print $1 }')
```

8. Exit the Ansible shell session:

```
exit
```

- 9. If you have not already done so, you must *install ORAS* and *obtain your Harbor credentials*, which you will need for step 11.
- 10. If needed, use SSH to access the Management Node again. Open a shell session on the server. Log in with the system password you defined in the ISO menu.
- 11. Log in to Harbor repository:

```
oras login registry.scilo.tools/sciencelogic/
```

- Enter the username you used to log in to the browser-based session of Harbor.
- Enter the password (CLI Secret) that you saved from the browser-based session of Harbor.
- 12. Download the deployment files:

```
cd /home/em7admin/
oras pull registry.scilo.tools/sciencelogic/sl1x-deploy:11.2
cd sl1x-deploy
```

13. Copy the inventory template file to the file named sl1x-inv.yml:

```
cp sl1x-inv-template.yml sl1x-inv.yml
```

14. Edit the file sl1x-inv.yml to match your SL1 Extended system:

```
vi sl1x-inv.yml
```

CAUTION: Do not remove colons when editing this file.

- Make sure that the **sl1_version** value is set to the latest version in the 11.2 code line.
- Supply values in all the fields that are applicable. For details on the sl1x-inv.yml, see the manual *Installing SL1 Extended Architecture*.
- Save your changes and exit the file (: wq).
- 15. Pull the Docker image that is referenced in the docker-compose file:

```
docker-compose -f docker-compose.external.yml pull
```

16. Update credentials on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy ssh-
keys --ask-pass
```

When prompted, enter the System Password that you entered in the ISO menu.

17. Run the cn-helm-upgrade service and the app-purge service:

```
docker-compose -f docker-compose.external.yml run --rm deploy cn-
helm-upgrade
```

docker-compose -f docker-compose.external.yml run --rm deploy apppurge

18. Run the deploy command:

```
docker-compose -f docker-compose.external.yml run --rm deploy sllx
```

19. Update security packages on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy
package-updates
```

Upgrading to 11.1.x

Upgrading from 11.1.x to the Latest Version of 11.1.x

To upgrade the SL1 Extended Architecture from the 11.1.x line to a later version of the 11.1.x line:

- 1. Use SSH to access the Management Node. Open a shell session on the server. Log in with the System Password you defined in the ISO menu.
- 2. In the Management Node, navigate to the sl1x-deploy directory. To do this, enter the following at the shell prompt:

```
cd sl1x-deploy
```

- 3. Backup the following files:
 - /home/em7admin/sl1x-deploy/sl1x-inv.yml
 - /home/em7admin/sl1x-deploy/output-files/cluster.yml
 - /home/em7admin/sl1x-deploy/output-files/cluster.rkestate
 - /home/em7admin/sl1x-deploy/output-files/kube_config_cluster.yml

NOTE: ScienceLogic recommends that you back up these files at regular intervals

4. Run the following command to enter the Ansible shell on the docker container:

```
docker-compose -f docker-compose.external.yml run --rm deploy shell
```

5. Delete any failed charts:

```
helm ls | awk '/FAILED/'
```

6. If the above command results in any output, run the following command:

```
helm delete $(helm ls | awk '/FAILED/ { print $1 }')
```

7. Exit out of ansible shell session:

```
exit
```

- 8. If you have not already done so, you must *install ORAS* and *obtain your Harbor credentials*, which you will need for step 10.
- 9. If needed, use SSH to access the Management Node again. Open a shell session on the server. Log in with the system password you defined in the ISO menu.

10. Log in to Harbor repository:

```
oras login registry.scilo.tools/sciencelogic/
```

- Enter the username you used to log in to the browser-based session of Harbor.
- Enter the password (CLI Secret) that you saved from the browser-based session of Harbor.
- 11. Download the deployment files:

```
cd /home/em7admin/
oras pull registry.scilo.tools/sciencelogic/sl1x-deploy:11.1
cd sl1x-deploy
```

12. Edit the file sl1x-inv.yml to match your SL1 Extended system:

```
vi sl1x-inv.yml
```

CAUTION: Do not remove colons when editing this file.

- Make sure that the **sl1_version value** is set to the latest version in the 11.1 code line.
- Supply values in all the fields that are applicable. Supply values in all the fields that are applicable. For details on the sllx-inv.yml, see the manual *Installing SL1 Extended Architecture*.
- Save your changes and exit the file (:wq).
- 13. Pull the docker image:

```
docker-compose -f docker-compose.external.yml pull
```

14. Update credentials on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy ssh-keys --ask-pass
```

When prompted, enter the System Password that you entered in the ISO menu.

15. Run the deploy commands:

```
docker-compose -f docker-compose.external.yml run --rm deploy kafka-
purge
```

```
docker-compose -f docker-compose.external.yml run --rm deploy sl1x
```

16. Update security packages on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy
package-updates
```

Upgrading from 10.2.x to 11.1.x

To upgrade the SL1 Extended Architecture from the 10.2.x line to the 11.1.x line:

- 1. Use SSH to access the Management Node. Open a shell session on the server. Log in with the System Password you defined in the ISO menu.
- 2. In the Management Node, navigate to the sl1x-deploy directory. To do this, enter the following at the shell prompt:

```
cd sl1x-deploy
```

- 3. Backup the following files:
 - /home/em7admin/sl1x-deploy/sl1x-inv.yml
 - /home/em7admin/sl1x-deploy/output-files/cluster.yml
 - /home/em7admin/sl1x-deploy/output-files/cluster.rkestate
 - /home/em7admin/sl1x-deploy/output-files/kube config cluster.yml

NOTE: ScienceLogic recommends that you back up these files at regular intervals

4. Run the following command to enter the Ansible shell on the docker container:

```
docker-compose -f docker-compose.external.yml run --rm deploy shell
```

5. In the Ansible shell, delete the following deprecated helm charts:

```
helm delete --purge sl1-cn-registration
```

6. Delete any other failed charts:

```
helm ls | awk '/FAILED/'
```

7. If the above command results in any output, run the following command:

```
helm del --purge $(helm ls | awk '/FAILED/ { print $1 }')
```

8. Exit the Ansible shell session:

```
exit
```

- 9. If you have not already done so, you must *install ORAS* and *obtain your Harbor credentials*, which you will need for step 11.
- 10. If needed, use SSH to access the Management Node again. Open a shell session on the server. Log in with the system password you defined in the ISO menu.
- 11. Log in to Harbor repository:

```
oras login registry.scilo.tools/sciencelogic/
```

- Enter the username you used to log in to the browser-based session of Harbor.
- Enter the password (CLI Secret) that you saved from the browser-based session of Harbor.
- 12. Download the deployment files:

```
cd /home/em7admin/
oras pull registry.scilo.tools/sciencelogic/sl1x-deploy:11.1
cd sl1x-deploy
```

13. Rename old inventory file:

```
mv sl1x-inv.yml jfrog-sl1x-inv.yml
```

14. Copy the inventory template file to the file named sllx-inv.yml:

```
cp sl1x-inv-template.yml sl1x-inv.yml
```

15. Edit the file sl1x-inv.yml to match your SL1 Extended system:

```
vi sl1x-inv.yml
```

CAUTION: Do not remove colons when editing this file.

- Make sure that the **sl1 version value** is set to the latest version in the 11.1 code line.
- Supply values in all the fields that are applicable. For details on the sl1x-inv.yml, see the manual *Installing SL1 Extended Architecture*.
- Save your changes and exit the file (:wq).
- 16. Update the docker image:

```
docker-compose -f docker-compose.external.yml pull
```

17. Update credentials on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy ssh-
keys --ask-pass
```

- When prompted, enter the System Password that you entered in the ISO menu.
- 18. Run the cn-helm-upgrade service and the app purge service:

```
docker-compose -f docker-compose.external.yml run --rm deploy cn-
helm-upgrade
```

docker-compose -f docker-compose.external.yml run --rm deploy apppurge

19. Run the deploy commands at the shell prompt:

```
docker-compose -f docker-compose.external.yml run --rm deploy sl1x
```

20. Update security packages on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy
package-updates
```

Upgrading from 10.1.x to 11.1.x

To upgrade the SL1 Extended Architecture from the 10.1.x line to the 11.1.x line:

- 1. Use SSH to access the Management Node. Open a shell session on the server. Log in with the System Password you defined in the ISO menu.
- 2. In the Management Node, navigate to the sl1x-deploy directory. To do this, enter the following at the shell prompt:

```
cd sl1x-deploy
```

- 3. Backup the following files:
 - /home/em7admin/sl1x-deploy/sl1x-inv.yml
 - /home/em7admin/sl1x-deploy/output-files/cluster.yml
 - /home/em7admin/sl1x-deploy/output-files/cluster.rkestate
 - /home/em7admin/sl1x-deploy/output-files/kube config cluster.yml

NOTE: ScienceLogic recommends that you back up these files at regular intervals

4. Run the following command to enter Ansible shell on the the docker container:

```
docker-compose -f docker-compose.external.yml run --rm deploy shell
```

5. Inside the Ansible shell delete the following helm charts:

```
helm delete --purge sl1-cn-registration

helm delete --purge model-registry

helm delete --purge aiml-redis-inputcache

kubectl patch pvc redis-data-model-registry-redis-master-0 -p '
{"metadata":{"finalizers":null}}'

kubectl patch pvc redis-data-aiml-redis-inputcache-master-0 -p '
{"metadata":{"finalizers":null}}'
```

```
kubectl delete pvc redis-data-model-registry-redis-master-0 --force -
-cascade=true
```

kubectl delete pvc redis-data-aiml-redis-inputcache-master-0 --force
--cascade=true

6. Delete any failed charts:

```
helm ls | awk '/FAILED/'
```

If the above command results in any output, run the following command:

```
helm delete --purge $(helm ls | awk '/FAILED/ { print $1 }')
```

7. Exit the ansible shell session:

exit

- 8. If you have not already done so, you must *install ORAS* and *obtain your Harbor credentials*, which you will need for step 10.
- 9. If needed, use SSH to access the Management Node again. Open a shell session on the server. Log in with the system password you defined in the ISO menu.
- 10. Log in to Harbor repository:

```
oras login registry.scilo.tools/sciencelogic/
```

- Enter the username you used to log in to the browser-based session of Harbor.
- Enter the password (CLI Secret) that you saved from the browser-based session of Harbor.
- 11. Download the deployment files:

```
cd /home/em7admin/
oras pull registry.scilo.tools/sciencelogic/sl1x-deploy:11.1
cd sl1x-deploy
```

12. Rename old inventory file:

```
mv sl1x-inv.yml jfrog-sl1x-inv.yml
```

13. Copy the inventory template file to the name sl1x-inv.yml:

```
cp sl1x-inv-template.yml sl1x-inv.yml
```

14. Edit the file sl1x-inv.yml to match your SL1Extended system:

```
vi sllx-inv.yml
```

CAUTION: Do not remove colons when editing this file.

- Make sure that the **sl1 version value** is set to the latest version in the 11.1 code line.
- Supply values in all the fields that are applicable. For details on the sl1x-inv.yml, see the manual *Installing SL1 Extended Architecture*.
- Save your changes and exit the file (:wq).
- 15. Update the docker image:

```
docker-compose -f docker-compose.external.yml pull
```

16. To update credentials on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy ssh-
keys --ask-pass
```

When prompted, enter the System Password that you entered in the ISO menu.

17. Run helm upgrade and purge app services:

```
docker-compose -f docker-compose.external.yml run --rm deploy cn-helm-upgrade
```

```
docker-compose -f docker-compose.external.yml run --rm deploy app-
purge
```

18. Run the deploy command:

```
docker-compose -f docker-compose.external.yml run --rm deploy sllx
```

19. Update security packages on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy
package-updates
```

Upgrading from 8.14.x to 11.1.x

To upgrade the SL1 Extended Architecture from the 8.14.x line to the 11.1.x line:

- 1. Use SSH to access the Management Node. Open a shell session on the server. Log in with the System Password you defined in the ISO menu.
- 2. In the Management Node, navigate to the sl1x-deploy directory. To do this, enter the following at the shell prompt:

```
cd sl1x-deploy
```

3. Backup the following files:

- /home/em7admin/sl1x-deploy/sl1x-inv.yml
- /home/em7admin/sl1x-deploy/output-files/cluster.yml
- /home/em7admin/sl1x-deploy/output-files/cluster.rkestate
- /home/em7admin/sl1x-deploy/output-files/kube config cluster.yml

NOTE: ScienceLogic recommends that you back up these files at regular intervals

3. Run the following command to enter the Ansible shell on the docker container:

```
docker-compose -f docker-compose.external.yml run --rm deploy shell
```

4. Make a note of the HOSTS value from running the following command:

```
kubectl get ing responder-ingress
```

5. In the Ansible shell delete the the following services on helm chart:

```
helm delete --purge sl1-cn-registration
```

helm delete --purge sl1-streamer

helm delete --purge sls-api-storeconfig

helm delete --purge avail-store

helm delete --purge da-postprocessing-service

helm delete --purge bundle-manager

6. Delete any failed charts:

```
helm ls | awk '/FAILED/'
```

If the above command results in any output, run the following command:

```
helm delete --purge $(helm ls | awk '/FAILED/ { print $1 }')
```

7 Exit the Ansible shell session:

exit

8. Monitor the queues until they are drained:

```
check https://<HOSTS>/api/queues/list/?api key=asdfQ345sdf
```

where:

HOSTS is the value from step #5.

Refresh that page until all queues have a value of 0 (zero).

- 9. If you have not already done so, you must *install ORAS* and *obtain your Harbor credentials*, which you will need for step 11.
- 10. If needed, use SSH to access the Management Node again. Open a shell session on the server. Log in with the system password you defined in the ISO menu.
- 11. Log in to Harbor repository:

```
oras login registry.scilo.tools/sciencelogic/
```

- Enter the username you used to log in to the browser-based session of Harbor.
- Enter the password (CLI Secret) that you saved from the browser-based session of Harbor.
- 12. Download the deployment files:

```
cd /home/em7admin/
oras pull registry.scilo.tools/sciencelogic/sl1x-deploy:10.1
cd sl1x-deploy
```

13. Rename old inventory file:

```
mv sl1x-inv.yml sl1x-inv.yml.8.14
```

14. Copy the inventory template file to the name sllx-inv.yml:

```
cp sl1x-inv-template.yml sl1x-inv.yml
```

15. Edit the file sl1x-inv.yml to match your SL1Extended system:

```
vi sl1x-inv.yml
```

CAUTION: Do not remove colons when editing this file.

- Make sure that the sl1 version value is set to the latest version in the 11.1 code line.
- Supply values in all the fields that are applicable. Supply values in all the fields that are applicable. For details on the sllx-inv.yml, see the manual *Installing SL1 Extended Architecture*.
- Save your changes and exit the file (:wq).
- 16. Download the deployment latest files:

```
docker-compose -f docker-compose.external.yml pull

docker-compose -f docker-compose.external.yml run --rm deploy ssh-
keys --ask-pass
```

When prompted, enter the System Password that you entered in the ISO menu.

17. Update the SL1 Extended system compute nodes at the shell prompt:

```
docker-compose -f docker-compose.external.yml run --rm deploy cn
```

18. Navigate to the sllx-deploy directory and download and extract latest templates:

```
cd /home/em7admin/
oras pull registry.scilo.tools/sciencelogic/sl1x-deploy:11.1
cd sl1x-deploy
```

19. Update libraries and credentials on all nodes:

```
docker-compose -f docker-compose.external.yml pull

docker-compose -f docker-compose.external.yml run --rm deploy ssh-
keys --ask-pass
```

When prompted, enter the System Password that you entered in the ISO menu.

20. Run helm upgrade and purge app services:

```
docker-compose -f docker-compose.external.yml run --rm deploy cn-helm-upgrade

docker-compose -f docker-compose.external.yml run --rm deploy app-
```

21. Run the deploy command:

purge

```
docker-compose -f docker-compose.external.yml run --rm deploy sl1x
```

22. Update security packages on all nodes:

```
docker-compose -f docker-compose.external.yml run --rm deploy
package-updates
```

Chapter

6

SL1 Self-Monitoring

Overview

SL1 includes various tools that enable your SL1 system to monitor the appliances within your system as well as your other SL1 stacks. This proactive system health monitoring helps prevent outages and other major issues.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon
- To view a page containing all of the menu options, click the Advanced menu icon (···).

This chapter covers the following topics:

The Workflow for SL1 Self-Monitoring	239
PowerPacks Required for Self-Monitoring	239
Credentials Required for Self-Monitoring	242
Discovering Your SL1 Devices	243
Enabling Connectivity on Port 7707	243
Aligning SL1 Self-Monitoring Dynamic Applications	244
Aligning the Correct Credentials to Your Devices	246
Configuring Run Book Automations to Populate Dashboards	246
Additional Self-Monitorina Resources	249

The Workflow for SL1 Self-Monitoring

The workflow for SL1 self-monitoring is:

- 1. Ensure you have the latest version of the required PowerPacks.
- 2. Create the appropriate credentials.
- 3. Discover your SL1 devices.
- 4. Enable connectivity on port 7707 (not required in all scenarios)
- 5. Align additional Dynamic Applications to your SL1 devices using device templates.
- 6. Ensure the correct credentials are aligned to the Dynamic Applications.
- Configure run book automations to populate dashboards with data about your SL1 devices.

PowerPacks Required for Self-Monitoring

To self-monitor SL1, you must first have the latest versions of the following PowerPacks:

- ScienceLogic Support Pack
- Data Pull Support
- SL1: Operational Insights

ScienceLogic Support Pack

SL1 includes the "ScienceLogic Support Pack" PowerPack by default with all SL1 releases.

This PowerPack was developed by ScienceLogic Support to help you monitor your SL1 systems. It allows an SL1 stack to monitor itself and other SL1 stacks.

The "ScienceLogic Support Pack" PowerPack:

- ensures that all SL1 appliances are monitored and running the same version of SL1
- ensures that all SL1 appliances appear on the **Devices** page
- ensures that configuration files on SL1 appliances and clusters are kept in sync
- monitors the health and configuration of MariaDB
- generates alerts when system resources like disk-space are approaching capacity
- monitors DNS entries for Database Servers and All-In-One Appliances
- monitors long-running processes and queries
- monitors out-of-memory conditions
- ensures that CRM and corosync configurations are up to date
- ensures that configuration files match among high-availability Database Servers
- monitors crucial SL1 processes like data pull and config push

- monitors "rows behind" situations and generates alerts
- monitors and fixes backlogs of email messages
- generates alerts if any of the following files differ:
 - ° /etc/my.cnf.d/silo mysql.cnf
 - ° /etc/silo.conf
 - ° /etc/siteconfig/mysql.siteconfig
 - 'etc/siteconfig/siloconf.siteconfig
- collects telemetry related to Device Groups

The PowerPack is designed to work "out of the box" with very little configuration required. The Dynamic Applications included in the PowerPack should automatically align when you discover your SL1 appliances for self-monitoring.

NOTE: For more information about the Dynamic Applications that are included in the "ScienceLogic Support Pack" PowerPack, see the following knowledge base article: https://support.sciencelogic.com/s/article/2951.

TIP: Because the PowerPack is included in SL1 installations and upgrades by default, you cannot download it from the ScienceLogic Support site. Whenever you upgrade your SL1 stack to the latest release, you should go to the PowerPack Manager page (System > Manage > PowerPacks) to check for a new version of the "ScienceLogic Support Pack" PowerPack. For more information about updating default PowerPacks, see the section on "How SL1 Updates Default PowerPacks" in the PowerPacks manual.

Data Pull Support

The "Data Pull Support" PowerPack is also included by default in all SL1 releases.

It includes several Dynamic Applications that use SNMP to collect configuration and performance data related to data pull, which is the process by which SL1 Database Servers retrieve collected data from Data Collectors and Message Collectors.

TIP: Because the PowerPack is included in SL1 installations and upgrades by default, you cannot download it from the ScienceLogic Support site. Whenever you upgrade your SL1 stack to the latest release, you should go to the PowerPack Manager page (System > Manage > PowerPacks) to check for a new version of the "Data Pull Support" PowerPack. For more information about updating default PowerPacks, see the section on "How SL1 Updates Default PowerPacks" in the PowerPacks manual.

SL1: Operational Insights PowerPacks

To self-monitor SL1, you will also need either the "SL1: Operational Insights - On Premise" or "SL1: Operational Insights - SaaS" PowerPack, depending on your system configuration:

- "SL1: Operational Insights On-Premise" is required for MariaDB databases.
- "SL1: Operational Insights SaaS" is required for Aurora RDS databases or SaaS stacks.

These PowerPacks include a variety of Dynamic Applications, run book actions and automation policies, dashboards, and other tools that provide additional SL1 platform health visibility using data collected by the "ScienceLogic Support Pack".

Unlike the "ScienceLogic Support Pack" and "Data Pull Support" PowerPacks, the "SL1: Operational Insights" PowerPacks *are not* included by default in SL1 releases. To use them, you must first download them from the ScienceLogic Support site and then install them on your SL1 system.

IMPORTANT: If you are downloading version 105 or later of the "SL1: Operational Insights - On-Premise" or "SL1: Operational Insights - SaaS" PowerPack, then you can follow the steps below to download and install the PowerPack directly.

However, if you are upgrading from version 104 or earlier, there are additional steps that you must follow. These steps are detailed in the user manual that can be downloaded along with the PowerPack file on the ScienceLogic Support Site at https://support.sciencelogic.com/s/powerpacks.

NOTE: You can periodically check the ScienceLogic Support Site at https://support.sciencelogic.com/s/powerpacks for any newer versions of the "SL1: Operational Insights - SaaS" PowerPacks.

TIP: By default, installing a new version of a PowerPack overwrites all content from a previous version of that PowerPack that has already been installed on the target system. You can use the *Enable Selective PowerPack Field Protection* setting in the *Behavior Settings* page (System > Settings > Behavior) to prevent new PowerPacks from overwriting local changes for some commonly customized fields. (For more information, see the *System Administration* manual.)

IMPORTANT: The minimum required MySQL version is 5.6.0.

To download and install the PowerPack:

- Search for and download the PowerPack from the PowerPacks page (Product Downloads > PowerPacks & SyncPacks) at the <u>ScienceLogic Support Site</u>.
- 2. In SL1, go to the **PowerPacks** page (System > Manage > PowerPacks).
- 3. Click the [Actions] button and choose Import PowerPack. The Import PowerPack dialog box appears.
- 4. Click [Browse] and navigate to the PowerPack file from step 1.

- 5. Select the PowerPack file and click [Import]. The PowerPack Installer modal displays a list of the PowerPack contents.
- 6. Click [Install]. The PowerPack is added to the PowerPacks page.

NOTE: If you exit the **PowerPack Installer** modal without installing the imported PowerPack, the imported PowerPack will not appear in the **PowerPacks** page. However, the imported PowerPack will appear in the **Imported PowerPacks** modal. This page appears when you click the **[Actions]** menu and select *Install PowerPack*.

Credentials Required for Self-Monitoring

To self-monitor SL1, you must ensure that you have all of the required credentials:

- The "EM7 Default V2" SNMP credential
- A copy of the "SL1 CDB" credential
- A copy of the "SL1 Collector Database" credential

All three of these credentials are included by default on your SL1 system.

For self-monitoring purposes, the "EM7 Default V2" SNMP credential does not need to be updated or copied.

However, you must make a copy of the two database credentials. This is done to ensure those credentials are not accidentally overwritten whenever you update your SL1 system. After you have made copies of those credentials, you can then assign the appropriate database IP address, username, and password to each of those copies.

NOTE: If you have an on-premises SL1 system, then you should enter your MariaDB IP address, username, and password in the copied credentials. If you have a SaaS SL1 system, then you should enter your Aurora RDS IP address, username, and password in the copied credentials. SaaS customers can obtain the correct Aurora RDS credential information from ScienceLogic.

To copy and update the database credentials:

- 1. Go to the **Credentials** page (Manage > Credentials).
- 2. Click the **Actions** icon (**) of the credential you want to duplicate ("SL1 CDB" or "SL1 Collector Database") and then select *Duplicate*. A copy of the credential appears on the **Credentials** page.
- 3. To edit the copied credential, click its **Actions** icon (**) and then select *Edit/Test*. The **Edit Credential** modal appears.

- 4. In the **Edit Credential** modal, supply values in the following fields:
 - Name. Type a new name for the copied credential.
 - Database User. Type the database username associated with a valid account on the database.
 - For the "SL1 CDB" credential, enter the database username for the primary Database Server.
 - For the "SL1 Collector Database" credential, enter the database username for the Data Collector or Message Collector.
 - Password. Type the password associated with the database user you entered in the Database User field.
 - Hostname/IP. Type the database hostname or IP address.
- 5. After editing the fields in the **Edit Credential** modal, click the **[Save & Close]** button.

Discovering Your SL1 Devices

After creating your credentials, you will then use those credentials to discover your SL1 appliances.

To do so, follow the instructions found in the "Adding Devices Using Unguided Discovery" section of the **Discovery & Credentials** manual.

While configuring your discovery policy, make sure to do the following:

- Select the "EM7 Default V2" SNMP credential.
- Additionally, select your copies of the "SL1 CDB" credential and/or "SL1 Collector Database" credentials, depending on whether you are discovering the Database Server, one or more Data Collectors or Message Collectors, or both the Database Server and one or more collectors.
- When listing the IP addresses that you want to discover, include the IP addresses of all SL1 appliances that you want to discover.
- Under **Advanced Options**, select the **Discover non-SNMP** toggle to turn it on.

Upon discovering your SL1 appliances, most SNMP-based Dynamic Applications should automatically be aligned to the appropriate devices.

TIP: After discovering your SL1 appliances, you can go to the **Appliance Manager** page (System > Settings > Appliances) to confirm that they all appear on the page and that their settings are correct. For example, the **Device Name** on the **Devices** and **Device Manager** (Devices > Device Manager) pages should match the **Device Name** on the **Appliance Manager** page.

Enabling Connectivity on Port 7707

On-premises Data Collector and Message Collector appliances do not allow connections to port 7707 (MariaDB) from an external device. Therefore, if you want one on-premises Data Collector to monitor another Data Collector or Message Collector, then there are some additional steps you must take to enable connectivity on port 7707.

NOTE: Some Dynamic Applications collect data from MariaDB/ Aurora and should be able to connect to port 7706 (DB/AlO) or 7707 (Data/ Message Collector) Please ensure that any firewalls between the monitoring collector and the monitored appliances allow communication from the monitoring collector to the monitored appliances on port 7706 or 7707.

NOTE: If this scenario does not apply to your SL1 configuration, then you can skip this section.

For the instructions below, consider the following scenario:

- "Collector A" is the Data Collector or Message Collector you want to monitor.
- "Collector B" is the Data Collector on which you want to monitor Collector A.

To enable connectivity on port 7707 in this scenario:

1. Log in to the Web Configuration Utility for Collector A using any web browser supported by SL1. The address of the Web Configuration Utility is in the following format:

https://<Collector-A-IP-address>:7700

NOTE: For AWS instances, *Collector-A-IP-address* is the public IP for the AWS instance for Collector A. To locate the public IP address for an AWS instance, go to AWS, go to the *Instances* page, and highlight an instance. The **Description** tab in the lower pane will display the public IP.

- 2. When prompted to enter your username and password, log in as the "em7admin" user with the appropriate password. After logging in, the main **Configuration Utility** page appears.
- 3. Click the [Device Settings] button. The Settings page appears.
- 4. On the Settings page, add the IP address for Collector B to the Database IP Address field, immediately after the IP address that is already listed for Collector A, separated by a comma and no space. For example, if the IP address for Collector A is 10.10.10.1 and the IP address for Collector B is 10.20.20.2, then you would enter "10.10.10.1,10.20.20.2" (without the quotation marks) in the Database IP Address field
- Click [Save] and log out of the Web Configuration Utility. With this change saved, the firewalld rules on Collector A will be updated to allow connectivity to port 7706 (MariaDB) from the IP address for Collector B.

Aligning SL1 Self-Monitoring Dynamic Applications

After discovering your SL1 appliances, you must ensure that they are properly set up for monitoring. The easiest way to do this is to apply the device templates that are included in the "ScienceLogic Support Pack," "Data Pull

Support," and "SL1: Operational Insights" PowerPacks to ensure your SL1 device classes have the necessary Dynamic Applications aligned to them.

To align the appropriate self-monitoring Dynamic Applications using device templates:

- 1. Go to the **Device Manager** page (Devices > Device Manager).
- 2. In the **Device Class** column, use the filter field to search for the appropriate device class based on the table at the end of this section.
- 3. Select the checkbox for each row that contains the device class type that you want to modify.

NOTE: Because each of these device classes requires a different configuration, you should modify devices of only one device class at a time.

- 4. From the **Select Action** field at the bottom of the page, select MODIFY by Template and then click **[Go]**. The **Bulk Device Configuration** modal appears.
- 5. In the *Template* drop-down field at the top of the **Bulk Device Configuration** modal, select the appropriate device template based on the table at the bottom of this section.

NOTE: You can select only one device template at a time. For device classes that have multiple device templates, complete steps 5-7 for one template, then repeat the steps for the other templates.

- 6. Click the [Dyn Apps] tab and verify that a list of Dynamic Applications appear in the **Subtemplate** Selection pane.
- 7. Click [Apply], and then click [Confirm].
- 8. Repeat steps 1-7 as needed until all of the device classes needed for self-monitoring have all of the appropriate device templates applied to them, based on the following table:

Appliance Type	Device Class	Device Templates
Primary Database Server or cluster IP device	SL1 Database	Support: SL1 Active DB/VIP
		SL1: Database - On Premise
		SL1 System Processes
Administration Portal	EM7 Admin Portal	Support: SL1 Application Portal
Data Collector	SL1 Data Collector	Support: SL1 Collector
		SL1: Collectors
		SL1 System Processes
Message Collector	SL1 Message Collector	Support: SL1 Message Collector
		SL1 System Processes

NOTE: It can take Dynamic Applications up to 15 minutes to start collecting data after they are aligned.

Aligning the Correct Credentials to Your Devices

When you align the self-monitoring Dynamic Applications to your SL1 appliances using the device templates that are included in the self-monitoring PowerPacks, those Dynamic Applications use the unedited versions of the "SL1 CDB" and "SL1 Collector Database" credentials that are included in the PowerPacks.

Now, you must edit those Dynamic Applications to use the *copies you made for those credentials* instead of the original versions that are included in the self-monitoring PowerPacks. This will prevent SL1 from overwriting your self-monitoring configuration whenever you install updates for those PowerPacks in the future.

To ensure the correct credentials are aligned to your SL1 devices:

- 1. Go to the **Device Manager** page (Devices > Device Manager).
- 2. Locate one of your SL1 devices and click its wrench icon (). The **Device Administration** panel appears.
- 3. On the **Device Administration** panel, click the **[Collections]** tab. The **Dynamic Application Collections** page appears.
- 4. On the **Dynamic Application Collections** page, locate and select the checkboxes for any Dynamic Applications that have "SL1 CDB" listed in the **Credential** column.
- 5. From the **Select Action** field at the bottom of the page, select your copied version of the "SL1 CDB" credential from the list and then click [Go]. The **Dynamic Application Collections** page will refresh and your copied version of the "SL1 CDB" credential should now be listed in the **Credential** column for the Dynamic Applications you selected.
- 6. Repeat steps 4 and 5 to replace the credential for any Dynamic Applications that currently have the "SL1 Collector Database" credential in the **Credential** column with your copy of that credential.

Configuring Run Book Automations to Populate Dashboards

The "SL1: Operational Insights" PowerPacks include two run book actions and automation policies: "SL1: Collector Data Collection" and "SL1: System Log Data Collection."

These automations collect data that is then used to populate the "Collector Performance" and "System Logs Summary" dashboards, respectively, with data relating to your monitored SL1 appliances.

TIP: If you are using the ScienceLogic SL1 Operational Insights - On-Premise Community PowerPack, please review the manual that is shipped with the PowerPack for more information on configuring run book automations. Be advised, the manual shipped with the PowerPack is not official ScienceLogic documentation.

SL1: Collector Data Collection

The "SL1: Collector Data Collection" automation is responsible for collecting SL1 Collector-specific data that is used in the "Collector Performance" dashboard. The automation policy is configured to trigger the "SL1: Collector Data Collection" run book action four times once per hour. The automation helps identify SL1 Collectors that have been discovered and match the following criteria required to appear in the "Collector Performance" dashboard:

- Data Collectors and Message Collectors should be discovered as managed devices.
- The discovered SL1 Collector's **Device Name** on the **Devices** and **Device Manager** (Devices > Device Manager) pages should match the name of the same collector from the **Appliance Manager** page (System > Settings > Appliances).
- The SL1 Collectors should have the following two Dynamic Applications aligned and successfully collecting data:

° Support: File System

Host Resource: Configuration

• The Data Collectors should be in a collector group (CUG). This does not apply to Message Collectors.

When the automation runs, it stores the data in a custom table, which is then read and displayed by the dashboard widget.

SL1: System Log Data Collection

The "SL1: System Log Data Collection" automation is responsible for collecting system log-specific data that is used in the "System Logs Summary" dashboard. The Automation is configured to trigger the "SL1: System Log Data Collection" run book action five times once per hour.

The automation parses the top problem logs, including SIGTERMs, PoolWorker logs, and unhandled exceptions.

When the automation runs, it stores the data in a custom table, which is then read and displayed by the dashboard widget.

NOTE: If the total system log count is greater than 6 million, the automation will not collect data; instead, the "System Logs Summary" dashboard will display a message stating that the log count is too high. If this occurs, delete older logs to bring the total count below 6 million.

Verifying Your Devices

Before you configure the run book automation policies required to populate the "Collector Performance" and "System Logs Summary" dashboards, you must verify that you have the necessary devices in your SL1 system. The method for doing so will vary based on whether you have an on-premises SL1 system or a SaaS SL1 system. Both methods are described below.

On-Premises SL1 Systems

To verify that you have the necessary devices:

- 1. Go to the **Device Manager** page (Devices > Device Manager).
- 2. In the **Device Class** column, use the filter field to search for devices with the "SL1 Database" device class.

- 3. Verify that all Database Servers are discovered.
- 4. If the Database Servers are not discovered, then you must *discover them*. Otherwise, if they are, you can skip to the next section.

SaaS SL1 Systems

To verify that you have the necessary device:

- 1. Go to the **Device Manager** page (Devices > Device Manager).
- 2. In the **Device Name** column, use the filter field to search for a device with the name "SL1 Stats".
- 3. Verify that the "SL1 Stats" device exists. If it does not yet exist, proceed to the next step. Otherwise, if it does, you can skip to the next section.
- 4. From the [Actions] menu, select Create Virtual Device. The Create Virtual Device modal appears.
- 5. Complete the following fields:
 - Device Name. Type "SL1 Stats".
 - Organization. Select System.
 - **Device Class**. Select Virtual Device | Dynamic App Emissary.
 - Collector. Select Self Monitoring Collector.
- 6. Click [Add] and then exit the modal.

Configuring the Run Book Automations

To configure the run book automation policies required to populate the "Collector Performance" and "System Logs Summary" dashboards:

- 1. Go to the **Automation Policy Manager** page (Registry > Run Book > Automation).
- 2. In the **Automation Policy Name** column, use the filter field to search for a policy with the name "SL1: Collector Data Collection".
- 3. Click the wrench icon () for the "SL1: Collector Data Collection" automation policy. The **Automation Policy Editor** modal appears.
- 4. In the **Available Devices** field, use the filter field to search for the appropriate device:
 - For on-premises SL1 deployments, search for the active SL1 Database Server device.
 - For SaaS SL1 deployments, search for the "SL1 Stats" device.
- 5. Select the device from the **Available Devices** field and then click the right arrow icon to move it to the **Aligned Devices** field.
- 6. Click [Save] and then exit the Automation Policy Editor modal.
- 7. Repeat steps 1-6 to search for and configure the "SL1" System Log Data Collection" automation policy.

Additional Self-Monitoring Resources

For information about additional steps you can take in SL1 to monitor your SL1 system, see the following chapters in this manual:

- Daily Health Tasks
- Monitoring and Maintaining SL1
- Diagnostic Tools

Chapter

7

Monitoring and Maintaining SL1

Overview

This chapter describes how to manage user access, manage scheduled tasks, and more.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon
- To view a page containing all of the menu options, click the Advanced menu icon (...).

This chapter covers the following topics:

Monitoring and Managing User Access	250
Managing Scheduled Tasks	253
Putting the Database Server into Maintenance Mode	257
Monitoring Overall System Usage and Statistics	258
Viewing an Overview of All Events	259
Viewing Events by Appliance and Event Source	260

Monitoring and Managing User Access

SL1 lets multiple users log into the same SL1 system at the same time. The time a user spends logged into SL1 is known as a *user session*. You can end a user's session in SL1, and you can also limit the number of users that can be simultaneously logged into an SL1 system.

The Access Sessions page allows administrators to monitor user logins and logouts to the user interface.

From this page, you can also:

- End a user's session.
- View a list of accounts that are locked out of the user interface due to invalid username and password.
- Unlock accounts that are locked out of the user interface.

Viewing Information about Each Access Session

The **Access Sessions** page displays a list of recent logins to the user interface. To view the **Access Sessions** page:

- 1. Go to the **Access Sessions** page (System > Monitor > Access Logs).
- 2. For each session, the Access Sessions page displays:
 - User Account. Username of person logging in to the user interface.
 - **User Display Name**. The username, email address, or preferred display name. This value is determined by the user's authentication resource settings.
 - Last Address. IP address from which the user accessed the user interface.
 - State. Current status of the user. The choices are:
 - ° Active. User is currently logged in to the user interface.
 - ° Expired. User's session in the user interface was killed.
 - ^o Logged Out. User logged out of the user interface.
 - Never Used. User logged in to the user interface and did not perform any tasks before the session was killed.
 - Login Time. Date and time at which the user logged in.
 - Last-Hit Time. Date and time at which the user last loaded a page in the user interface.
 - Logout Time. Date and time at which the user logged out.
 - Session Duration. Length of time between login and logout.
 - Session ID. Unique numeric ID assigned to each user session.

Deleting a User's Session

From the **Access Sessions** page, you can end a user's session in the user interface. The user must log in again to access the user interface. The status of the session will be "expired".

To end a user's session:

- 1. Go to the **Access Sessions** page (System > Monitor > Access Logs).
- 2. In the Access Sessions page, find the session you want to end. Click the checkbox (2) for that session.
- 3. Click the **Select Actions** field (in the lower right of the page) and then select *Kill user session*. Click the **[Go]** button

4. Each selected session is ended. The user associated with each selected session is logged out of the user interface. The status of the session changes to "expired".

NOTE: After ending a user's session, that user can immediately log in to the user interface again. To prevent a user from logging in to the user interface, you must disable the user's account. For information on user accounts, see the manual **Organizations and Users**.

Limiting the Number of Simultaneous User Sessions

Starting with SL1 12.1.1, the maximum number of simultaneous user sessions was set to 300 by default. If you get an "HTTP Response code was 429 (Too Many Requests)" error or a "User sessions at maximum" in SL1, you can adjust the **USER MAX SESSIONS** value in the **/opt/em7/nextui/nextui.conf** file:

- 1. SSH to the SL1 appliance and log in as user em7admin.
- 2. At the command line, open the nextui.conf file in the vi editor:

```
sudo vi /opt/em7/nextui/nextui.conf
```

- In the NextUI configuration file, set a new value for USER_MAX_SESSIONS, such as USER_MAX_ SESSIONS=1000 for 1,000 concurrent user sessions.
- Save your changes and restart the NextUI service:

```
sudo systemctl restart nextui
```

Viewing Lockouts and Unlocking Lockouts

If a user enters incorrect login information multiple times in a row, that username, the user's IP address, or both will be locked out of the user interface.

To view lockouts or restore login privileges to locked out users:

- 1. Go to the **Access Sessions** page (System > Monitor > Access Logs).
- 2. In the Access Sessions page, click the [Lockouts] button.
- 3. The **Account Lockouts** modal page allows administrators to view a list of locked-out accounts and to restore login privileges to locked out users.
- 4. The Account Lockouts modal page displays the following about each lockout:
 - Attempt Account. Username that caused the lockout.
 - From Address. IP address from which the failed login attempts originated.
 - Attempt Time. Date and time at which lockout occurred.
 - Tries. Number of times user tried to log in to the user interface.
- 5. To remove the lock for the user account and allow logins from the username and/or IP address, click the bomb icon ().

Global Settings for Lockouts

The platform includes global settings that define how lockouts behave. In the **Behavior Settings** page (System > Settings > Behavior), the following fields affect lock-outs:

- · Account Lockout Type
- Account Lockout Attempts
- Account Lockout Duration
- Lockout Contact Information

Audit Logs

For additional information about users and their actions in the platform, you can view the **Audit Logs** page. The **Audit Logs** page provides a complete audit trail for the platform. The **Audit Logs** page displays a record of all actions in the platform that are generated by users or by managed elements. For details, see the section on **Audit Logs**.

Improved User Session Control with tmux

Starting with SL1 version 12.2.1, the tmux utility now runs by default when you access an SL1 system using SSH. The *tmux utility* is a terminal multiplexer that enables a number of terminals to be created, accessed, and controlled from a single screen.

In previous versions of SL1, session control relied on the default shell **TMOUT** variable, which logged out user sessions after five minutes of inactivity. Starting with SL1 version 12.2.1, this function is now integrated into tmux, automatically locking sessions after 15 minutes of idleness, or if an unclean SSH disconnect or dropped SSH connection occur. This update ensures that idle work is detached rather than lost, resembling workstation behavior when idle. Upon login, SL1 checks for detached tmux sessions and attaches detached tmux sessions if it finds them. Otherwise SL1 starts a new session.

Beyond improved session control, tmux also introduces advanced features like scroll-back buffering with search, built-in clipboarding, multiple sessions and panes, detaching or attaching sessions, and session supervision or sharing. For more information about tmux shortcuts and usage, see https://tmuxcheatsheet.com/.

NOTE: When using the command-line interface on an SL1 appliance, the interface is meant for limited administrative purposes only.

Managing Scheduled Tasks

The **Schedule Manager** page (Registry > Schedules > Schedule Manager) allows you to view and manage all the scheduled processes you have defined in your system.

You can define scheduled processes in the following pages:

- Report Scheduler. (For more information, see the **Reports** manual.)
- My Work Schedule. (For more information, see the Organizations and Users manual.)
- Recurring Ticketing Scheduler. (For more information, see the Ticketing manual.)
- Discovery Control Panel. (For more information, see the **Discovery and Credentials** manual.)
- Dashboards. (For more information, see the **Dashboards** manual.)
- IT Service Editor. (For more information, see the *IT Services* manual.)
- Device Manager. (For more information, see the **Device Management** manual.)
- Backup Management. (For more information, see the section on Configuration Backups.)

Managed schedules are loaded in batches of 1,000 by default to prevent the Process Manager from becoming overloaded and stopping the scheduled jobs prematurely. Previously, all scheduled jobs were loaded simultaneously. You can update the default batch number of scheduled jobs by going to the Database Tool page (System > Tools > DB Tool) and entering the following in the **SQL Query** field, replacing

with the number of scheduled jobs you want to load per batch:

```
INSERT INTO master.system_custom_config (field, field_value) VALUES
('load_schedules_in_batches', <batch_number>) ON DUPLICATE KEY UPDATE
field = 'load_schedules_in_batches', field_value = <batch_number>
```

Recommended System Maintenance

ScienceLogic also recommends that you take the following actions on a regular basis to reduce outages as much as possible.

Daily:

- Review "SL1 Operational Insights: Database Performance" classic dashboard
- Review "SL1 Operational Insights: Collector Performance" classic dashboard
- Review "SL1 Operational Insights: System Log Summary" classic dashboard
- Review "SL1 Operational Insights: Backup History" classic dashboard

TIP: You can find the *SL1* Operational Insights PowerPack on the **PowerPacks** page at the ScienceLogic Support Site: https://support.sciencelogic.com/s/powerpacks.

Weekly:

- Run the System Status Script and review:
 - Address every error item in the report
 - Read Knowledge Base articles
 - Open tickets for issues when help from SL1 Support is needed

Monthly:


· Review capacity items. You must understand License Usage and how to project future capacity

Quarterly:

- Audit User Profile access to verify that it meets expected needs
- Audit DNS servers and Timeservers on all collectors

Viewing the List of Schedules

The **Schedule Manager** page (Registry > Schedules > Schedule Manager) displays the following about each schedule:




- Schedule Summary. Displays the name assigned to the scheduled process.
- Schedule Description. Displays a description of the scheduled process.
- **Event ID**. Displays a unique, numeric ID for the scheduled process. SL1 automatically creates this ID for each scheduled process.
- sch id. Displays a unique, numeric ID for the schedule. SL1 automatically creates this ID for each schedule.
- Context. Displays the area of SL1 upon which the schedule works.
- Timezone. Displays the time zone associated with the scheduled process.
- Start Time. Displays the date and time at which the scheduled process will begin.
- **Duration**. Displays the duration, in minutes, which the scheduled process occurs.
- Recurrence Interval. If applicable, displays the interval at which the scheduled process recurs.
- End Date. If applicable, displays the date and time on which the scheduled process will recur.
- Last Run. If applicable, displays the date and time the scheduled process most recently ran.
- Owner. Displays the username of the owner of the scheduled process.

- Organization. Displays the organization to which the scheduled process is assigned.
- *Visibility*. Displays the visibility level for the scheduled process. Possible values are "Private", "Organization", or "World".
- Enabled. Specifies if the scheduled process is enabled. Possible values are "Yes" or "No".

Enabling or Disabling One or More Schedules

You can enable or disable one or more scheduled process from the **Schedule Manager** page (Registry > Schedules > Schedule Manager). To do this:

1. Go to the **Schedule Manager** page (Registry > Schedules > Schedule Manager).




- 2. Select the checkbox icon for each scheduled process you want to enable or disable.
- 3. Click the **Select Action** menu and choose Enable Schedules or Disable Schedules.
- 4. Click the [Go] button.

Deleting One or More Schedules

You can delete one or more scheduled process from the **Schedule Manager** page (Registry > Schedules > Schedule Manager). To do this:

1. Go to the **Schedule Manager** page (Registry > Schedules > Schedule Manager).



- 2. Select the checkbox icon for each scheduled process you want to delete.
- 3. Click the **Select Action** menu and choose Delete Schedules.
- 4. Click the [Go] button.

Putting the Database Server into Maintenance Mode

You can now put the Database Server in maintenance mode and stop all pull processes from the Data Collectors. You can then perform database maintenance or network maintenance without generating events.

After maintenance is completed, you can put the put the Database Server out of maintenance mode. Pull processes from the Data Collectors will resume from the point where they were paused.

The new commands are silostart and silostop.

To put a Database Server in maintenance mode:

- 1. Either go to the console of a Database Server or SSH to access the Database Server.
- 2. Log in as em7admin with the appropriate password.
- 3. At the shell prompt, execute the following:

To put a Database Server out of maintenance mode:

- 1. Either go to the console of a Database Server or SSH to access the Database Server.
- 2. Log in as **em7admin** with the appropriate password.
- 3. At the shell prompt, execute the following:

silostart


Monitoring Overall System Usage and Statistics

The **System Usage** page displays:

- Tables that show the type and number of each type of task performed by SL1
- An optional line graph that displays system usage. To enable the display of this graph, go to the **Behavior** Settings page (System > Settings > Behavior) and uncheck the *Hide Perpetual License Count* checkbox.
 The graph displays the following metrics over time:
 - Capacity. The total monitoring capacity of the system. This value is determined by the license(s) for the Database Server(s) or All-In-One Appliance(s) in the system.
 - Number of Devices. The number of devices currently discovered in the system.
 - System Usage. The amount of Capacity that the devices in the system are currently using. This value is the sum of the Device Ratings for all devices in the system. The Device Rating for each device is calculated daily and is based on the number of collections performed for that device.
- If you have a subscription license, you can also generate reports about subscription licensing.

To view the **System Usage** page:

- 1. Go to the **System Usage** page (System > Monitor > System Usage).
- 2. The **System Usage** page appears.



Viewing an Overview of All Events

The **Event Overview** page (System > Monitor > Event Overview) provides a graphical overview of all events in SL1.

The **Event Overview** page displays the following reports:

- **Number of Events by Severity**. This graph displays event distribution by severity for the last 24 hours and for the last 7 days.
 - ° The y-axis displays the number of events.
 - ° The x-axis displays severity.
 - ° The red line represents events in the last 24 hours.
 - The blue line represents events in the last 7 days.
 - Mousing over a data point in the red line displays the number of events of the specified severity in the last 24 hours.
 - Mousing over a data point on the blue line displays the number of events of the specified severity in the last 7 days.

- Most Common Event Types. This pie graph displays the ten most frequently occurring events for the last 7 days.
 - [°] Each slice of the pie represents an event type. The legend on the left maps each slice color to an event and lists the actual number of events of that type.
 - The graph displays percent. Compared to the total number of occurrences for the top ten events, each slice displays the percent that belong to a specific event.
- **Mean Time-to-Resolution**. This bar graph displays the number of events generated in the last 24 hours, 7 days, 14 days, and 30 days, and their average resolution time.
 - ° The y-axis displays the number of events.
 - ° The x-axis displays the time span. There is a bar for 24 hours, 7 days, 14 days, and 30 days.
 - ° The red bars represent the actual number of events associated with the time-to-resolution.
 - The blue bars represent the average number of events associated with the time-to-resolution.
 - ° Mousing over a bar displays the number of events associated with the time-to-resolution.

Viewing Events by Appliance and Event Source

The **Event Statistics** page displays a graph of the number of events processed by a selected Database Server, Data Collector, or Message Collector.

The **Event Statistics** page displays the following information:

- Appliance. In the field in the upper left, select from the list of all Database Servers, Data Collectors, and Message Collectors.
- Event Type. In the next field on the upper left, select from the list of event types. The choices are:
 - ° API. The event was generated by an external API.
 - ° Dynamic. Event was generated by a monitoring application running on the device.
 - ° Email. The event was generated by an incoming email.
 - ° Internal. Event was generated by SL1.
 - ° Syslog. Event was generated from standard system log generated by device.
 - ° Trap. Event was generated by an SNMP trap.

The graph displays the average number of events processed by the selected appliance, for the selected duration.

- The y-axis displays the average number of events.
- The x-axis displays time. The increments vary depending upon the selected data type (from the **[Options]** menu) and the date range (from the **Date Range Selection** pane).

- Mousing over any point in any line displays the value at that time-point in the **Mouse-over** column in the **Data Table** pane.
- You can use your mouse to scroll the report to the left and right.

Chapter

7

Admin Notifier

Overview

This chapter describes the **Admin Notifier**, which alerts administrator users upon login to any issues on monitored SL1 appliances that could lead to an outage, such as the database running out of space.

After login, the Admin Notifier displays a banner if any of the filtered events are found so that you can take action on the issues immediately.

This chapter covers the following topics:

How Does the Admin Notifier Work?	263
What Issues Does the Admin Notifier Monitor?	264

How Does the Admin Notifier Work?

When certain events are present that could lead to a system outage, the Admin Notifier appears in SL1 for administrator users at login and persists as a banner at the top of the screen until no qualifying events are found. The Admin Notifier monitors your SL1 appliances for the events listed in the table in What Issues Does the Admin Notifier Monitor?

NOTE: If you are using the classic SL1 user interface, the Admin Notifier has additional functions. See *Admin Notifier in the Classic SL1 User Interface*.

After logging in to SL1, administrators will see the following modal if qualifying events are found:

System Warning You have 1 event which may lead to SL1 system failure. OK View Event

Click [OK] to continue or click [View Events] to go to the Events page to see a view filtered by admin events.

The System Warning banner will persist across the user interface until all of the qualifying events have been acknowledged.

To interact with the banner, you can click one of the buttons that appears on the banner:

- **Dismiss**. Hides the banner for the duration of your session or until another qualifying event is logged. If qualifying events are still present, the banner will reappear upon your next login.
- **Snooze**. Hides the banner for 15 minutes. If qualifying events are still present after 15 minutes, the banner will reappear.
- View Events. Opens the Events page with a filter applied that shows only the admin events.

Admin Notifier in the Classic SL1 User Interface

The System Warning banner appears in the classic user interface.

In the classic user interface, you can select events to add to or remove from the System Warning banner. On the **Event Policy Manager** page (Registry > Events > Event Manager), the **Select Action** menu on the Event Policy Manager page includes the following options: *Enable Admin Banner Warning* and *Disable Admin Banner Warning* for selected events.

The **Event Policy Manager** page also includes a new **Admin Warning** column that specifies whether or not an event will be included in the System Warning Banner.

What Issues Does the Admin Notifier Monitor?

The following table includes the events that might appear in the Admin Notifier, the Dynamic Application that triggers the event, the severity of the event, and references that can help you resolve the problem before it causes an outage. Knowledge Base Articles (KBA) are found on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).

Event Name	Dynamic Application	Severity	Reference
	Support: Database Configuration	Critical	Renew license. See the chapter on Licensing and Configuring an Appliance in the Installation manual or Knowledge Base Article 4978 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: DRBD Proxy License Expiration Eminent	Support: DRBD Proxy License Expiration	Critical	Renew license. See the chapter on Licensing and Configuring an Appliance in the Installation manual or Knowledge Base Article 4979 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
InnoDB Space: Critical Threshold	Support: InnoDB Size	Critical	See the chapter on Device Thresholds and Data Retention in the Device Management manual or Knowledge Base Article 49870 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: SL1 Config - Appliance Not Licensed	Support: SL1 Configuration	Critical	License your SL1 appliance. See the chapter on <i>Licensing</i> and Configuring an Appliance in the <i>Installation</i> manual or Knowledge Base Article 4981 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: MariaDB Config - InnoDB Force Recovery Non-Zero Value	Support: MariaDB Configuration	Critical	See Knowledge Base Article 4982 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Poller: File system usage exceeded (critical) threshold	Internal	Critical	See Knowledge Base Article 4983 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: Appliance Validation Not Monitored	Support: Appliance Validation	Major	Discover all appliances as devices.
Support: Appliance Validation Minimum AIO Requirements Not Met	Support: Appliance Validation	Major	See Knowledge Base Article 4984 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).

Event Name	Dynamic Application	Severity	Reference
Support: Appliance Validation Minimum AP Requirements Not Met	Support: Appliance Validation	Major	See Knowledge Base Article 4985 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: Appliance Validation Minimum DB Requirements Not Met	Support: Appliance Validation	Major	See Knowledge Base Article 4986 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: Appliance Validation Minimum DC Requirements Not Met	Support: Appliance Validation	Major	See Knowledge Base Article 4987 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: Appliance Validation Minimum MC Requirements Not Met	Support: Appliance Validation	Major	See Knowledge Base Article 4988 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: API Message Backlog Has Exceeded Threshold	Support: Async Message Backlog Performance	Major	See Knowledge Base Article 4989 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: Syslog Message Backlog Has Exceeded Threshold	Support: Async Message Backlog Performance	Major	See Knowledge Base Article 4990 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: Trap Message Backlog Has Exceeded Threshold	Support: Async Message Backlog Performance	Major	See Knowledge Base Article 4991 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: Cluster Resource Template Outdated	Support: Cluster Configuration	Major	See Knowledge Base Article 4992 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: DNS Resolution - Invalid Response	Support: Database Configuration	Major	See Knowledge Base Article 4993 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).
Support: SL1 will run out of space in less than 14 days	Support: DB Space Estimator	Critical	See Knowledge Base Article 4994 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).

Event Name	Dynamic Application	Severity	Reference	
Mail Backlog: Critical	Support: Mail Backlog	Critical	See Knowledge Base Article 4995 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).	
Support: MariaDB Config - File per table	Support: MariaDB Configuration	Critical	See Knowledge Base Article 4996 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).	
Support: MariaDB Connections High - Critical	Support: MariaDB Performance	Critical	See Knowledge Base Article 4997 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).	
Support: High Rows Behind High	Support: Rows Behind	Critical	See Knowledge Base Article 4998 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).	
Support: Medium Rows Behind High	Support: Rows Behind	Major	See Knowledge Base Article 4999 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).	
Siteconfig Check: Differing Variable	Support: Siteconfig Check	Critical	See Knowledge Base Article 5000 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).	
Siteconfig Check: Missing Variable	Support: Siteconfig Check	Critical	See Knowledge Base Article 5001 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).	
Support: SL1 Config - Bad Timezone	Support: SL1 Configuration	Critical	Reset timezone to UTC. See Knowledge Base Article 5002 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).	
Support: SL1 Config - Pause file detected	Support: SL1 Configuration	Critical	The system is not currently collecting any information. See Knowledge Base Article 5003 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).	
Support: Out of Memory - Process Has Been Killed	Syslog	Major	See Knowledge Base Article 5004 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).	
Support: MariaDB Error	Syslog	Major	See Knowledge Base Article 5005 on the ScienceLogic Support website (https://support.sciencelogic.com/s/knowledge).	

Chapter

8

Diagnostic Tools

Overview

This chapter describes some diagnostic tools for troubleshooting and diagnosing problems in SL1.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon
- To view a page containing all of the menu options, click the Advanced menu icon (...).

This chapter covers the following topics:

Viewing Information About ScienceLogic Processes	267
Debugging a Process and Viewing Debug Logs	273
Viewing Information About Unhandled Exceptions	274
Viewing the Output of the System Status Script	277
Viewing the Database Tables on the Database Server	277
Disabling Normalization, Re-Enabling Normalization, and Backfilling Raw Data	279
Enable Logging for Data Pull Storage Objects	282
Controlling Log Settings	283

Viewing Information About ScienceLogic Processes

The **Process Manager** page allows you to view a list of ScienceLogic processes and optionally define parameters for those processes. These processes gather, manipulate, and publish the data used in SL1.

CAUTION: ScienceLogic recommends that you do not edit the values in this page without first consulting ScienceLogic. Incorrect values can severely disrupt ScienceLogic platform operations.

ScienceLogic processes fall into three scheduling categories or Frequencies:

- Asynchronous. The process is launched in response to a system event or user request.
- Scheduled. The process is launched on a regular schedule.
- Always. The process always runs while SL1 is running.


SL1 performs many tasks in parallel:

- Through a modular design, allowing functions to be distributed to multiple processing platforms.
- Through multi-processing, where multiple instances of a process run simultaneously.

Viewing the List of ScienceLogic Processes

To view the list of process in the **Process Manager** page:

1. Go to the **Process Manager** page (System > Settings > Admin Processes).



- 2. The **Process Manager** page displays information about each ScienceLogic process. The **Process Manager** page displays the following for each process:
 - **Process Name**. Name of the process.
 - Program File. Name of the executable file associated with the process.
 - Frequency. Frequency with which the platform launches the process. Possible values are:

- ^o Asynchronous. The process is launched in response to a system event or user request.
- Always. The process always runs while SL1 is running.
- ° Scheduled. The process runs at intervals ranging from 1 Minute to Daily.
- Runtime Offset. This field applies only to scheduled processes and allows the platform to stagger the launch of a process. The field specifies the number of minutes after the default scheduled time to execute a process. The default scheduled time at which processes are initially executed is midnight UTC. So if a process has a Frequency of 5 Minutes and the Runtime Offset is set to "2", the process will execute at two minutes past UTC midnight, seven minutes past UTC midnight, 12 minutes past UTC midnight, 17 minutes past UTC midnight, etc. Choices range from 0–1439.
- Async Throttle. This field applies only to asynchronous processes. This field indicates the number of jobs per process that can run simultaneously.
- **Batch Factor**. This field applies only to scheduled processes and determines how many multithreaded child processes are spawned on each execution of the process.
 - number of tasks a process is responsible for completing/**Batch Factor** = number of child processes that will be spawned
 - The number of tasks is typically determined by the number of devices the process is collecting data from
 - The maximum number of child processes is limited by the number of CPUs installed in the SL1 appliance that runs the process.

NOTE: *Batch Factor* defines the maximum number of worker processes or child processes. This value has precedence over the value specified in the section of this manual on *Tuning Collector Groups in the silo.conf File*.

• *Time Factor*. Determines how long the process can run before being stopped by the process manager. This setting only applies to asynchronous processes and scheduled processes. For asynchronous processes, this is the length of time an instance of the process can run. For scheduled processes, the value of *Time Factor* is used to calculate *Run Length*.

(Frequency * Time Factor) + Frequency = Run Length

For example, suppose a process runs every 15 minutes (as specified in the *Frequency* field). A *Time Factor* of 2 means the process is allowed to run for 45 minutes. A *Time Factor* of 0 means the process is allowed to run for 15 minutes.

- **Run Length**. Specifies how long the process can run before being stopped by the process manager. This number is based on the **Time Factor** for the process.
- State. Current operational state of the process. Possible values are:
 - ° Enabled. Process can run.
 - Disabled Process cannot run

- **Debug**. Specifies whether debugging information is enabled for the process. For more details on debugging a process, see the section **Debugging a Process**.
- ID. Unique numeric ID assigned to each process by SL1.
- Edited By. Date and time the process settings were last edited.
- Edit Date. Date and time the process settings were last edited.

Searching and Filtering the List of ScienceLogic Processes

The **Process Manager** page includes 13 filters, in the top row in the list of processes. You can specify one or more parameters to filter the display of processes. Only processes that meet all the filter criteria will be displayed in the **Process Manager** page.

You can filter by one or more of the following parameters. The list of processes is dynamically updated as you select each filter.

- For each filter except *Edit Date*, you must enter text to match against. SL1 will search for processes that match the text, including partial matches. Text matches are not case-sensitive. You can use the following special characters in each filter:
 - , (comma). Specifies an "or" operation. For example:
 "dell, micro" would match all values that contain the string "dell" OR the string "micro".
 - & (ampersand). Specifies an "and" operation. For example:
 "dell & micro" would match all values that contain the string "dell" AND the string "micro".
 - ! (exclamation mark). Specifies a "not" operation. For example:
 "!dell" would match all values that do not contain the string "dell".
- Process Name You can enter text to match, including special characters (comma, ampersand, and exclamation mark), and the Process Manager page will display only processes that have a matching name.
- Program File. You can enter text to match, including special characters (comma, ampersand, and
 exclamation mark), and the Process Manager page will display only processes that have a matching
 program file.
- Frequency. You can enter text to match, including special characters (comma, ampersand, and
 exclamation mark), and the Process Manager page will display only processes that have a matching
 frequency number.
- Runtime Offset. You can enter text to match, including special characters (comma, ampersand, and
 exclamation mark), and the Process Manager page will display only processes that have a matching
 runtime offset.
- Async Throttle. You can enter text to match, including special characters (comma, ampersand, and
 exclamation mark), and the Process Manager page will display only processes that have a matching
 throttle number.
- **Batch Factor**. You can enter text to match, including special characters (comma, ampersand, and exclamation mark), and the **Process Manager** page will display only processes that have a matching batch factor.

- *Time Factor*. You can enter text to match, including special characters (comma, ampersand, and exclamation mark), and the **Process Manager** page will display only processes that have a matching time factor.
- Run Length. You can enter text to match, including special characters (comma, ampersand, and
 exclamation mark), and the Process Manager page will display only processes that have a matching run
 length.
- **State**. You can enter text to match, including special characters (comma, ampersand, and exclamation mark), and the **Process Manager** page will display only processes that have a matching state ("Enabled" or "Disabled").
- **Debug**. You can enter text to match, including special characters (comma, ampersand, and exclamation mark), and the **Process Manager** page will display only processes that have a matching debug state ("Enabled" or "Disabled").
- ID. You can enter text to match, including special characters (comma, ampersand, and exclamation mark),
 and the Process Manager page will display only processes that have a matching ScienceLogic process ID.
- *Edited By*. You can enter text to match, including special characters (comma, ampersand, and exclamation mark), and the **Process Manager** page will display only processes that have a matching "created by" or "edited by" value.
- *Edit Date*. You can select from a list of time periods. The **Process Manager** page will display only processes that have been created or edited within that time period:
 - ° All. Display all processes that match the other filters.
 - [°] Last Minute. Display only processes that have been edited within the last minute.
 - ^o Last Hour. Display only processes that have been edited within the last hour.
 - ^o Last Day. Display only processes that have been edited within the last day.
 - ^o Last Week. Display only processes that have been edited within the last week.
 - ^o Last Month. Display only processes that have been edited within the last month.
 - ^o Last Year. Display only processes that have been edited within the last year.

Editing the Parameters of a ScienceLogic Process

To view details about a specific process or edit the settings for a specific process:

CAUTION: ScienceLogic recommends that you do not edit the values in this page without first consulting ScienceLogic. Incorrect values can severely disrupt ScienceLogic platform operations.

- 1. Go to the **Process Manager** page (System > Settings > Admin Processes).
- 2. In the **Process Manager** page, find the process you want to edit. Click its wrench icon (**).
- 3. The **Process Editor** page appears and is populated with values from the selected process.

- Process Name. Name of the process. This field is read-only and cannot be changed.
- **Program File**. Name of the executable file associated with the process. This field is read-only and cannot be changed.
- Operating State. Current operational state of the process. Specifies whether the process is enabled and able to run. Select from the drop-down list. The choices are:
 - Enabled. Process can run.
 - ° Disabled. Process cannot run.
- **Debug Mode**. Enables or disables debugging information for a process. For more details on debugging a process, see the section **Debugging a Process**.

NOTE: You cannot enable debug mode for the process Message Collection: SNMP Trap.

- *Frequency*. This field appears only for scheduled processes and asynchronous processes. Specifies the frequency with which SL1 launches the process. Select from the drop-down list. The choices are:
 - ° Asynchronous. For asynchronous processes, this is the only available option. You cannot edit the frequency.
 - ° Scheduled. For scheduled processes, you can edit the frequency. You can select from intervals ranging from 1 Minute to Daily.

NOTE: If a process is set to a frequency of Asynchronous or Always, this field cannot be changed. If a process is set to a time interval, this field cannot be changed to Asynchronous or Always.

- **Async Throttle**. This field appears only for asynchronous processes. This field indicates the number of jobs per process that can run simultaneously. This setting only applies to asynchronous processes.
- Runtime Offset. This field only appears for scheduled processes. This field allows SL1 to stagger the launch of a process. The value specified in this field specifies minutes after the default scheduled time for a process. For example, if a process has a Frequency of 5 Minutes and the Minute Offset is set to "2", the process will execute at two minutes past the hour, seven minutes past the hour, 12 minutes past the hour, 17 minutes past the hour, etc. Choices range from 0–1439.
- **Batch Factor**. This field applies only to scheduled processes and determines how many multithreaded child processes are spawned on each execution of the process.
 - number of tasks a process is responsible for completing/**Batch Factor** = number of child processes that will be spawned
 - The number of tasks is typically determined by the number of devices the process is collecting data
 - The maximum number of child processes is limited by the number of CPUs installed in the SL1 appliance that runs the process.

NOTE: *Batch Factor* defines the maximum number of worker processes or child processes. This value has precedence over the value specified in the section of this manual on *Tuning Collector Groups in the silo.conf File*.

- *Time Factor*. This field appears only for scheduled processes and asynchronous processes. This field determines how long a process can run before being killed.
 - For scheduled processes, SL1 uses the formula (Frequency * Time Factor) + Frequency.

For example, suppose a process runs every 15 minutes. A factor of 2 means the process is allowed to run for 45 minutes. Factor of 0 means process is allowed to run for 15 minutes.

- ° For asynchronous processes, SL1 simply uses the value in this field as the number of minutes a process can run. This field does not appear for processes that are always running.
- Appliance Types. Specifies the appliance types where the process is allowed to run.

NOTE: All changes to the settings in the **Process Manager** page are logged in the **Audit Logs** page (System > Monitor > Audit Logs). The associated log entry will specify the user who altered a process, the process that was altered, and which settings for the process were changed.

4. If you make changes to one or more fields, click the [Save] button to save your changes.

Debugging a Process and Viewing Debug Logs

When you debug a process, you tell SL1 to use verbose logging for that process. You can then view SL1 log file to view the logs.

There might be circumstances where you have narrowed down a problem to a specific ScienceLogic process (for example, based on an error message or event). When this happens, you might find it helpful to turn on debugging for that process and view the debug logs.

WARNING: ScienceLogic recommends that you enable the debug option only while troubleshooting a problem and that you then immediately turn off debugging when you have completed troubleshooting. Don't leave the debug option enabled during normal operation of SL1. When you turn on debugging, SL1 will run significantly more slowly.

NOTE: You cannot enable debug mode for the process Message Collection: SNMP Trap.

To enable the debug option for a process:

- 1. In the **Process Manager** page, find the process you want to edit. Select its wrench icon (🎤).
- 2. The **Process Editor** page appears and is populated with values for the selected process.
- 3. Edit the following field:
 - **Debug**. Enables or disables debugging information for a process. Select *Enabled*.
- 4. Click the [Save] button in the Process Editor page.
- 5. Log in to the console of the appliance where the process is running. Alternately, you can use SSH to open a shell session on the appliance. Log in as **em7admin** with the appropriate password.

TIP: To view a list of IP addresses for all appliances in your system, go to the **Appliance Manager** page (System > Settings > Appliances).

6. If the process you are debugging is a process that has a *Frequency* of *Always*, you must restart the process to make it pick up the new debug status (enabled). To restart the process, enter the following at the shell prompt:

```
sudo service process name restart
```

For example, if you were debugging the process for the event engine, you would enter:

```
sudo service em7_event restart
```

- 7. Navigate to the directory /var/log/em7. View the file silo.log. The most recent entries will be posted at the end of the file.
- 8. After you have finished troubleshooting the process, remember to disable debugging. If the process has a **Frequency** of Always, you must restart the process to make it pick up the new debug status (disabled).

Viewing Information About Unhandled Exceptions

An **exception** specifies that something happened "out of the norm" that is preventing the software from executing the next step. Exceptions are a specific type of error, usually the result of invalid input, missing input, or a network error that prevents communication between software modules. For most exceptions, SL1 will handle the exception by logging a specific error in the System Logs and will continue to run the process. However, **if the platform does not handle the exception**, the process will stop running, and SL1 will generate an error message describing **the unhandled exception**.

Viewing the List of Unhandled Exceptions

To view the list of unhandled exceptions for all appliances:

- 1. Go to the **Unhandled Exceptions** page (System > Monitor > Unhandled Exceptions).
- 2. The Unhandled Exceptions page displays the following for each unhandled exception:



- Exception Filename. Full path of the file where the exception occurred.
- Line. Line number of the line in the file where the exception occurred.
- Exception Information. Error message associated with the exception.
- First Occurrence. Date and time of the first occurrence of the exception.
- Last Occurrence. Date and time of the last occurrence of the exception.
- Count. Number of times the exception has occurred.

Searching and Filtering the List of Unhandled Exceptions

The **Unhandled Exceptions** page includes six filters. You can filter the list of exceptions by one or multiple of the following parameters: exception filename, line number, exception descriptions, first occurrence, last occurrence, and count. Only exceptions that meet all the filter criteria will be displayed in the **Unhandled Exceptions** page.

You can filter by one or more of the following parameters. The list of devices is dynamically updated as you select each filter.

- For the first three filters, you must enter text to match against. SL1 will search for exceptions that match the
 text, including partial matches. Text matches are not case sensitive. You can use the following special
 characters in each filter:
 - Specifies an "or" operation. For example:

"dell, micro" would match all values that contain the string "dell" OR the string "micro".

! Specifies a "not" operation. For example:

"!dell" would match all values that do not contain the string "dell".


- Exception Filename. You can enter text to match, including special characters, and the Unhandled Exceptions page will display only exceptions that have a matching filename.
- Line. You can enter text to match, including special characters, and the **Unhandled Exceptions** page will display only exceptions that have a matching line number.
- Exception Information. You can enter text to match, including special characters, and the Unhandled Exceptions page will display only exceptions that have a matching description.
- *First Occurrence*. Only those exceptions that match all the previously selected fields and have the specified first occurrence date will be displayed. The choices are:
 - ° All. Display exceptions with all first occurrence dates.
 - ^o Last Minute. Display only exceptions that first occurred within the last minute.
 - ^o Last Hour. Display only exceptions that first occurred within the last hour.
 - ^o Last Day. Display only exceptions that first occurred within the last day.
 - Last Week. Display only exceptions that first occurred within the last week.
 - ^o Last Month. Display only exceptions that first occurred within the last month.
 - ^o Last Year. Display only exceptions that first occurred within the last year.
- Last Occurrence. Only those exceptions that match all the previously selected fields and have the specified last occurrence date will be displayed. The choices are:
 - ° All. Display exceptions with all last occurrence dates.
 - Last Minute. Display only exceptions that last occurred within the last minute.
 - ^o Last Hour. Display only exceptions that last occurred within the last hour.
 - ^o Last Day. Display only exceptions that last occurred within the last day.
 - ^o Last Week. Display only exceptions that last occurred within the last week.
 - ^o Last Month. Display only exceptions that last occurred within the last month.
 - ^o Last Year. Display only exceptions that last occurred within the last year.
- **Count**. You can enter text to match, including special characters, and the **Unhandled Exceptions** page will display only exceptions that have a matching count number.

Saving the Unhandled Exception to the Local Computer

You can save the full text of the unhandled exception to a file on your local computer. You can then view the text in a text editor.

To save the full text of the unhandled exception to a file:

- 1. Go to the **Unhandled Exceptions** page (System > Monitor > Unhandled Exceptions).
- 2. In the **Unhandled Exceptions** page, find the exception you want to save to a file. Click its green diskette icon (■).



3. When prompted, you can either immediately view the text file with a text editor or save the file to your local computer for viewing later.

Viewing the Output of the System Status Script

For each Database Server, Data Collector, and Message Collector, you can view the output of the system status script for that appliance. To do this:

- 1. Go to the **Appliance Manager** page (System > Settings > Appliances).
- 2. Locate the Database Server, Data Collector, or Message Collector that you want to view diagnostic information about.
- 3. Click on its magnifying-glass icon () to view the output of the system status script for that appliance.

Viewing the Database Tables on the Database Server

In some circumstances, you might need to view the contents of the database tables (the permanent tables are stored on the Database Server). There are two ways to do this:

- Using the built-in Database Tools in the **Database Tool** page (System > Tools > DB Tool).
- Using the link to the phpMyAdmin interface in the Appliance Manager page (System > Settings > Appliances).


Accessing the Database Tool

The **Database Tool** page allows administrators to view information about the internal ScienceLogic databases and run SQL queries against those internal databases.

CAUTION: Contact ScienceLogic for details on using the **Database Tool** page and troubleshooting databases. Do not make changes to the database or run the Optimizer Tool without guidance from ScienceLogic.

To access the database tool:

1. Go to the **Database Tool** page (System > Tools > DB Tool).



- 2. To run an SQL query from the Database Tool page, enter values in the following fields:
 - Select Database. Select a database to query.
 - **SQL Query**. Enter an SQL query to execute against the selected database. For more information on each database and each table, use the options in the **[Actions]** menu.

NOTE: You must be familiar with SQL and know how to build a proper query before using the **Database Tool** page.

- 3. Click the **[Go]** button to execute the guery.
- 4. The results from the guery are displayed in the pane at the bottom of the page.
- 5. To view the reports about the a database(s), click the [Actions] menu. The following options are available:

- *Engines*. Displays status information about the server's storage engines. For each engine, the modal page displays a description of the engine, whether the engine is supported by SL1, and whether or not the engine supports transactions, XA, and save points.
- Global Status. Displays a list of global variables used in the database tables and the current value for each global variable.
- InnoDB Variables. Displays a list of InnoDB variables used in SL1 and the value for each variable.
- Open Tables. Displays a list of currently open tables. For each table, the modal page displays the
 database name, table name, whether the table is currently in use, and whether the table is currently
 locked.
- Optimizer Tool. Leads to the Database Optimizer Tool page, where you can choose to optimize, repair, check, flush, or analyze all the tables in a database.

CAUTION: Contact ScienceLogic for details on using the **Database Optimizer Tool** page. Do not run the Optimizer Tool without guidance from ScienceLogic.

- **Processes**. Displays a list of running threads on the databases and tables. For each process, the modal page displays the connection ID, the database user who issued the statement, the host name of the client that issued the statement, the affected database, the command, the time in seconds that the thread has been in its current state, the state of the thread, and any available description of the process.
- Table Status. Displays the status of each database table in the platform. For each table, the modal page displays the table name, the database engine, database version, row format, number of rows, average row-length, length of the data file, maximum length of the data file, length of the index file, number of allocated but unused bytes, the next auto-increment value, the create time for the table, the update time for the table, the table's character set and collation, the live checksum value, options used with CREATE TABLE, and any comments.
- Variables. Displays a list of all database system variables used in SL1 and the value of each variable.

Disabling Normalization, Re-Enabling Normalization, and Backfilling Raw Data

ScienceLogic does not recommend stopping normalization on Data Collectors. However, there are rare occasions where ScienceLogic Customer Support might ask you to disable normalization as part of troubleshooting.

To disable normalization:

- 1. Either go to the console of the Database Server or use SSH to access the Database Server.
- 2. Log in as user em7admin with the appropriate password.
- 3. Type the following at the command line:

sudo visilo

This is the file where users can customize the silo.conf file. In step #6, you will execute a command that sends these changes to the system silo.conf file.

4. In the LOCAL section, add the following line:

```
rollups disabled=ON
```

- 5. Save your changes and exit the file (:wq).
- 6. Restart the data collection process to ensure they receive the change. Type the following at the command line:

```
sudo service em7_hfpulld restart

sudo service em7_lfpulld restart

sudo service em7_mfpulld restart
```

To re-enable normalization and normalize data that was collected while normalization was disabled:

- 1. Either go to the console of the Database Server or use SSH to access the Database Server.
- 2. Log in as user em7admin with the appropriate password.
- 3. Type the following at the command line:

```
sudo visilo
```

4. In the LOCAL section, add the following line:

```
rollups_disabled=OFF
```

- 5. Save your changes and exit the file (:wq).
- 6. Restart the data collection process to ensure collectors receive the change. Type the following at the command line:

```
sudo service em7_hfpulld restart

sudo service em7_lfpulld restart

sudo service em7_mfpulld restart
```

7. At the command line, type the following to normalize the data that was collected while normalization was disabled:

```
[/opt/em7/backend/data_normalizer_backfill.py --database, <database>
--dids <[device IDs]> --start <start date> --end <end date> --workers
<number of workers>
```

NOTE: To get help, at the shell prompt, type "/opt/em7/backend/data normalizer backfill.py -h".

where:

- --database database. Specifies the database that you want to backfill with normalized data. The choices are:
 - ° data avail. Table that stores normalized data for availability.
 - ° data cv. Table that stores normalized data for Web Content policies.
 - ° data dns. Table that stores normalized data for DNS policies.
 - data email. Table that stores normalized data for Email Round-Trip policies.
 - ° data ports. Table that stores normalized data for TCP-IP Ports policies.
 - ° data procs. Table that stores normalized data for System Processes policies.
 - ° data services. Table that stores normalized data for Windows Services policies.
 - ° data storage. Table that stores normalized data for file systems.
 - ° data tv. Table that stores normalized data for SOAP/XML Transaction policies.
 - dynamic_app_data_appID. Table that stores normalized data for a Dynamic Application. Specify the application ID for the Dynamic Application.
- --dids device IDs. Specifies the device ID of the device or devices for which you want to normalize data.
 - ° You can specify a single device ID.
 - You can specify multiple device IDs, separated by commas and surrounded by square brackets.
 - ° If you do not specify any device IDs, SL1 will normalize the specified data for all devices in your system.
- --start start date. The timestamp that specifies the data to normalize. Raw data with a time stamp at this time or later will be normalized. SL1 will normalize data starting with this timestamp and ending with the end-date timestamp.
 - ° Specify the timestamp in the format yyyy-mm-dd hh:mm:ss, using a 24-hour clock. Surround the timestamp with single quotes.
- --end end date. The timestamp that specifies the data to normalize. Raw data with a time stamp at
 this time or earlier will be normalized. SL1 will normalize data starting with the start-date timestamp
 and ending with this timestamp.
 - ° Specify the timestamp in the format yyyy-mm-dd hh:mm:ss, using a 24-hour clock. Surround the timestamp with single quotes.
- --workers workers. Number of worker processes to assign to this task. This field is optional. Please consult ScienceLogic Customer Support for suggestions on worker processes.

For example:

```
python /opt/em7/backend/data_normalizer_backfill.py --database
dynamic_app_data_16 --start '2017-10-01 00:00:00' --end '2017-10-10
00:00:00' --workers 10
```

This command normalizes raw data collected by the Dynamic Application with an application ID of 16, associated with all subscriber devices (no device IDs specified, so defaults to "all devices"), and that was collected between midnight on October 1, 2017 and midnight on October 10, 2017. The data_normalizer_backfill.py code uses ten worker processes to perform the normalization.

Enable Logging for Data Pull Storage Objects

To investigate missed polls or slow database queries, you can temporarily enable logging for data pull storage objects. After you complete the diagnostics, you must disable logging for data pull storage objects, because the logging can affect the performance of data pull.

Enable

To enable logging for data pull storage objects:

- 1. Either go to the console of the Database Server or use SSH to access the Database Server.
- 2. Log in as an administrator.
- 3. At the shell prompt, enter the following:

```
sudo visilo
```

4. In the silo.conf file, add the following lines:

```
[DATAPULL]
log_storage_object_stats = 1
```

- 5. Save your changes to the file (:wq).
- 6. You must restart the data collection processes to ensure they receive the change. To do this, enter the following at the shell prompt:

```
sudo service em7_hfpulld restart

sudo service em7_lfpulld restart

sudo service em7_mfpulld restart
```

Disable

When you have completed your diagnostics, disable logging for data pull storage objects. To do this:

- 1. Either go to the console of the Database Server or use SSH to access the Database Server.
- 2. Log in as an administrator.
- 3. At the shell prompt, enter the following:

```
sudo visilo
```

4. In the silo.conf file, edit the following:

```
[DATAPULL]

log storage object stats = 0
```

- 5. Save your changes to the file (:wq).
- 6. You must restart the data collection processes to ensure they receive the change. To do this, enter the following at the shell prompt:

```
sudo service em7_hfpulld restart

sudo service em7_lfpulld restart

sudo service em7_mfpulld restart
```

Controlling Log Settings

In rare cases, you may need to modify log levels or suppression of certain logs in SL1, usually at the request of ScienceLogic Customer Support. To do so, you will navigate to the **PHP Developer Logs** page (System > Tools > PHP Developer Logs). This section describes the options included on the PHP Developer Logs page.

NOTE: This page is is only available for Administrator-level users in SL1.

Setting UI Developer Log Levels

When configuring logging on an appliance, you must specify a log level. The log level controls the types of messages that are written to the user interface log file (em7php.log). Each type of message has an associated number; the log level is the sum of all enabled messages. The numbers and associated message types are:

Controlling Log Settings 283

- 1. Critical
- 2. Error
- 4. Warning
- 8. Info
- 16. Debug
- 32. Trace

To determine the log level, sum the numbers associated with each type of message you want to enable. For example, if you want to enable Critical, Error, and Warning messages, you would sum one, two, and four to get a log level value of seven.

Setting UI/REST MySQL Query Log Levels

The UI/REST MySQL Query Log Levels settings let you specify the log level for the mysqli.log file. This log file collects every PHP-based call to MySQL and includes general information about the query. Determine the granularity of data you want and select one or more checkboxes.

- Error
- Warning
- Info (non-error)

In addition, if you select the **Request URI** option, the mysqli.log file will include the request URI.

Configuring Advanced Log Settings

In the Advanced Settings section, you can configure the suppressions and the date/time format you want to use:

- Suppression List. This list acts as a bitmask to log entries. For example, to suppress all entries for css-em7, you would enter "css.em7::127", where 127 is the sum of all possible log levels. You can specify multiple suppressions in the list, separated by commas.
- **Datetime Format**. Specifies a user-defined date format that will be used for 5 system logs. You can use any date variables supported by the PHP date function in this field.

NOTE: Seconds and milliseconds are always appended to the date/time stamp.

Include IP in log filenames. Select this option to add the IP address from which the user is logged in to
the name of each log file.

Downloading Logs from the PHP Developer Logs page

To download the logs from the PHP Developer Logs page (System > Tools > PHP Developer Logs):

- 1. Go to the **PHP Developer Logs** page (System > Tools > PHP Developer Logs
- 2. Under **Download Logs**, select a logfile to download.

NOTE: This page is is only available for Administrator-level users in SL1.

COUNT(*)	module	name	cug_name
46	4	emanbwl013	PFZR_IRL_CG
16	18	emapuul021	PFZR_PUUR_CG
16	22	emarinl014	PFZR_IRL_CG

Controlling Log Settings 285

Chapter

9

Changing Passwords

Overview

This chapter describes how to change every administrator password used in SL1.

NOTE: Appliances installed as an AWS EC2 instance have the "root" operating system account disabled by default. During the setup process, the user "ec2-user" is automatically added to the operating system configuration. The ec2-user account can be used to perform administrative tasks that require SSH command-line access. The ec2-user account is permitted to perform all operating system commands using the "sudo" command without a password.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon (=).
- To view a page containing all of the menu options, click the Advanced menu icon (···).

This chapter covers the following topics:

Disabling phpMyAdmin	287
Changing the Password for the Default User Interface Account	287
Changing the Password for the Default Console User	288
Changing the Password for the Web Configuration Utility	288
Changing Database Passwords	288

Disabling phpMyAdmin

The phpMyAdmin interface provides a web interface for viewing and managing MySQL databases. By default, you can log in to the Database Server using the phpMyAdmin interface to view and manage the MySQL databases on all Database Servers, Data Collectors, and Message Collectors in the system.

To disable phpMyAdmin, you must disable the service and then disable the ports on which the service runs. To do this:

- 1. If you are using a distributed system, either go to the console of the Database Server or use SSH to access the Database Server. Open a shell session on the server. Log in as an administrator.
- 2. If you are using an All-In-One Appliance, either go to the console of the All-In-One Appliance or use SSH to access the All-In-One Appliance. Open a shell session on the server. Log in as an administrator.

NOTE: For details on enabling and using SSH, see the manual **System Administration**. For details and warnings about root access and instructions on how to make root access secure, see the manual **System Administration**.

3. Edit the file /etc/siteconfig/firewalld-rich-rules.siteconfig:

```
sudo vifirewalld
```

4. Add the following lines:

```
rule service name="phpmyadmin" reject\
rule port port="8008" protocol="tcp" reject
```

5. Save your changes and exit the file (:wq).

Changing the Password for the Default User Interface Account

To change the password used by the **em7admin** user account to access the user interface:

- 1. Go to the **User Accounts** page (Registry > Accounts > User Accounts).
- 2. Click the wrench icon () for the em7admin user. The **Account Permissions** page appears.
- 3. Enter the new password in the **Change Password** field.
- 4. Re-type the new password in the Confirm Password field.

TIP: You can use the following special characters in the *em7admin* user account password:

```
+ _)(*&^ %$#@!|}{":?><=-\][';/.,
```

- 5. Click the [Save] button. A pop-up window appears, asking you to confirm the change.
- 6. Click [OK]. The message "Password Saved" is displayed.

Changing the Password for the Default Console User

To change the password for the default administrative user **em7admin** for console logins and SSH access:

- 1. Either go to the console of the SL1 appliance or use SSH to access the server.
- 2. Log in as user **em7admin** with the current password.
- 3. At the shell prompt, type the following:

passwd

4. When prompted, type and re-type the new password.

TIP: You can use the following special characters in the *em7admin* user account password:

Changing the Password for the Web Configuration Utility

If you want to change the password for the Web Configuration Utility on all SL1 appliances, you must log in to the Web Configuration Utility on each node or appliance and perform the steps in this section.

You cannot change the username for the Web Configuration Utility. The username remains em7admin.

To change the password for the Web Configuration Utility:

- 1. Log in to the Web Configuration Utility. The Configuration Utilities page appears.
- 2. Click the [Device Settings] button. The Settings page appears.
- 3. In the **Settings** page, type the following:
 - Web Config Password (change only). Type the new password.
 - Confirm Web Config Password. Type the new password again.
- 4. Click [Save].
- 5. Perform steps 1-4 for each node or appliance for which you want to change the password for the Web Configuration Utility.

Changing Database Passwords

The following SL1 appliances include a database instance:

- All-In-One Appliances
- Database Servers
- Data Collectors
- Message Collectors

By default, SL1 appliances use the following user accounts to access appliance databases:

- ap_user. This user is used by the user interface to access the database on a Database Server or All-In-One
 Appliance. This user account exists only on the Administration Portal and does not exist by default on Data
 Collectors and Message Collectors. By default, this user has the user name apuser and the password
 apuser.
- *clientdbuser*. For SL1 version 11.3.0 and later, this user is the default database user for MariaDB. This user has the same password as em7admin and root, and the password is set during the initial installation. The *clientdbuser* does not have super privileges.
- **dbuser**. For versions of SL1 before 11.3.0, this user is used by ScienceLogic platform processes to access the database instance on all appliances. By default, this user has the user name **root**.

To change the password for the **ap** user account, you must:

1. Configure a new password for the Administration Portal using the Web Configuration Utility for the Administration Portal.

To change the password for the *clientdbuser* or the *dbuser* account, you must:

- 1. Configure a new password in the database instance.
- 2. Configure SL1 to use the new password.

WARNING: Exercise caution when manipulating MySQL user accounts. Do not use these procedures unless you are confident and know how to undo changes, should something go wrong.

Configuring a New Password on Collector Appliances

Perform the following steps to change the password for a user on a Collector:

- 1. Either go to the console of the Database Server, All-In-One Appliance, Data Collector, or Message Collector or use SSH to access the server in CLI mode.
- 2. Log in as **em7admin** with the appropriate password.
- 3. Run the following command to launch the MySQL prompt:

```
silo mysql
```

4. From the MySQL prompt, change the root password by running the following SQL query:

```
SET PASSWORD FOR CURRENT_USER() = PASSWORD('new password');
```


5. To effect the change immediately, run the following SQL query:

```
MariaDB [(none)]> FLUSH PRIVILEGES;
```

6. Ensure you can access the database with the new password. Exit the MySQL interface, and test by running the following command, entering the new password when prompted:

```
mysql -u root -p
```

- 7. Edit the /etc/silo.conf file and change the **dbpasswd** variable to the new password. See **Editing** Silo.Conf for assistance.
- 8. From the SL1 interface, go to the **Appliances** page (System > Settings > Appliances) and click the wrench icon () on the Collector. Then update the DB User and DB Password to the new values.



9. Confirm in the Collector Status page (System > Monitor > Collector Status) that the Collector is available.

Editing Silo.Conf

- 1. Either go to the console of the SL1 appliance or use SSH to access the SL1 appliance.
- 2. Open a shell session on the server.
- 3. Type the following at the command line:

```
sudo visilo
```

- 4. Edit the value assigned to *clientdbuser* or *dbuser* and to *ap_user*. Assign the value you defined in the section *Configuring a New Password in the Database Instance*.
- 5. Save and close the file (:wq).

Updating the master.system_settings_licenses Table

To update the master.system_settings_licenses table after you have changed the root password on a Data Collector or Message Collector:

- 1. Go to the **Appliance Manager** page (System > Settings > Appliances).
- 2. Locate the Data Collector or Message Collector in the list of appliances. Note the value in the *ID* column for the Data Collector or Message Collector.

- 3. Go to the **Database Tool** page (System > Tools > DB Tool).
- 4. Enter the following in the **SQL Query** field, replacing <new password> with the new password and <ID value of Collector> with the value you noted in step 2:

```
UPDATE master.system_settings_licenses SET db_user='root', db_
pass=<new password> WHERE id=<ID value of Collector>;
```

If you want to update all Data Collectors and Message Collectors with the same password, enter the following in the SQL Query field, replacing < new password> with the new password:

```
UPDATE master.system_settings_licenses SET db_user='root', db_
pass='<new password>' WHERE function in (5,6);
```

5. Click the [Go] button.

Changing the MySQL Root Password on Database Appliances

To change the MySQL root password on database appliances:

- 1. Either go to the console of the Database Server or use SSH to access the server in CLI mode.
- 2. Log in as **em7admin** with the appropriate password.

NOTE: If your Database Appliances are part of an HA cluster, place your HA cluster in maintenance mode using the steps found in the *High Availability and Disaster Recovery* manual.

3. Run the following command to launch the MySQL prompt:

```
silo_mysql
```

4. From the MySQL prompt, change the root password by running the following SQL query:

```
MariaDB [(none)]> SET PASSWORD FOR 'root' = PASSWORD('new password');
```

5. To effect this change immediately, run the following SQL query. Enter the new password when prompted.

```
MariaDB [(none)]> FLUSH PRIVILEGES;
```

6. Ensure you can access the database with the new password. Exit the MySQL interface, and test by running the following command, entering the new password when prompted:

```
mysql -u root -p
```

7. Edit the **silo.conf** file, as described in **Editing Silo.Conf**. Change the **dbpasswd** variable to the new password in both the [LOCAL] and [CENTRAL] sections.

NOTE: If you have clustered database appliances, be sure to update the silo.conf file for all cluster members.

- 8. If you have admin portals, update the **dbpasswd** variable in **silo.conf** on all admin portals.
- 9. If the Data Collector's MySQL root user password is now different from the MySQL root user password on the Database Server, and the **db_pass** column in **master.system_settings_licenses** is "NULL", then the Database Server will attempt to use its own password to connect.
- 10. Change the **db_pass** column for the collectors to their root MySQL user password using the instructions in **Updating the master.system_settings_licenses Table**.
- 11. If you placed an HA cluster into maintenance mode to perform these steps, remember to return it to ready mode by setting coro_config to option 1. For more information, see the High Availability and Disaster Recovery manual.

Recovering the Root MySQL Password

To reset the root MySQL password if you become locked out:

- 1. Either go to the console of the Database Server or use SSH to access the server in CLI mode.
- 2. Log in as **em7admin** with the appropriate password.
- 3. Stop the em7 and mariadb services:

```
systemctl stop em7 mariadb
```

4. Start the mariadb service with the "--skip-grant-tables' option:

```
systemctl set-environment MYSQLD_OPTS="--skip-grant-tables" systemctl
start mariadb
```

5. Access the MySQL database:

```
mysql -u root mysql
```

6. Reset the root password from the MySQL prompt:

```
UPDATE user SET password=PASSWORD('{new password}') WHERE
User='root';
```

7. Stop the mariadb service again, unset the environment variable, and restart the service, using the following sequence of commands:

```
systemctl stop mariadb

systemctl unset-environment MYSQLD_OPTS

systemctl start mariadb
```

8. Ensure that you can access the MySQL database with the new password:

```
mysql -u root -p
```

9. Restart the em7 service:

```
systemctl start em7
```

Ensure that the password you set is also updated in the /etc/silo.conf dbpasswd variable. For more
information, see Changing the MySQL Root Password on Database Appliances

Recovering the MySQL SNMP User Account on Data Collector

If you have removed the SNMP user account from the Data Collector's MySQL database in an attempt to harden your system, you must recover the account so that SL1 can insert incoming SNMP traps into the database for processing.

To restore the SNMP user account:

- 1. Either go to the console of the Database Server or use SSH to access the server in CLI mode.
- 2. Log in as **em7admin** with the appropriate password.
- 3. Run the following command to restore the SNMP user account:

```
/opt/em7/share/scripts/em7 firstboot.d/30 trap listener-db init.sh
```

Changing the MariaDB Password on SL1 Appliances

The following sections describe how to change the MariaDB password on SL1 appliances. This procedure differs based on the version of SL1 that you are using.

NOTE: This procedure should only be used when you do not know the current password and the SL1 application cannot login to the database.

Changing the MariaDB Password in SL1 11.3.0 and Above

On SL1 systems that were deployed from an 11.3.0 ISO or upgraded to 11.3.1 or above, use the following instructions to change the MariaDB password in Database Servers, Data Collectors, Message Collectors, and All-In-One Appliances:

- 1. Either go to the console of the Database Server or use SSH to access the server in CLI mode.
- 2. Log in as **em7admin** with the appropriate password.
- 3. Determine the username that SL1 uses for MariaDB access:

```
sl1-config silo LOCAL dbuser
```

4. Stop all SL1 services:

```
sudo siloctl stop
```

5. Access the MariaDB database with the super privileged account:

```
sudo /bin/mysql -u root mysql
```

6. Reset the password for the username that you identified in step 3 from the MariaDB prompt:

```
SET PASSWORD FOR '{username from step 3}'@'%' = PASSWORD('{new password}');
```

7. Exit the MariaDB database prompt:

/q

8. Edit the **silo.conf** file, as described in **Editing Silo.Conf**. Change the **dbpasswd** variable to the new password in both the [LOCAL] and [CENTRAL] sections.

NOTE: If you have clustered database appliances, be sure to update the **silo.conf** file for all cluster members.

NOTE: Upon saving, visilo will validate that the password works. If the password fails, ensure that you are typing it correctly, or that you set the password for the correct account in step 3.

9. Restart all SL1 services:

siloctl start

Changing the MariaDB Password in SL1 Versions Prior to 11.3.0

On SL1 systems that were deployed from an 11.2.x or older ISO and not patched to version 11.3.1 or above, use the following instructions to change the MariaDB password in Database Servers, Data Collectors, Message Collectors, and All-In-One Appliances:

- 1. Either go to the console of the Database Server or use SSH to access the server in CLI mode.
- 2. Log in as **em7admin** with the appropriate password.

NOTE: If your Database Appliances are part of an HA cluster, place your HA cluster in maintenance mode using the steps found in the *High Availability and Disaster Recovery* manual.

3. Stop all SL1 services:

```
sudo siloctl stop
```

4. Stop the MariaDB service:

```
systemctl stop mariadb
```

5. Start the MariaDB service with the "--skip-grant-tables" option:

```
systemctl set-environment MYSQLD_OPTS="--skip-grant-tables";
systemctl start mariadb
```

6. Access the Maria DB database:

```
silo mysql -u root mysql
```

7. Reset the password from the MariaDB prompt:

```
SET PASSWORD FOR 'root'@'%' = PASSWORD('{new password}');
```

8. Exit the MariaDB database prompt:

\q

9. Stop the MariaDB service again, unset the environment variable, and restart the service:

```
systemctl stop mariadb

systemctl unset-environment MYSQLD_OPTS

systemctl start mariadb
```

10. Edit the **silo.conf** file, as described in **Editing Silo.Conf**. Change the **dbpasswd** variable to the new password in both the [LOCAL] and [CENTRAL] sections.

NOTE: If you have clustered database appliances, be sure to update the **silo.conf** file for all cluster members.

11. Verify that the password works:

```
silo mysql
```

12. Restart all SL1 services:

sudo siloctl start

13. If you placed an HA cluster into maintenance mode to perform these steps, remember to return it to ready mode by setting coro_config to option 1. For more information, see the High Availability and Disaster Recovery manual.

Chapter

10

Changing the IP Address of an SL1 Appliance

Overview

The IP address for an appliance is configured at installation. To change the IP address for an appliance after installation and preserve your SL1 license, use the procedures in this section.

IMPORTANT: If you are running SL1 on a cloud-based service like AWS or Azure, the following change procedures do not apply. The IP settings are provided automatically by DHCP, and configuration changes must be made in the DHCP provider's settings.

Moving an SL1 appliance to a new network requires pre-planning. If your SL1 configuration includes one or more Administration Portals, PhoneHome Collectors, or is configured for High Availability or Disaster Recovery, you must perform additional steps after changing IP addresses. The steps in this section allow you to change the IP address for an SL1 appliance with minimal downtime.

NOTE: This procedure requires downtime, so plan to perform this procedure during a maintenance window.

CAUTION: Ensure console access to the appliance you are migrating in case of typographical or other errors that might prevent network access when changing IP addresses.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon (=).
- To view a page containing all of the menu options, click the Advanced menu icon (---).

This chapter covers the following topics:

Changing the IP Address on an All-In-One Appliance	298
Changing the IP Address on a Database Server	301
Changing the IP Address on a Data Collector or Message Collector	310
Confirming the IP Address Change on the Appliance Manager Page	312

Changing the IP Address on an All-In-One Appliance

To change the primary IP address of an All-In-One Appliance:

Step 1. Stop the EM7 Service

Before changing the IP address, you must stop the EM7 service. To stop the EM7 service:

- 1. Either go to the console of the SL1 appliance or use SSH to access the server.
- 2. Login as user **em7admin** with the appropriate password.
- 3. Type the following at the command line:

```
sudo systemctl stop em7
```

Step 2. Change the IP Address in the silo.conf File

You must change the ipaddress value in the silo.conf configuration file.

- 1. Either go to the console of the SL1 appliance or use SSH to access the server.
- 2. Type the following at the command line:

```
sudo visilo
```

3. Change the following line in the [LOCAL] section of the file to specify the new IP address:

```
ipaddress = new IP address
```

4. Save and quit the file (:wq).

Step 3. Change the IP Address in the /etc/hosts File

If the /etc/hosts file includes an entry for the appliance, update the entry with the new IP address.

- 1. Either go to the console of the SL1 appliance or use SSH to access the server.
- 2. Type the following at the command line:

```
sudo vi /etc/hosts
```

3. If you see an IP address for the All-In-One Appliance, change the IP address to the new IP address.

NOTE: Updating the /etc/hosts/ file automatically restarts the dnsmasq service to ensure the service can read the updated file.

Step 4. Change the IP Address in the Network Interface Configuration File

NOTE: Be sure to set the IPADDR, PREFIX, GATEWAY and DNS# variables to the appropriate values for the new network. The PREFIX is the subnet mask in CIDR notation.

To change the IP address, Netmask, Gateway address, and DNS Server for an appliance in the ifconfig file:

- 1. Either go to the console of the SL1 appliance or use SSH to access the server.
- 2. Login as user **em7admin** with the appropriate password.
- 3. Type the following at the command line:

```
sudo ifconfig
```

4. Your output will look like this:

```
inet6 fe80::250:56ff:fe84:455f prefixlen 64 scopeid 0x20<link>
ether 00:50:56:84:45:5f txqueuelen 1000 (Ethernet)

RX packets 1774927 bytes 161985469 (154.4 MiB)

RX errors 0 dropped 861 overruns 0 frame 0

TX packets 1586042 bytes 158898786 (151.5 MiB)

TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0

lo: flags=73<UP, LOOPBACK, RUNNING> mtu 65536
inet 127.0.0.1 netmask 255.0.0.0
inet6 ::1 prefixlen 128 scopeid 0x10<host>
loop txqueuelen 0 (Local Loopback)

RX packets 13406577 bytes 4201274223 (3.9 GiB)

RX errors 0 dropped 0 overruns 0 frame 0

TX packets 13406577 bytes 4201274223 (3.9 GiB)

TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
```

5. Examine the output, find the interface that uses the old IP address, and note its name.

6. Use the vi editor to edit the settings for the interface. To do this, enter the following at the command line:

```
sudo vi /etc/sysconfig/network-scripts/ifcfg-interface name you noted
in step #5
```

For example, from our output, we could enter:

```
sudo vi /etc/sysconfig/network-scripts/ifcfg-ens32
```

7. The ifcfg file will look like this:

```
TYPE=Ethernet
BOOTPROTO=none
DNS1=10.64.20.33
DEFROUTE=yes
IPV4 FAILURE FATAL=no
IPV6INIT=yes
IPV6 AUTOCONF=yes
IPV6 DEFROUTE=yes
IPV6 FAILURE FATAL=no
NAME=ens32
UUID=d471435d-9adf-47c9-b3f3-32f61dccbad8
DEVICE=ens32
ONBOOT=yes
IPADDR=10.64.68.20
PREFIX=24
GATEWAY=10.64.68.1
IPV6 PEERDNS=yes
IPV6 PEERROUTES=yes
```

- 8. You can edit one or more of the following settings:
 - DNS1=IP address of the DNS server that will be used by the SL1 appliance.
 - IPADDR=New IP address of the SL1 appliance.
 - **PREFIX**=netmask for the SL1 appliance.
 - GATEWAY=IP address of the network gateway that will be used by the SL1 appliance.
- 9. Save your changes and exit the file (:wq)
- 10. At the command line, enter the following:

```
service network restart
```

Step 5. Update the IP Address in the MySQL Database

In this step, you must set the new IP address in the master.system_settings_licenses table so that when SL1 is restarted, the new IP address is recognized as licensed.

- 1. Either go to the console of the SL1 appliance or use SSH to access the server.
- 2. Login as user **em7admin** with the appropriate password.
- 3. Enter the following at the command line:

```
silo_mysql
```

4. At the mysql prompt, enter the following query:

```
UPDATE master.system_settings_licenses SET ip="[new IP address]"
WHERE ip="[old IP address]" LIMIT 1;
```

For example:

```
[em7admin@hostname ~]$ silo_mysql

MariaDB [(none)]> UPDATE master.system_settings_licenses SET
ip="192.168.10.22" WHERE ip="10.1.1.240";
Query OK, 1 row affected (0.01 sec)
Rows matched: 1 Changed: 1 Warnings: 0
MariaDB[(none)]>
```

5. Type "exit" to exit the MySQL session.

Step 6. Reboot the Appliance

Reboot the appliance to apply all of the changes you made.

The system will boot up and will start the interface with the new IP address. SL1 will start up and will learn from the database that the new IP address matches its configuration file and the value in the database table. Therefore, SL1 will keep the current license for the appliance.

Step 7. Confirm the Change in SL1

After changing the IP address for your SL1 appliance, go to the **Appliance Manager** page (System > Settings > Appliances) and confirm that the correct IP address for that appliance appears in the *IP Address* column. If it does not, you must *update it*.

Changing the IP Address on a Database Server

Changing the primary IP address of a Database Server requires additional steps if

- the Database Server resides in a High Availability configuration or a Disaster Recovery configuration
- the Database Server might connect to Data Collectors configured for PhoneHome

In addition, when you change the primary IP address of a Database Server, you must update the configurations for any Data Collectors, Message Collectors and Administration Portals that communicate with that Database Server.

WARNING: For Clustered Database Appliances (using HA, DR, or HA+DR), ScienceLogic recommends that you place the cluster into maintenance mode. Also, ScienceLogic recommends that you wait to wait to change the virtual IP address until all of the Database Servers have been moved to its new location, if applicable.

To change the IP address of a Database Server:

Step 1. Stop the EM7 Service

Before changing the IP address, you must stop the EM7 service. To stop the EM7 service:

- 1. Either go to the console of the Database Server or use SSH to access the server.
- 2. Login as user **em7admin** with the appropriate password.
- 3. Enter the following at the command line:

```
sudo systemctl stop em7
```

Step 2. Change the IP Address in the silo.conf File

You must change the ipaddress value in the silo.conf configuration file. To do so:

- 1. Either go to the console of the SL1 appliance or use SSH to access the server.
- 2. Enter the following at the command line:

```
sudo visilo
```

3. Change the following line in the [LOCAL] section of the file to specify the new IP address:

```
ipaddress = new IP address
```

4. Save and quit the file (:wq).

Step 3. Change the IP Address in the /etc/hosts File

If the /etc/hosts file contains an entry for the appliance, update the entry with the new IP address.

- 1. Either go to the console of the SL1 appliance or use SSH to access the server.
- 2. Enter the following at the command line:

3. If you see an IP address for the Database Server, change the IP address to the new IP address.

Step 4. Change the IP Address in the Network Interface Configuration File

NOTE: Be sure to set the IPADDR, PREFIX, GATEWAY and DNS# variables to the appropriate values for the new network. The PREFIX is the subnet mask in CIDR notation.

To change the IP address, Netmask, Gateway address, and DNS Server for an appliance in the ifconfig file:

- 1. Either go to the console of the Database Server or use SSH to access the server.
- 2. Login as user **em7admin** with the appropriate password.
- 3. Enter the following at the command line:

```
sudo ifconfig
```

4. Your output will look like this:

```
ens32: flags=4163<UP,BROADCAST,RUNNING,MULTICAST> mtu 1500inet
10.64.68.20 netmask 255.255.255.0 broadcast 10.64.68.255
inet6 fe80::250:56ff:fe84:455f prefixlen 64 scopeid 0x20<link>
ether 00:50:56:84:45:5f txqueuelen 1000 (Ethernet)
RX packets 1774927 bytes 161985469 (154.4 MiB)
RX errors 0 dropped 861 overruns 0 frame 0
TX packets 1586042 bytes 158898786 (151.5 MiB)
TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
lo: flags=73<UP, LOOPBACK, RUNNING>
                                  mtu 65536
inet 127.0.0.1 netmask 255.0.0.0
inet6 ::1 prefixlen 128 scopeid 0x10<host>
loop txqueuelen 0 (Local Loopback)
RX packets 13406577 bytes 4201274223 (3.9 GiB)
RX errors 0 dropped 0 overruns 0 frame 0
TX packets 13406577 bytes 4201274223 (3.9 GiB)
TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
```

5. Examine the output, find the interface that uses the old IP address, and note its name.

6. Use the vi editor to edit the settings for the interface. To do this, enter the following at the command line:

```
sudo vi /etc/sysconfig/network-scripts/ifcfg-interface name you noted
in step #5
```

For example, from our output, we could enter:

```
sudo vi /etc/sysconfig/network-scripts/ifcfg-ens32
```

7. The ifcfg file will look like this:

```
TYPE=Ethernet
BOOTPROTO=none
DNS1=10.64.20.33
DEFROUTE=yes
IPV4 FAILURE FATAL=no
IPV6INIT=yes
IPV6 AUTOCONF=yes
IPV6 DEFROUTE=yes
IPV6 FAILURE FATAL=no
NAME=ens32
UUID=d471435d-9adf-47c9-b3f3-32f61dccbad8
DEVICE=ens32
ONBOOT=yes
IPADDR=10.64.68.20
PREFIX=24
GATEWAY=10.64.68.1
IPV6 PEERDNS=yes
IPV6 PEERROUTES=yes
```

- 8. You can edit one or more of the following settings:
 - DNS1=IP address of the DNS server that will be used by the Database Server.
 - IPADDR=New IP address of the Database Server.
 - PREFIX=netmask for the Database Server.
 - GATEWAY=IP address of the network gateway that will be used by the Database Server.
- 9. Save your changes and exit the file (:wq)
- 10. At the command line, enter the following:

```
sudo service network restart
```

Step 5. Update the IP Address in the MySQL Database

In this step, you must set the new IP address in the master.system_settings_licenses table so that when the Database Server is restarted, SL1 recognizes the new IP address as licensed.

- 1. Either go to the console of the SL1 appliance or use SSH to access the server.
- 2. Login as user **em7admin** with the appropriate password.
- 3. Enter the following at the command line:

```
silo mysql
```

4. At the mysql prompt, enter the following query:

```
UPDATE master.system_settings_licenses SET ip="[new IP address]"
WHERE ip="[old IP address] LIMIT 1"
```

For example:

```
[em7admin@hostname ~]$ silo_mysql

MariaDB [(none)]> UPDATE master.system_settings_licenses SET
ip="192.168.10.22" WHERE ip="10.1.1.240";
Query OK, 1 row affected (0.01 sec)
Rows matched: 1 Changed: 1 Warnings: 0

MariaDB[(none)]>
```

5. Enter "exit" to exit the MySQL session.

Step 5a: For Database Servers Configured with PhoneHome

If your Database Server is configured with PhoneHome, perform the following additional steps to change the IP address of the :Database Server.

NOTE: If you add additional Database Servers with new IP addressees, wait for the Database Servers to migrate, and then the PhoneHome collectors will attempt to connect using the new Database Server IP addresses. After the databases reconnect, you can remove database entries with old IP addresses from the PhoneHome configuration.

- 1. Either go to the console of the Database Server or use SSH to access the server.
- 2. Enter the following at the command line:

```
phonehome status
```

NOTE: If you are planning to change the IP address of multiple Database Servers, you will want to update all of the relevant IP addresses in PhoneHome in this step.

3. The output will look like the following:

```
Phone Home Client configuration:
 Config Revisions: Device: 2 Destinations: 7 Global: 9
Device Id Type
               State Status Forwards
______
      collector Enabled forwarded
                                Phone Home collector 15
               State Host/Ip Port
Device Id Type
                                    Name
     database Enabled 192.168.2.2 7705 Phone Home database 11
11
12
     database Enabled 192.168.2.4 7705 Phone Home database 12
     database Enabled 192.168.2.6 7705 Phone Home database 13
13
```

- 4. Note the Device ID for the Database Server. .
- 5. Run the phonehome set command to change the IP address for the device ID that corresponds to the Database Server. To do this, enter the following:

```
phonehome set <device_id> ip="<new_ip_address>"
```

where:

- <device id> is the device ID you noted in step #4.
- <new ip address> is the new IP address.

For example

```
[root@<database_hostname username>] # phonehome set 11 ip="<new_
ip_address>"
```

Reloading sshd configurations

6. For each Database Server that you want to change the IP address, perform step #5.

Step 5b For Clustered Database Appliances (using HA, DR, or HA+DR)

If your Database Servers are clustered for High Availability (HA), Disaster Recovery (DR), or both (HA+DR), to change the IP address of the Database Servers, you must also modify the clustering software configuration files, as described in this step.

1. Either go to the console of the Database Server or use SSH to access the server.

WARNING: Changes to the running Cluster Resource Manager (CRM) configuration take effect immediately. ScienceLogic recommends that you wait to wait to change the virtual IP address until all of the Database Servers have been moved to its new location, if applicable.

2. You must edit the settings for the virtual IP for the cluster. At the command line, enter the following:

```
crm resource stop virtual_ip
crm resource param virtual_ip set ip <new_IP_address>
crm resource param virtual_ip set cidr_netmask <new_subnet_mask_in_
CIDR_notation>
crm resource start virtual_ip
```

- 3. In a High Availability configuration, the two Database Servers use two rings:
 - ringO defines the private interfaces that are connected directly to one another via crossover cable.
 - ring1 defines the public interfaces that host the virtual IP and conduct the SL1 related tasks.

To update these values in a High Availability configuration, you must edit the file /etc/corosync/corosync.conf..

- 4. Use a file editor like vi to edit /etc/corosync/corosync.conf.
- 5. You will see something like this:

```
nodelist {
node {
  ring0_addr: 192.168.25.200
  ring1_addr: 10.1.20.25
  name: hardb1
  nodeid: 1
}
node {
  ring0_addr: 192.168.25.201
  ring1_addr: 10.1.20.26
  name: hardb2
  nodeid:2
}
```

6. For the Database Server with the new IP address, edit the value for ringO_addr to match the new IP address. Save the file.

DRBD is the service that synchronizes the Database Servers in a High Availability or Disaster Recovery configuration. The DRBD file /etc/drbd.d/r0.res defines how data (on resource 0) is synchronized.

- In SL1 configured for High Availability, DRBD uses the private IPs to synchronize high-availability data.
- In SL1 configured for High Availability plus Disaster Recovery, DRBD uses the private interface to synchronize high-availability data and the virtual IP and the public IP addresses to synchronize data for disaster recovery.
- In SL1 configured for Disaster Recovery, DRBD uses the virtual IP and the public IP addresses to synchronize data.=

7. Use a file editor like vi to edit /etc/drbd.d/r0.res. It will look something like this:

```
resource r0 {
protocol A;
device /dev/drdb1;
 stacked-on-top-of r0-L {
 address 127.0.0.1:7789;
 proxy on hadrdb1 hadrdb2 {
  inside 127.0.0.1:7790;
  outside 192.168.25.200:7788;
 }
on hadrdb2
 disk /dev/mapper/em7vg-db;
 address 127.0.0.1:7789;
 meta-disk internal;
 proxy on hadrdb3 {
  inside 127.0.0.1:7790;
  outside 192.168.25.201:7788;
 }
```

- 8. Replace instances of the old IP address with the new IP address and save the file.
- 9. Shut down the Database Server.
- 10. Upon reboot of the Database Server, run a discovery session to rediscover the Database Server with its new IP address.

Step 6. Reboot the Appliance

Reboot the Database Server to apply all of the changes you made.

CAUTION: If you are migrating a High Availability cluster, shut down the secondary first, then the primary, so that SL1 does not perform a failover. Restart up the primary first, and after it is up and running, restart on the secondary.

The system will boot up and will start the interface with the new IP address. SL1 will start up and will learn from the database that the new IP address matches its configuration file and the value in the database table. Therefore, SL1 will keep the current license for the appliance.

Step 7. Change the Database Appliance IP Address in the Administration Portals, Data Collectors, and Message Collectors

You must edit the configuration for each SL1 node that communicates with the Database Server. To do so, perform the following steps on each Administration Portal, Data Collector, and Message Collector in your SL1 system.

Perform the following steps to log in to the Web Configuration Utility:

1. You can log in to the Web Configuration Utility using any web browser supported by SL1. The address of the Web Configuration Utility is in the following format:

https://<ip-address-of-appliance>:7700

NOTE: For AWS instances, *ip-address-of-appliance* is the public IP for the AWS instance. To locate the public IP address for an AWS instance, go to AWS, go to the **Instances** page, and highlight an instance. The **Description** tab in the lower pane will display the public IP.

- 2. When prompted to enter your user name and password, log in as the "em7admin" user with the appropriate password.
- 3. After logging in, the main **Configuration Utility** page appears.
- 4. Click the [Device Settings] button in the upper-right of the page. The Settings page appears.
- 5. In the **Settings** page, enter the following:
 - Database IP Address. The new IP address of the Database Server.
 - **Database Username**. Username for the database account that the Administration Portal will use to communicate with the Database Server.
 - Accept the default values in all other fields.
- 6. Click the [Save] button. You may now log out of the Web Configuration Utility.

Step 8. Confirm the Change in SL1

After changing the IP address for your SL1 appliance, go to the **Appliance Manager** page (System > Settings > Appliances) and confirm that the correct IP address for that appliance appears in the **IP Address** column. If it does not, you must **update it**.

Changing the IP Address on a Data Collector or Message Collector

You can change the IP address of a Data Collector or Message Collector in two ways:

- In the Web Configuration Utility
- From the command line of the Data Collector or Message Collector

Regardless of the method you choose, SL1 will automatically update the IP address of the Data Collector or Message Collector in:

- /etc.sillo.conf
- /etc/sysconfig/network-scripts/ifcfg-ens160
- /etc/hosts
- the master.system_settings_licenses table, in the ip column

The following sections explain the necessary steps.

Using the Web Configuration Utility to Change the IP Address of a Data Collector or Message Collector

Perform the following steps to log in to the Web Configuration Utility:

1. You can log in to the Web Configuration Utility using any web browser supported by SL1. The address of the Web Configuration Utility is in the following format:

https://<ip-address-of-appliance>:7700

NOTE: For AWS instances, *ip-address-of-appliance* is the public IP for the AWS instance. To locate the public IP address for an AWS instance, go to AWS, go to the **Instances** page, and highlight an instance. The **Description** tab in the lower pane will display the public IP.

- 2. When prompted to enter your user name and password, log in as the "em7admin" user with the appropriate password.
- 3. After logging in, the main **Configuration Utility** page appears.
- 4. Select the Interfaces tab.
- 5. In the Interfaces page, select the interface that you want to edit.
- 6. Enter values in the following field:
 - Interface IP Address. Required. Enter the IP address for the bonded interface in standard IPv4, dotted-octet format.
- 7. The IP address for the Data Collector or Message Collector will be automatically updated in all the necessary configuration file and database tables.

Using the Command Line to Change the IP Address of a Data Collector or Message Collector

- 1. Either go to the console of the Data Collector or Message Collector or use SSH to access the server.
- 2. At the shell prompt, enter:

where:

- interface ID is the name of the interface, usually ensn32 or ens160.
- new IP is the new IP address to assign to the interface.
- 3. The IP address for the Data Collector or Message Collector will be automatically updated in all the necessary configuration file and database tables.

Confirming the IP Address Change on the Appliance Manager Page

After changing the IP address for your SL1 appliance, go to the **Appliance Manager** page (System > Settings > Appliances) and confirm that the correct IP address appears for that appliance in the *IP Address* column.

If the **Appliance Manager** page does not display the new IP address, you can manually update the address. To do so:

- 1. Go to the **Appliance Manager** page (System > Settings > Appliances).
- 2. Click the wrench icon (🎤) of the appliance you want to update. Its values appear in the fields at the top of the page.
- 3. In the IP Address field, type the new IP address.
- 4. Click [Save].

Chapter

11

Changing Name Servers on an SL1 Appliance

Overview

This chapter describes how to change domain name servers (DNS) on an SL1 appliance.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon
- To view a page containing all of the menu options, click the Advanced menu icon (....).

This chapter covers the following topics:

Changing Name Servers on an SL1 Appliance	3	14	4
Installing Additional RPMs on an SL1 Appliance	. 3	1!	5

Changing Name Servers on an SL1 Appliance

Domain Name Server (DNS) server settings are configured at installation. You cannot adjust the DNS settings later through the Web Configurator. Instead, you must use the command line interface (CLI) to change the DNS server information. This action requires no downtime.

IMPORTANT: If you are running SL1 on a cloud-based service like AWS or Azure, the following change procedures do not apply. The DNS settings are provided automatically by DHCP, and configuration changes must be made in the DHCP provider's settings.

To change the DNS settings:

1. Edit the /etc/resolv.conf file by entering the following command:

```
sudo vi /etc/resolv.conf
```

- 2. Change the nameserver entry to the IP address of the new DNS or add new DNS entries to the file.
- 3. Save and quit to commit the changes.

This change immediately causes the OS to use the new DNS, with no reboot or service restarts required. If you have multiple nameservers listed in the file, the system will try each entry in the list until it gets a response or runs out of nameservers.

Next, add the DNS to the interface configuration file so that the change will persist if the network service is restarted or the appliance is rebooted.

To add one or more domain name servers to the interface configuration file:

- 1. Either go to the console of the SL1 appliance or use SSH to access the server.
- 2. Log in as user **em7admin** with the appropriate password.
- 3. Determine the name of your primary interface (not the "lo" interface) by running the following command:

```
ip addr
```

4. Edit the corresponding interface configuration file in the /etc/sysconfig/network-scripts directory:

```
sudo vi /etc/sysconfig/network-scripts/ifcfg-{interface name}
```

5. Find the "DNS1" entry and change the IP address to the IP address of the new DNS.

NOTE: You can enter additional DNS servers and define them as DNS2, DNS3, and so on.

6. Save and guit to commit the changes.

Installing Additional RPMs on an SL1 Appliance

For certain patch releases, ScienceLogic might require additional RPMs to be installed on specific appliance types. If an RPM install is required, the release notes will indicate the additional RPMs to install on each specific appliance type.

To install additional RPMs on an appliance, perform the following steps:

- 1. Download the RPM files provided by ScienceLogic to your local machine.
- 2. Log in as root at the appliance console.
- 3. Copy each of the downloaded RPM files to the appliance. To copy the downloaded files, perform the following command as root at the console of the appliance:

```
scp <username-on-local-machine>@<ip-address-of-your-local-
machine>:<full-path-to-rpm-on-your-local-machine> <full-path-on-
appliance-to-copy-to>
```

4. Use the following command to run the RPM installer for each of the RPM files:

```
rpm -U <name-of-rpm-file>.rpm
```

5. If you have not yet done so, apply the latest patch to your SL1 system.

Chapter

12

Backup Management

Overview

This chapter describes how to prepare to back up your SL1 system, to define and run your backups, and to restore from different backup types.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon
- To view a page containing all of the menu options, click the Advanced menu icon (...).

This chapter covers the following topics:

Types of SL1 Backups	317
The Workflow for Backing Up and Restoring SL1	320
Planning for SL1 Backups	321
Creating Backup Credentials	321
Configuring Backups	323
Mounting Backup Files	331
Restoring Backups	333
Retaining Backups	349
Additional Configuration for Solaris NFS Remote Shares	351
Performing Configuration and Full Backups on the DR Database Server	351

Types of SL1 Backups

SL1 allows you to define three types of backups for your system:

- Configuration Backups, which include the core database tables and files required to restore an SL1 system. A configuration backup includes scope and policy information, but not performance data, data collected using configuration Dynamic Applications, events, or logs.
- Full Backups, which include all SL1 databases and tables. A full backup does not back up the configuration files in /etc/backup.conf. As a result, PhoneHome configuration files are not backed up in a full backup; you can back up PhoneHome files and other configuration files in a configuration backup.
- Disaster Recovery Backups, which include a full backup of the disaster recovery database for SL1 systems configured for disaster recovery (DR). The DR backup is similar to the full backup.

NOTE: If you have a large SL1 system and large backup files, you have the option to *perform standard* configuration or full backups on the disaster recovery Database Server. This is different than performing a disaster recovery backup.

The **Backup Management** page (System > Settings > Backup) lets you define your backups and run them on demand.

CAUTION: ScienceLogic does not support vmotion or VMware Snapshots for backups of data. For backup purposes, ScienceLogic supports only ScienceLogic backups to remote storage. Be advised that vmotion and VMware Snapshots can cause SL1 outages.

Configuration Backups

A **configuration backup** stores a copy of the core database tables that are required to restore an SL1 system. Configuration backups use the "MySQL dump" tool to create backups.

Note the following information about configuration backups:

- SL1 automatically retains your last seven configuration backups, but will retain only one back up per day. If more than one configuration backup is created on the same day, SL1 retains the most recent one.
- SL1 can launch configuration backups automatically at the interval you specify.
- During configuration backup, the ScienceLogic database remains online.
- When the configuration backup starts, SL1 creates a temporary mount point to your remote share in /data.local/backup/remote<unix_timestamp>.
- If you have a large system and very large backup files, you can use an alternative method to perform
 backups that reduces performance issues during backup. For more information, see the section Performing
 Config Backups and Full Backups on a Disaster Recovery Database Server.

317 Types of SL1 Backups

What Does a Configuration Backup Include?

A configuration backup includes:

- Scope and policy information, but **not performance data**, **data collected using configuration Dynamic Applications**, **or events**.
- By default, the following files are backed up during a configuration backup:
 - ° /etc/backup.conf
 - ° /etc/corosync/corosync.conf
 - ° /etc/drbd.d/r0.res
 - ° /etc/drbd-proxy.license
 - ° /etc/hosts
 - ° /etc/my.cnf.d/silo mysql.cnf
 - ° /etc/nginx/*
 - ° /etc/phonehome/*
 - ° /etc/php-fpm.d/*.conf
 - ° /etc/postfix/main.cf
 - ° /etc/silo.conf
 - ° /etc/siteconfig/*
 - ° /etc/ssh/*.key
 - ° /etc/ssh/*.pub
 - ° /etc/sysconfig/network-scripts/ifcfg-*
 - ° /etc/sysctl.d/*
 - ° /etc/systemd/system/mariadb.service.d/*.conf
 - ° /opt/em7/nextui/nextui.conf
 - ° /usr/libexec/postfix/main.cf
 - ° /var/log/em7/*
- All files and folders specified in /etc/backup.conf. If you have additional files that you want to include in
 configuration backups, you can include them in the file /etc/backup.conf. For more information, see the
 section on Adding Files to Include in Configuration Backups.
- The following databases:
 - master. Includes system-level settings for SL1, Dynamic Application definitions and alignments, run book automation and action policies, monitoring policy definitions, and credentials.

Types of SL1 Backups 318

- master access. Includes user account information, access keys, and access hooks.
- master_ap2. Includes files from the new UI, including files from Business Services.
- master_biz. Includes asset information, dashboards, distribution lists, document templates, IT Service policy information, organization information, product SKU information, RSS feeds, ticketing information, and user preferences. By default, configuration backups do not include the ticket_external requests table from the master biz database.
- master_custom. Includes GUI customizations, dashboard widget definitions, and PowerPack files.
- master_dev. Includes information associated with device records, excluding performance data, data collected using configuration Dynamic Applications, events, or logs.
- master dns. Includes DNS information.
- master_events. The configuration backup includes only the event_suppressions table from this database. This table stores event suppression settings.
- master_filestore. Includes information about files, PowerPacks, and notes. By default, configuration backups do not include the tables metadata_system_package, metadata_system_patch, storage_system_package, and storage_system_patch.
- ° master platform. Includes information about ScienceLogic appliances.
- master_reports. Includes custom report definitions.
- ° **mysql**. Contains the configuration settings for the MariaDB database.
- ° scheduler. Includes all instances of scheduled items: reports, discovery sessions, etc.
- sysinfo. Contains the configuration settings for High Availability, Disaster Recovery, and PhoneHome Collectors.

Full Backups

A *full backup* creates a complete backup of the ScienceLogic database. Full backups use a built-in tool call MariaBackup.

Note the following information about full backups:

- SL1 can launch full backups automatically at the interval you specify.
- During a full backup, the ScienceLogic database remains online.
- If you have a large system and very large backup files, you can use an alternative method to perform
 backups that reduces performance issues during backup. For more information, see the section Performing
 Config Backups and Full Backups on a Disaster Recovery Database Server.

What Does a Full Backup Include?

A full backup includes all databases and tables.

A full backup does *not* back up the configuration files in /etc/backup.conf. As a result, PhoneHome configuration files are not backed up in a full backup; you can back up PhoneHome files and other configuration files in a configuration backup.

NOTE: For very large SL1 systems, ScienceLogic recommends you use a SAN with snapshot technology to backup and restore data.

NOTE: If your SL1 System uses AWS RDS (remote database), the Full Backup option is disabled.

Disaster Recovery Backups

Disaster recovery backups are similar to full backups, but are available only for SL1 systems that are configured for disaster recovery (DR).

DR backups temporarily stop replication, mount the database, and run a full backup of the DR database. The process then re-enables replication and performs a partial resynchronization from the primary.

Note the following information about DR backups:

- DR backups use 'tar' to create a copy and compress the /data.local/db directory.
- During DR backup, the primary ScienceLogic database remains online.
- DR backups are not available on two-node high availability (HA) clusters.

What Does a Disaster Recovery Backup Include?

Disaster recovery backups include all configuration data, performance data, and log data.

NOTE: If your SL1 System uses AWS RDS (remote database), the DR Backup option is disabled.

The Workflow for Backing Up and Restoring SL1

The workflow for backing up SL1 is:

- 1. Plan the backup.
- 2. Create a backup credential.
- 3. Configure the backup.

Once the backup file has been created, should you ever need to restore that backup, the workflow is:

- 1. Mount the backup (NFS and SMB shares only).
- 2. Restore the backup.
- 3. Retain the backup (full and DR backups only).

Planning for SL1 Backups

Before creating a backup of your SL1 system, you must determine the following:

- The external system or service to which the backup will be stored. Your options are:
 - NFS file share
 - SMB file share
 - ° S3 storage service

NOTE: It is the responsibility of the system administrator for the external system to create any necessary entries in /etc/fstab required to allow the SL1 system to access the share as root.

- The hostname or IP address of the system or service to which the backup will be stored.
- The directory to which you will write the backup.

Creating Backup Credentials

To configure a backup, you must include a credential that allows SL1 to write to the external systems where you will store the backups. There are two types of credentials that you can create for this task:

- An S3 Backup credential, if you are backing up your system to an S3 storage service
- A Basic/Snippet credential, for all other backup scenarios

The sections below describe how to create both credential types.

Creating an S3 Backup Credential

You can use an S3 storage service to store configuration backups for SL1. To do so, you will need to create a credential that enables SL1 to connect to the S3 service. SL1 includes an **S3 Backup** credential type, which uses field names and terminology specific to S3 services, that you can use to connect with your S3 service.

NOTE: SL1 supports the use of Amazon Web Services (AWS) or MinIO for S3 backup storage.

To define an S3 backup credential:

- 1. Go to the **Credentials** page (Manage > Credentials).
- 2. Click the [Create New] button and then select Create S3 Backup Credential. The Create Credential modal page appears.
- 3. Supply values in the following fields:
 - **Name**. Type a unique name for the credential. Can be any combination of alphanumeric characters, up to 64 characters.
 - All Organizations. Toggle on (blue) to align the credential to all organizations, or toggle off (gray)
 and then select one or more specific organizations from the What organization manages this
 service? drop-down field to align the credential with those specific organizations.

NOTE: To learn more about credentials and organizations, see the section on "Aligning Organizations with a Credential" in the **Discovery & Credentials** manual.

- **Timeout (ms)**. Type the time, in milliseconds, after which SL1 will stop trying to communicate with the S3 storage service.
- **Provider**. Select the S3 storage provider you want to use to store the backup. Choices are Amazon Web Services (AWS) S3 and Minio Object Storage.
- Access Key ID. Type the Access Key ID for the S3 account on which you want to store the backup.
- **Secret Access Key**. Type the Secret Access Key for the S3 account on which you want to store the backup.
- Endpoint. Type the URL of the S3 endpoint. The endpoint URL should not include the bucket name.
- Region. Select the region of the S3 endpoint.
- Bucket. Type the name of the S3 bucket on which you want to store the backup.
- Encryption Password. Type the encryption password for the backup file.
- Encryption Salt. Type the encryption salt used to safeguard the backup file encryption password.
- 4. Click [Save & Close].

NOTE: If you would like to test your credential using the Credential Tester panel, click [Save & Test]. For detailed instructions on using the Credential Tester panel, see the section on "Using the Credential Tester Panel" in the *Discovery & Credentials* manual.

Creating a Basic/Snippet Backup Credential

If you are backing up your SL1 system to a platform other than an Amazon Web Services S3 bucket, you must create a **Basic/Snippet** backup credential that allows SL1 to write to the external backup systems.

To create a **Basic/Snippet** backup credential:

- 1. Go to the **Credentials** page (Manage > Credentials).
- 2. Click [Create New] and select Create Basic/Snippet Credential. The Create Credential modal appears.

NOTE: Alternatively, if you are using the classic SL1 user interface, you can go to the **Credential**Management page (System > Manage > Credentials), click the [Actions] button, and select

Create Basic/Snippet Credential to use the **Credential Editor** modal.

- 3. Define values in the following fields:
 - Name. Name of the credential. Can be any combination of alphanumeric characters.
 - Organization. Select All Organizations or select an organization from the drop-down.
 - Hostname/IP. The hostname or IP address.
 - Port. This field is deprecated. Backups will not use this field.
 - Timeout (ms). This field is deprecated. Backups will not use this field.
 - **Username**. Username to use when connecting to the external system. If you are backing up to NFS-remote, this field is not required.
 - **Password**. Password to use when connecting to the external system. If you are backing up to NFS-remote, this field is not required.
- 4. Click [Save & Close].

Configuring Backups

This section describes how to configure SL1 backups.

Depending on the backup type, this process might include multiple steps:

- 1. Include additional files or directories (configuration backups only).
- 2. View the included databases and tables (configuration backups only).
- 3. Define the configuration, full, or disaster recovery backup options.

When you define the backup options, you must determine the external storage protocol and directory on which the backup will be stored. You have the following storage options:

- NFS mount
- SMB mount
- \$3 storage service

NOTE: You cannot store backups on the SL1 Database Server or All-In-One Appliance.

323 Configuring Backups

Adding Files to Include in Configuration Backups

All files and directories that are specified in /etc/backup.conf are included in configuration backups. If you have additional files or directories that you want to include in configuration backups, you can edit the /etc/backup.conf file to include them.

To add files or directories that you want to include in configuration backups:

- 1. Either go to the console of the SL1 appliance or use SSH to access the server.
- 2. Enter the following at the command line:

sudo vi /etc/backup.conf

- 3. Move the cursor below the line that says, "Custom files can be added below this line".
- 4. Make the following updates based on what you want to include:
 - To add a file, enter the full directory path and filename.
 - To add a directory or folder, enter an asterisk (*) instead of a filename after the full directory path.
- 5. Save your changes and quit the file (:wq).

Viewing the Databases and Tables Included or Excluded from a Configuration Backup

NOTE: This section applies only to users who are running a version of SL1 prior to 11.2.0. If you are running SL1 11.2.0 or later, you can determine which databases and tables are included or excluded in configuration backups by going to the **Backup Management** page (System > Settings > Backup) and clicking [Advanced Settings] in the Configuration Backup pane. For more information, see the section on Defining a Configuration Backup.

NOTE: This process does not apply to full or disaster recovery backups.

To see which databases and tables are included in configuration backups in your environment:

Navigate to the **Database Tool** page (System > Tools > DB Tool)

NOTE: The **Database Tool** page displays only for users that have sufficient permissions to access that page.

2. In the **Select Database** field, select Master.

Configuring Backups 324

3. In the "SQL Query" field, enter this query:

```
SELECT backup db list FROM 'system settings backup' WHERE id = 1
```

To see which databases and tables are excluded in configuration backups in your environment:

- 1. Navigate to the **Database Tool** page (System > Tools > DB Tool)
- 2. In the Select Database field, select Master.
- 3. In the "SQL Query" field, enter this query:

```
SELECT backup_cb_table_exclude FROM 'system_settings_backup' WHERE id
= 1
```

Defining a Configuration Backup

To define and schedule a configuration backup:

- 1. Go to the **Backup Management** page (System > Settings > Backup).
- 2. In the **Configuration Backup** pane, provide values in the following fields:
 - Every. Together with the Interval field, specifies the frequency of the backup.
 - *Interval*. Together with the *Every* field, you must specify how frequently SL1 should automatically execute a configuration backup. Your choices are:
 - ° Disabled. Configuration backups are disabled. If you want to run on-demand configuration backups only, you do not need to change this setting.
 - ° Day. SL1 will execute configuration backups daily as specified (for example, every 2 days).
 - Week. SL1 will execute configuration backups weekly as specified (for example, every 2 weeks).
 - Month. SL1 will execute configuration backups monthly as specified (for example, every 1 month).
 - Start Time / Date. If you enabled configuration backups, you must specify the start time. You must specify the date on which you want configuration backups to begin, as well as the time of day you want the backups to run. For example, you might want to run configuration backups during a maintenance window late at night. Click the field to open a calendar and time selector.
 - **Timezone**. Optional. Specify the timezone to use when running a backup. The default is UTC. Use the drop-down list to select the timezone.
 - Configuration Credentials. Select the credential you created for SL1 to use to connect to your external system (NFS, SMB, or S3). For more information, see Creating a Backup Credential.

- **Configuration Protocol**. Specify the type of external system where the configuration backup will be stored. Choices are:
 - NFS-Remote. When you select this option, SL1 stores the configuration backup on an NFS share.

NOTE: If you select the *NFS-remote* option, and your NFS share is hosted on a Solaris system, you must perform the steps listed in the *Additional Configuration for Solaris NFS Mounts* section.

- SMB-Remote. When you select this option, SL1 stores the configuration backup on an SMB share
- ° S3. When you select this option, SL1 stores the configuration backup in an S3 bucket.
- Configuration Subdirectory. Specify a directory on the NFS or SMB share or S3 service in which you would like to store the configuration backup. When entering the subdirectory path, include the leading slash ("/"). On the remote share, the current Unix time will be appended to the directory name to ensure the directory name is unique each time the backup runs.

NOTE: You will need this value as well as your backup credential information and any mount options that you specify in step 3 below if you mount the backup to an NFS or SMB share

Configuration Backup on DR. Select this checkbox if you want to perform configuration backups
from the Disaster Recovery Database Server. This alternative method to backing up SL1 can reduce
performance issues during backup for users with large systems and very large backup files. For
more information, see the section on Performing Configuration and Full Backups on the DR
Database Server.

- 3. To access additional configuration options for this backup, click [Advanced Settings]. The set of advanced options that appears are the same fields that you would have populated using SQL queries in versions of SL1 older than 11.2.0. These advanced fields refer to the column names in the SL1 Database:
 - backup smb mount options
 - backups nfs mount options
 - backup cmd options
 - comp cmd options
 - backup db list (JSON)
 - backup cb table exclude (JSON)

NOTE: For more information about these Advanced Settings, contact ScienceLogic Support.

NOTE: You will need the values from the mount option fields as well as your backup credential information and the value you entered in the Configuration Subdirectory field in step 2 above when mounting an NFS or SMB share.

- 4. Click [Save]. SL1 will execute the configuration backup at the specified interval, starting on the date you specified in the Start Time / Date field and using the time you specified in the Start Time / Date field.
- 5. To run the backup immediately, click the [Backup Now] button under Configuration Backup in the Immediate Backup section of the Backup Management page. SL1 will run the backup immediately, as well as running the scheduled backup you configured in this procedure.

Defining a Full Backup

Full backups include all databases and tables. SL1 automatically launches this backup at the frequency and time you specify.

To define and schedule a full backup:

- 1. Go to the **Backup Management** page (System > Settings > Backup).
- 2. In the **Full Backup** pane, provide values in the following fields:
 - Every. Together with the Interval field, specifies the frequency of the backup.
 - Interval. Together with the Every field, specifies how frequently SL1 should automatically execute a
 full backup. Your choices are:
 - Disabled. Full backups are disabled.
 - Day. SL1 will execute full backups daily as specified (for example, every 2 days).
 - ^o Week. SL1 will execute full backups weekly as specified (for example, every 2 weeks).
 - Month. SL1 will execute full backups monthly as specified (for example, every 1 month).

- Start Time / Date. If you enabled full backups, you must specify the start time. You must specify the date on which you want configuration backups to begin, as well as the time of day you want the backups to run. For example, you might want to run configuration backups during a maintenance window late at night. Click the field to open a calendar and time selector.
- *Timezone*. Optional. Specify the timezone to use when running a backup. The default is UTC. Use the drop-down list to select the timezone.
- Full Credentials. Select the credential you created for SL1 to use to connect to your external system (NFS, SMB, or S3). For more information, see Creating a Backup Credential.
- Full Protocol. Specify the type of external system where the full backup will be stored. Choices are:
 - ° NFS-Remote. When you select this option, SL1 stores the backup on an NFS share.

NOTE: If you select the *NFS-remote* option, and your NFS share is hosted on a Solaris system, you must perform the steps listed in the *Additional Configuration for Solaris NFS Mounts* section.

- ° SMB-Remote. When you select this option, SL1 stores the backup on an SMB share.
- ° S3. When you select this option, SL1 stores the backup in an S3 bucket.
- Full Subdirectory. Specify a directory on the NFS or SMB share or S3 service in which you would like to store the full backup. When entering the subdirectory path, include the leading slash ("/"). On the remote share, the current Unix time will be appended to the directory name to ensure the directory name is unique each time the backup runs.

NOTE: You will need this value as well as your backup credential information and any mount options that you specify in step 3 below if you mount the backup to an NFS or SMB share.

- Full Backup on DR. Select this checkbox if you want to perform full backups from the Disaster
 Recovery Database Server. This alternative method to backing up SL1 can reduce performance issues
 during backup for users with large systems and very large backup files. For more information, see the
 section on Performing Configuration and Full Backups on the DR Database Server.
- **Full Retention Period**. Specify in days how long you want SL1 to keep full backups before deleting them. SL1 will keep the number you specify, plus one additional backup. The default is 0.

NOTE: This field displays in SL1 version 11.2.0 and above. If you are running a version prior to 11.2.0, you can specify the retention period for full backups *using the Database Tool*.

- 3. To access additional configuration options for this backup, click [Advanced Settings]. The set of advanced options that appears are the same fields that you would have populated using SQL queries in versions of SL1 older than 11.2.0. These advanced fields refer to the column names in the SL1 Database:
 - backup smb mount options
 - backups nfs mount options
 - backup_cmd_options
 - comp cmd options

Also, the *Custom mariabackup Options* field lets you specify one or more custom backup options. For details on these options, see https://mariadb.com/kb/en/mariabackup-options/.

NOTE: For more information about these Advanced Settings, contact ScienceLogic Support.

- 4. Click [Save]. SL1 will execute the full backup at the frequency and time you specified in the Every, Interval, and Start Time/Date fields.
- 5. To run the backup immediately, click the [Backup Now] button under Full Backup. SL1 will immediately run the backup and will still run the backup at the frequency and time you specified in the Backup Frequency and Start Time fields.

Defining a Disaster Recover Backup

To define and schedule a DR backup:

- 1. Go to the **Backup Management** page (System > Settings > Backup).
- 2. In the **DR Backup** pane, provide values in the following fields:
 - Every. Together with the *Interval* field, specifies the frequency of the backup.
 - Interval. Together with the Every field, you must specify how frequently SL1 should automatically execute a DR backup. Your choices are:
 - Disabled. DR backups are disabled. If you want to run on-demand DR backups only, you do not need to change this setting.
 - ^o Day. SL1 will execute DR backups daily as specified (for example, every 2 days).
 - Week. SL1 will execute DR backups weekly as specified (for example, every 2 weeks).
 - Month. SL1 will execute DR backups monthly as specified (for example, every 1 month).

- Start Time/Date. If you enabled DR backups, you must specify the start time. You must specify the date on which you want DR backups to begin, as well as the time of day you want the backups to run. For example, you might want to run DR backups during a maintenance window late at night. Click the field to open a calendar and time selector.
- **Timezone**. Optional. Specify the timezone to use when running a backup. The default is UTC. Use the drop-down list to select the timezone.
- DR Credentials. Select the credential you created for SL1 to use to connect to your external system (NFS, SMB, or S3). For more information, see Creating a Backup Credential.
- DR Protocol. Specifies where SL1 should store the DR backups. Choices are:
 - ° NFS-Remote. When you select this option, SL1 stores the DR backup on an NFS share.

NOTE: If you select the NFS-remote option, and your NFS mount is hosted on a Solaris system, you must perform the steps listed in the Additional Configuration for Solaris NFS Mounts section of this chapter.

- ° SMB-Remote. When you select this option, SL1 stores the DR backup on an SMB share.
- S3. When you select this option, SL1 stores the DR backup in an S3 bucket.
- **DR Subdirectory**. Specify a directory on the NFS or SMB share or S3 service in which you would like to store the DR backup. When entering the subdirectory path, include the leading slash ("/"). On the remote share, the current Unix time will be appended to the directory name to ensure the directory name is unique each time the backup runs.

NOTE: You will need this value as well as your backup credential information and any mount options that you specify in step 3 below if you mount the backup to an NFS or SMB share.

• **DR Retention Period**. Specify in days how long you want SL1 to keep DR backups before deleting them. SL1 will keep the number you specify, plus one additional backup. The default is 0.

NOTE: This field displays in SL1 version 11.2.0 and above. If you are running a version prior to 11.2.0, you can specify the retention period for DR backups *using the Database Tool*.

- 3. To access additional configuration options for this backup, click [Advanced Settings]. The set of advanced options that appears are the same fields that you would have populated using SQL queries in versions of SL1 older than 11.2.0. These advanced fields refer to the column names in the SL1 Database:
 - backup smb mount options
 - backups nfs mount options
 - backup cmd options
 - comp cmd options

NOTE: For more information about these Advanced Settings, contact ScienceLogic Support.

- 4. Click [Save]. SL1 will execute the DR backup at the frequency and time you specified in the *Backup Frequency* and *Start Time* fields.
- 5. To run the backup immediately, click the [Backup Now] button under *DR Backup*. SL1 will immediately run the backup and will still run the backup at the frequency and time you specified in the *Backup Frequency* and *Start Time* fields.

Mounting Backup Files

If your backup is stored in an NFS or SMB share, then you must mount the backup before you can use it to restore your SL1 system. This section describes how to mount these two share types.

Mounting NFS Shares

Before beginning this process, you should have the following information:

- The IP address that is defined in the backup credential
- Based on which type of backup files you are mounting, the mount directory that is defined in the
 Configuration Subdirectory, Full Subdirectory, or DR Subdirectory field on the Backup Management
 page (System > Settings > Backup)
- Based on which type of backup files you are mounting, the value from the Configuration NFS Mount
 Options, Full NFS Mount Options, or DR NFS Mount Options field, which you can access by clicking
 [Advanced Settings] on the Backup Management page (System > Settings > Backup)

To mount a remote NFS share:

1. Execute the following command to mount the remote NFS share:

```
/bin/mount -t nfs <IP from backup credential>:/<subdirectory> /mnt -o <NFS mount options>
```

where:

- <IP from backup credential> is the IP address you defined in your backup credential.
- <subdirectory> is the mount directory that is defined in the Configuration Subdirectory, Full
 Subdirectory, or DR Subdirectory field on the Backup Management page (System > Settings >
 Backup) to store the backup.
- <NFS mount options> is the value from the Configuration NFS Mount Options field, which
 you can access by clicking [Advanced Settings] on the Backup Management page (System >
 Settings > Backup).

For example:

```
/bin/mount -t nfs 10.64.70.63:/backups /mnt -o lookupcache=none
```

2. After entering one of the above commands, if you are prompted to provide a password, enter the password that you defined in your backup credential.

Mounting SMB Shares

Before beginning this process, you should have the following information:

- The IP address and username that is defined in the backup credential
- Based on which type of backup files you are mounting, the mount directory that is defined in the
 Configuration Subdirectory, Full Subdirectory, or DR Subdirectory field on the Backup Management
 page (System > Settings > Backup)
- Based on which type of backup files you are mounting, the value from the **Configuration SMB Mount Options, Full SBM Mount Options**, or **DR SMB Mount Options** field, which you can access by clicking

 [Advanced Settings] on the **Backup Management** page (System > Settings > Backup)

To mount a remote SMB share:

Mounting Backup Files 332

1. Execute the following command to mount the remote SMB share:

```
/bin/mount -t cifs //<IP from backup credential>/<subdirectory> /mnt -o user=<username from backup credential>,<SMB mount options>
```

where:

- <IP from backup credential> is the IP address you defined in your backup credential.
- <username from backup credential> is the username you defined in your backup credential.
- <subdirectory> is the mount directory that is defined in the Configuration Subdirectory, Full Subdirectory, or DR Subdirectory field on the Backup Management page (System > Settings > Backup) to store the backup.
- < SMB mount options > is the value from the Configuration SMB Mount Options, Full SBM Mount Options, or DR SMB Mount Options field, which you can access by clicking [Advanced Settings] on the Backup Management page (System > Settings > Backup).

For example:

```
/bin/mount -t cifs //10.64.70.48/Lab_Backups /mnt -o
user=administrator,iocharset=utf8,file_mode=0777,dir_
mode=0777,uid=600,gid=607,setuids,noperm,sec=ntlm,vers=1.0
```

2. After entering the command, if you are prompted to provide a password, enter the password that you defined in your backup credential.

Restoring Backups

This section describes how to restore the following backup types:

- Configuration backup from an S3 bucket
- Configuration backup from a remote NFS or SMB share
- Full backup from an S3 bucket
- Full backup from a remote NFS or SMB share
- DR backup from an S3 bucket
- DR backup from a remote NFS or SMB share

Restoring a Configuration Backup from an S3 Bucket

If you have performed configuration backups, you can restore your system from a configuration backup in the event of data corruption or other failure. The configuration backup file contains one SQL (.**sql**) file for each database that was included in the configuration backup.

NOTE: These steps assume that the Database Server to which you are restoring the backup has not been previously configured and is on the same platform revision number as the Database Server used to create the backup file.

NOTE: To complete these steps, you must be familiar with how to edit a file using the vi text editor. If you need assistance with these steps, please contact ScienceLogic Support.

To restore a database using configuration backup files that were stored on an S3 storage service:

- 1. Either go to the console of the Database Server or use SSH to access the server.
- 2. Log in as user **em7admin** and assume root user privileges by using the following command:

```
sudo -s
```

3. Execute the following commands at the command line to uncompress the backup file, where < new_subdirectory > is a directory you create that will be the destination for your uncompressed files:

```
mkdir /data.local/db/<new_subdirectory>
cd /data.local/db/<new_subdirectory>
```

For example:

```
mkdir /data.local/db/my_backups

cd /data.local/db/my_backups
```

4. Execute the following commands:

```
export RCLONE_CONFIG_BACKUP_BUCKET_ACL="private"

export RCLONE_CONFIG_BACKUP_CHUNK_SIZE="128Mi"

export RCLONE_CONFIG_BACKUP_TYPE="s3"

export RCLONE_CONFIG_BACKUP_UPLOAD_CONCURRENCY="4"

export RCLONE_CONFIG_BACKUP_PROVIDER="<--- Provider --->"

export RCLONE_CONFIG_BACKUP_ACCESS_KEY_ID="<--- Access Key ID --->"

export RCLONE_CONFIG_BACKUP_SECRET_ACCESS_KEY="<--- Secret Access Key
--->"

export RCLONE_CONFIG_BACKUP_ENDPOINT="<--- Endpoint URL --->"

export RCLONE_CONFIG_BACKUP_REGION="<--- Region --->"

export RCLONE_CONFIG_CRYPT_TYPE="crypt"

export RCLONE_CONFIG_CRYPT_TYPE="crypt"

export RCLONE_CONFIG_CRYPT_DIRECTORY_NAME_ENCRYPTION="false"

export RCLONE_CONFIG_CRYPT_FILENAME_ENCRYPTION="off"

export RCLONE_CONFIG_CRYPT_FILENAME_ENCRYPTION="off"
```

```
Folder --->"

export RCLONE_CONFIG_CRYPT_PASSWORD="`rclone obscure '<--- Encryption

Password --->'`"

export RCLONE_CONFIG_CRYPT_PASSWORD2="`rclone obscure '<---

Encryption Salt --->'`"

rclone cat crypt:<--- File Name without the .bin --->|pigz -d|tar xv
```

5. Your target directory now contains configuration backup files. Copy these backup files to their original locations. For example:

```
cp -r opt /
cp -r var /
cp -r etc /
cp -r usr /
```

6. To restore a database, execute the following command using the username of a user that has administrative privileges in MySQL:

```
silo_mysql <name_of_database> -u <username> -p<password> < <name_of_
database>.sql
```

```
NOTE: Do not include a space between -p and the password.
```

For example, to restore the database "master" as the user "root" with the password "examplepassword", perform the following command:

```
silo_mysql master -u root -pexamplepassword < master.sql
```

- 7. To restore all the databases that are included in the backup file, repeat step 6 for each .sql file.
- 8. Re-license the Database Server using the standard licensing procedure. For details, see the section on *Licensing and Configuring an Appliance* in the *Installation and Initial Configuration* manual.

Restoring a Configuration Backup from a Remote NFS or SMB Share

If you have performed configuration backups, you can restore your system from a configuration backup in the event of data corruption or other failure. The configuration backup file contains one SQL (.sql) file for each database that was included in the configuration backup.

NOTE: These steps assume that the Database Server has not been previously configured.

NOTE: To complete these steps, you must be familiar with how to edit a file using the vi text editor. If you need assistance with these steps, please contact ScienceLogic Support.

To restore a database using the backup file:

1. Either go to the console of the Database Server or use SSH to access the server.

NOTE: The Database Server to which you are restoring the backup must be at the same revision number as the Database Server that created the backup file.

2. Log in as user **em7admin** and assume root user privileges by using the following command:

```
sudo -s
```

3. Execute the following commands at the command line to uncompress the backup file, where < new_subdirectory > is a directory you create that will be the destination for your uncompressed files:

```
mkdir /data.local/db/<new_subdirectory>
```

```
cd /data.local/db/<new_subdirectory>
```

For example:

```
mkdir /data.local/db/my backups
```

```
cd /data.local/db/my backups
```

4. Execute the following command to extract the backup into your directory, where < full path and filename for backup.tgz> is the location and name of your backup file:

```
pigz -dc <full path and file name for backup.tgz> | tar xv
```

For example:

```
pigz -dc /mnt/db1 config 2021-02-01 21-00-00.tgz | tar xv
```

5. Your target directory will now contain one SQL file for each database included in the backup. Copy the configuration backup files to their original locations. For example:

```
# cp -r opt /
```

cp -r var /

cp -r etc /

cp -r usr /

6. To restore a database, execute the following command using the username and password of a user that has administrative privileges in MySQL:

```
silo_mysql <name_of_database> -u <username> -p<password> < <name_of_
database>.sql
```

NOTE: Do not include a space between -p and the password.

For example, to restore the database "master" as the user "root" with the password "examplepassword", perform the following command:

```
silo mysql master -u root -pexamplepassword < master.sql</pre>
```

- 7. To restore all the databases that are included in the backup file, repeat step 8 for each .sql file.
- 8. Re-license the Database Server using the standard licensing procedure. For details, see the section on Licensing and Configuring an Appliance in the Installation and Initial Configuration manual.

Restoring a Full Backup from an S3 Bucket

NOTE: These steps assume that the Database Server to which you are restoring the backup has not been previously configured and is on the same platform revision number as the Database Server used to create the backup file.

NOTE: To complete these steps, you must be familiar with how to edit a file using the vi text editor. If you need assistance with these steps, please contact ScienceLogic Support.

To restore a SL1 system using a full backup file from an S3 bucket:

- 1. Either go to the console of the Database Server where you want to restore the backup, or use SSH to log in to the Database Server.
- 2. Log in as user **em7admin** and then assume root privileges:

```
sudo -s
```

3. Execute the following commands:

WARNING: Executing this command will stop the database. SL1 will not be operational until you complete the restore procedure.

```
siloctl --full stop
systemctl stop mariadb
rm -rf /data.local/db/*
cd /data.local/db/
export RCLONE_CONFIG_BACKUP_BUCKET_ACL="private"
export RCLONE_CONFIG_BACKUP_CHUNK_SIZE="128Mi"
```

```
export RCLONE CONFIG BACKUP TYPE="s3"
export RCLONE CONFIG BACKUP UPLOAD CONCURRENCY="4"
export RCLONE CONFIG BACKUP PROVIDER="<--- Provider --->"
export RCLONE CONFIG BACKUP ACCESS KEY ID="<--- Access Key ID --->"
export RCLONE CONFIG BACKUP SECRET ACCESS KEY="<--- Secret Access Key
export RCLONE CONFIG BACKUP ENDPOINT="<--- Endpoint URL --->"
export RCLONE CONFIG BACKUP REGION="<--- Region --->"
export RCLONE CONFIG CRYPT TYPE="crypt"
export RCLONE CONFIG CRYPT DIRECTORY NAME ENCRYPTION="false"
export RCLONE CONFIG CRYPT FILENAME ENCRYPTION="off"
export RCLONE CONFIG CRYPT REMOTE="backup:/<--- Bucket --->/<---
Folder --->"
export RCLONE CONFIG CRYPT PASSWORD="`rclone obscure '<--- Encryption
Password --->'`"
export RCLONE CONFIG CRYPT PASSWORD2="`rclone obscure '<---
Encryption Salt --->'`"
time rclone cat crypt:<--- Full Backup File Name without the .bin ---
>|pigz -d|mbstream -vvv -x -C .
```

4. Execute the following command, where *<directory for data extraction* is the directory you created in the previous step:

```
more /<directory for data extraction>/backup-my.cnf
```

- 5. Locate the line that looks like the following. Copy or write down the exact text that appears, such as: innodb_data_file_path=ibdata1:354M; ibdata2:500M:autoextend:max:8925M
- Execute the following command to edit the /etc/my.cnf.d/silo_mysql.cnf file: vimysql
- 7. Add the line you copied in Step 5 to the **mysql.siteconfig** file, such as: innodb_data_file_path=ibdata1:354M; ibdata2:500M:autoextend:max:8925M
- 8. Save the file and exit the editor:

```
:wq
```

9. Execute the following command to build the updated configuration file:

```
vimysql -f
```

10. Execute the following commands:

NOTE: The following process can take a long time to complete. To ensure the command is not interrupted, you should run the command in a "tmux" session.

To do so:

• Open a tmux session:

tmux

• Execute the following commands:

```
mariabackup --prepare -use-memory=<80% of available memory> --
target- dir=/data.local.db

cd /data.local/db

chown -R mysql.mysql *

systemctl start mariadb
```

NOTE: These commands assume you have changed directories to the directory that contains the extracted backup files. If you want to run these commands from a location other than the location of the extracted backup files, then you must enter a value after "target-dir=" to point to the directory where the extracted files are located. To learn more about MariaBackup, see https://mariadb.com/kb/en/full-backup-and-restore-with-mariabackup/.

NOTE: Depending on the size of the backup, the mariabackup command might take a long time to complete.

11. Because a full database restoration requires the database username and password, you must check the MariaDB username and password that are stored in the **silo.conf** file.

NOTE: If the backup was taken from an SL1 system installed from or upgraded to version 11.3.0 or later, the username will be **clientdbuser**.

If the backup was taken from an SL1 system that was installed from or last upgraded to a version prior to 11.3.0, the username will be **root**.

• To check the username and password in the **silo.conf** file, enter the following command:

visilo

- Check (and if necessary, update) the values in the abuser, abpasswd, and ap_pass fields in both the [LOCAL] and [CENTRAL] sections.
- Save and close the file:

:wq

NOTE: Upon saving, visilo will validate that the MariaDB passwords work. If the passwords fail, ensure that you are entering the correct ones. If the passwords are unknown, you must perform the password recovery and reset procedure described in the section **Changing the MariaDB Password on SL1 Appliances**.

12. Restart SL1:

siloctl --full start

13. Re-license the Database Server using the standard licensing procedure. For details, see the section on "Licensing and Configuring an Appliance" in the *Installation and Initial Configuration* manual.

NOTE: The start process from step 12 will fail and restart until your SL1 system is licensed. This is expected behavior.

Restoring a Full Backup from a Remote NFS or SMB Share

Before beginning this process, you should have the following information:

- The IP address and username that is defined in the backup credential
- The mount directory that is defined in the *Full Subdirectory* field on the *Backup Management* page (System > Settings > Backup)
- Based on which share type you are mounting the backup to, the value from either the Full NFS Mount
 Options or Full SMB Mount Options field, which you can access by clicking [Advanced Settings] on the
 Backup Management page (System > Settings > Backup)

NOTE: The following steps assume that the Database Server has not been previously configured.

NOTE: To complete these steps, you must be familiar with how to edit a file using the vi text editor. If you need assistance with these steps, please contact ScienceLogic Support.

To restore a SL1 system using a full backup file from a remote NFS or SMB share, perform the following steps:

1. Either go to the console of the Database Server where you want to restore the backup, or use SSH to log in to the Database Server.

NOTE: The Database Server to which you are restoring the backup must be at the same revision number as the Database Server that created the backup file.

2. Log in as user **em7admin** and then assume root privileges:

```
sudo -s
```

3. Stop MariaDB on the Database Server to which you are restoring the backup and remove the existing files in the /data.local/db directory used by MariaDB.

WARNING: Executing this command will stop the database. SL1 will not be operational until you complete the restore procedure.

4. Execute the following commands:

```
siloctl --full stop

systemctl stop mariadb

rm -rf /data.local/db/*
```

- 5. On the Database Server to which you are restoring the backup, extract the database files from the backup files into /data.local/db. This process can take a long time to complete. To ensure the command is not interrupted, you should run the command in a "tmux" session.
 - Open a tmux session:

tmux

• Open the /data.local/db directory:

```
cd/data.local/db
```

- Execute one of the following commands to mount the remote NFS or SMB share, where:
 - <IP from backup credential> is the IP address you defined in your backup
 credential.
 - «username from backup credential» is the username you defined in your backup
 credential.
 - * <full subdirectory> is the directory on a remote NFS, SMB, or S3 mount that you specified in the *Full Subdirectory* field on the *Backup Management* page (System > Settings > Backup) to store the backup.
 - < full NFS mount options > is the value from the Full NFS Mount Options field,
 which you can access by clicking [Advanced Settings] on the Backup Management page
 (System > Settings > Backup).
 - < full SMB mount options > is the value from the Full SMB Mount Options field,
 which you can access by clicking [Advanced Settings] on the Backup Management page
 (System > Settings > Backup).
 - ° For NFS, execute the following command:

```
/bin/mount -t nfs <IP from backup credential>:/<full subdirectory> /mnt -o <full NFS mount options>
```

For example:

```
/bin/mount -t nfs 10.64.70.63:/backups /mnt -o lookupcache=none
```

° For SMB, execute the following command:

```
/bin/mount -t cifs //<IP from backup credential>/<full subdirectory> /mnt -o user=<username from backup credential>,<full SMB mount options>
```

For example:

```
/bin/mount -t cifs //10.64.70.48/Lab_Backups /mnt -o user=administrator,iocharset=utf8,file_mode=0777,dir_ mode=0777,uid=600,gid=607,setuids,noperm,sec=ntlm,vers=1.0
```

• After entering one of the above commands, if you are prompted to provide a password, enter the password that you defined in your backup credential.

• Execute the following command to extract the backup into your directory, where < full path and filename for backup.gz > is the location and name of your backup file:

```
pigz -dc <full path and file name for backup.gz> \mid mbstream -x - C .
```

For example:

```
pigz -dc /mnt/db1_full_2021-02-01_21-00-00.gz | mbstream -x -C .
```

- Press "Ctrl + A" and then press "d" to detach from the session.
- Monitor the progress. After the mbstream command is complete, execute the following command:

```
watch -n1 'ps -ef |grep "[m]bstream";'
```

- 6. Update the MariaDB configuration. To do so:
 - Look up the maximum size limit for the tablespace file from the last time the backup was taken:

```
grep "autoextend:max" /data.local/db/backup-my.cnf
```

 Copy or write down the output exactly as it appears, because you will need it in a later step. For example:

```
innodb_data_file_
path=ibdata1:354M;ibdata2:500M:autoextend:max:8925M
```

• Execute the following command to open the MariaDB configuration:

```
vimysql
```

- In the editor, find a line that is similar to the "innodb_data_file_path" output from the example above and replace it with the line you copied or wrote down from that step.
- Save the file and exit the editor:

```
:wq
```

• Execute the following command to build the updated configuration file:

```
vimysql -f
```

7. Ensure that the database files are point-in-time consistent:

```
mariabackup --prepare --use-memory=<80% of available memory> -- target-dir=/data.local/db
```

NOTE: This command assumes you have changed to the directory that contains the extracted backup files. If you want to run the command from a different directory, then you must enter a value after "target-dir=" to point to the directory where the extracted files are located. To learn more about MariaBackup, see https://mariadb.com/kb/en/full-backup-and-restore-with-mariabackup/.

NOTE: Depending on the size of the backup, the mariabackup command might take a long time to complete.

6. Ensure you have proper ownership on the files:

```
chown -R mysql:mysql /data.local/db/*
```

7. Start Maria DB on the target Database Server:

```
systemctl start mariadb
```

8. Because a full database restoration requires the database username and password, you must check the MariaDB username and password that are stored in the **silo.conf** file.

NOTE: If the backup was taken from an SL1 system installed from or upgraded to version 11.3.0 or later, the username will be **clientdbuser**.

If the backup was taken from an SL1 system that was installed from or last upgraded to a version prior to 11.3.0, the username will be **root**.

• To check the username and password in the **silo.conf** file, enter the following command:

```
visilo
```

- Check (and if necessary, update) the values in the dbuser, dbpasswd, and ap_pass fields in both the [LOCAL] and [CENTRAL] sections.
- Save and close the file:

:wq

NOTE: Upon saving, visilo will validate that the MariaDB passwords work. If the passwords fail, ensure that you are entering the correct ones. If the passwords are unknown, you must perform the password recovery and reset procedure described in the section Changing the MariaDB Password on SL1 Appliances.

9. Restart SL1:

```
siloctl --full start
```

10. Re-license the Database Server using the standard licensing procedure. For details, see the section on Licensing and Configuring an Appliance in the Installation and Initial Configuration manual.

NOTE: The process from step 9 will fail and restart until your SL1 system is licensed. This is expected behavior.

Restoring a DR Backup from an S3 Bucket

NOTE: These steps assume that the Database Server to which you are restoring the backup has not been previously configured and is on the same platform revision number as the Database Server used to create the backup file.

NOTE: To complete these steps, you must be familiar with how to edit a file using the vi text editor. If you need assistance with these steps, please contact ScienceLogic Support.

To restore a Database Server using a DR backup file from an S3 bucket, perform the following steps:

- 1. Either go to the console of the Database Server where you want to restore the backup or use SSH to access the Database Server.
- 2. Log in as user **em7admin** and sudo to the root account:

```
sudo -s
```

3. Execute the following commands:

WARNING: Executing this command will stop the database. SL1 will not be operational until you complete the restore procedure.

```
siloctl --full stop
systemctl stop mariadb
rm -rf /data/db/*
cd /data/db
export RCLONE_CONFIG_BACKUP_BUCKET_ACL="private"
export RCLONE_CONFIG_BACKUP_CHUNK_SIZE="128Mi"
export RCLONE_CONFIG_BACKUP_TYPE="s3"
export RCLONE_CONFIG_BACKUP_UPLOAD_CONCURRENCY="4"
```

```
export RCLONE CONFIG BACKUP PROVIDER="<--- Provider --->"
export RCLONE CONFIG BACKUP ACCESS KEY ID="<--- Access Key ID --->"
export RCLONE CONFIG BACKUP SECRET ACCESS KEY="<--- Secret Access Key
--->"
export RCLONE CONFIG BACKUP ENDPOINT="<--- Endpoint URL --->"
export RCLONE CONFIG BACKUP REGION="<--- Region --->"
export RCLONE CONFIG CRYPT TYPE="crypt"
export RCLONE CONFIG CRYPT DIRECTORY NAME ENCRYPTION="false"
export RCLONE CONFIG CRYPT FILENAME ENCRYPTION="off"
export RCLONE CONFIG CRYPT REMOTE="backup:/<--- Bucket --->/<---
Folder --->"
export RCLONE CONFIG CRYPT PASSWORD="`rclone obscure '<--- Encryption
Password --->'`"
export RCLONE CONFIG CRYPT PASSWORD2="`rclone obscure '<---
Encryption Salt --->'`"
time rclone cat crypt:<--- Full Backup File Name without the .bin ---
>|pigz -d|mbstream -vvv -x -C .
rclone cat crypt:<--- File Name without the .bin --->|pigz -d|tar xv
```

NOTE: This process can take a long time to complete. To ensure the command is not interrupted, you should run the command in a "tmux" session.

4. Execute the following command, where *<directory for data extraction>* is the directory you created in the previous step:

```
more /<directory for data extraction>/backup-my.cnf
```

5. Locate the line that looks like the following. Copy or write down the exact text that appears, such as:

```
innodb data file path=ibdata1:354M;ibdata2:500M:autoextend:max:8925M
```

6. Execute the following command to edit the /etc/my.cnf.d/silo mysql.cnf file:

```
vimysql
```

7. Add the line you copied in Step 5 to the **mysql.siteconfig** file, such as:

```
innodb_data_file_path=ibdata1:354M;ibdata2:500M:autoextend:max:8925M
```

8. Save the file and exit the editor:

```
:wq
```

9. Execute the following command to build the updated configuration file:

```
vimysql -f
```

10. Execute the following commands:

```
mariabackup --prepare --target-dir= <-use-memory=<80% of available
memory>
```

cd /data.local/db

chown -R mysql.mysql *

systemctl start mariadb

NOTE: These commands assume you have changed directories to the directory that contains the extracted backup files. If you want to run these commands from a location other than the location of the extracted backup files, then you must enter a value after "target-dir=" to point to the directory where the extracted files are located. To learn more about MariaBackup, see https://mariadb.com/kb/en/full-backup-and-restore-with-mariabackup/.

NOTE: Depending on the size of the backup, the mariabackup command might take a long time to complete.

11. Because a full database restoration requires the database username and password, you must check the MariaDB username and password that are stored in the **silo.conf** file.

NOTE: If the backup was taken from an SL1 system installed from or upgraded to version 11.3.0 or later, the username will be **clientdbuser**.

If the backup was taken from an SL1 system that was installed from or last upgraded to a version prior to 11.3.0, the username will be **root**.

• To check the username and password in the **silo.conf** file, enter the following command:

visilo

- Check (and if necessary, update) the values in the dbuser, dbpasswd, and ap_pass fields in both the [LOCAL] and [CENTRAL] sections.
- Save and close the file:

:wq

NOTE: Upon saving, visilo will validate that the MariaDB passwords work. If the passwords fail, ensure that you are entering the correct ones. If the passwords are unknown, you must perform the password recovery and reset procedure described in the section **Changing the MariaDB Password on SL1 Appliances**.

12. Execute the following commands to restart SL1 and the database:

```
siloctl --full start
```

13. Re-license the Database Server using the standard licensing procedure. For details, see the section on "Licensing and Configuring an Appliance" in the *Installation and Initial Configuration* manual.

NOTE: The process from step 12 will fail and restart until your SL1 system is licensed. This is expected behavior

Restoring a DR Backup from a Remote NFS or SMB Share

To restore a Database Server using a DR backup file, perform the following steps:

NOTE: These steps assume that the Database Server has not been previously configured.

1. The Database Server to which you are restoring the backup must be at the same revision number as the Database Server that created the backup file.

- 2. Either go to the console of the Database Server where you want to restore the backup or use SSH to access the Database Server.
- 3. Log in as user **em7admin** and sudo to the root account:

```
sudo -s
```

4. Execute the following commands:

WARNING: Executing this command will stop the database. SL1 will not be operational until you complete the restore procedure.

```
siloctl --full stop

systemctl stop mariadb

rm -rf /data/db/*
```

5. Execute the following commands, substituting the full pathname of your backup file:

```
cd /data/db

pigz -dc <full path and name to backup file.tgz> | tar xvf -

mv /data/db/data/db/* .

rm -rf /data/db/data

cp /data/db/etc/my.cnf.d/silo_mysql.cnf /root/silo_mysql.bak

rm -rf /data/db/etc

chown -R mysql:mysql /data/db/*
```

6. Execute the following commands to restart SL1 and the database:

```
siloctl --full start
systemctl start mariadb
```

Retaining Backups

This section describes how to retain full and DR backups.

349 Retaining Backups

Retaining Full Backups

NOTE: This section applies only to users who are running a version of SL1 prior to 11.2.0. If you are running SL1 11.2.0 or later, you can set the retention value in the *Full Retention Period* field on the *Backup Management* page (System > Settings > Backup). For more information, see the section on *Defining a Full Backup*.

To specify the number of full backups to retain in SL1 versions prior to 11.2.0:

- 1. Go to the **Database Tool** page (System > Tools > DB Tool).
- 2. In the SQL Query field, enter the following:

```
UPDATE master.system_settings_backup SET backup_retention = <number
of backups to retain> WHERE id = 2
```

3. For example, the following command would retain five full backups, the last four plus the current backup:

```
UPDATE master.system_settings_backup SET backup_retention = 4 WHERE
id = 2
```

4. Click [Go]. SL1 will create an entry in /var/log/em7/silo.log when a backup is deleted.

Retaining DR Backups

NOTE: This section applies only to users who are running a version of SL1 prior to 11.2.0. If you are running SL1 11.2.0 or later, you can set the retention value in the *DR Retention Period* field on the *Backup Management* page (System > Settings > Backup). For more information, see the section on *Defining a Disaster Recovery Backup*.

To specify the number of DR backups to retain in SL1 versions prior to 11.2.0:

- 1. Go to the **Database Tool** page (System > Tools > DB Tool).
- 2. In the SQL Query field, enter the following:

```
UPDATE master.system_settings_backup SET backup_retention = <number
of backups to retain> WHERE id = 3
```

3. For example, the following command would retain five DR backups, the last four and the current backup:

```
UPDATE master.system_settings_backup SET backup_retention = 4 WHERE
id = 3
```

4. Click [Go]. SL1 will create an entry in /var/log/em7/silo.log when a backup is deleted.

Retaining Backups 350

Additional Configuration for Solaris NFS Remote Shares

To use the NFS-remote backup protocol with an NFS share hosted on a Solaris system, you must configure the Solaris system to allow the backup process to change file ownership permissions. To do this:

• In /etc/dfs/dfstab on the Solaris system, you must specify that the fully-qualified domain name of the Database Server or All-In-One Appliance can access the NFS file system as root. For example:

```
share -F nfs -o sec=sys,root=database.sciencelogic.local -d
"ScienceLogic Backup Share" /export/home/backup
```

• In /etc/defaults/nfs on the Solaris system, include the line NFSMAPID_DOMAIN=<domain of Database Server or All-In-One Appliance>. For example:

```
NFSMAPID DOMAIN=ScienceLogic.local
```

You can test this configuration by mounting the NFS file system from the console of your SL1 appliance, creating a new file on the file system using the "touch" command, and then executing the command "Is -la". If the Solaris system is configured correctly, the output of the Is command will indicate that the new file was created and is owned by the "root" user.

Performing Configuration and Full Backups on the DR Database Server

Users with large systems and very large backup files can use an alternative method to back up SL1: Performing backups from the disaster recovery Database Server. The benefit to this alternative method is that it reduces performance issues during the backup procedure.

It is important to note the differences between a disaster recovery backup and a configuration or full backup on the disaster recovery Database Server:

- A disaster recovery backup is a method for backing up the Disaster Recovery system.
- A configuration or full backup performed on the disaster recovery Database Server is an alternative method to **backing up SL1**.

Unlike the disaster recovery backup, which uses tar to make a compressed copy of the /data/db directory, performing a configuration backup from a disaster recovery Database Server uses the MySQL Dump tool and backs up the same data as described in the section on **Configuration Backups**.

Performing a full backup from a disaster recovery Database Server uses the MariaBackup tool and backs up the same data as described in the section on *Full Backups*.

During a configuration backup or full backup from a disaster recovery Database Server:

- The disaster recovery Database Server does not appear active to any other SL1 appliances.
- No applications or services can connect to the disaster recovery Database Server.

To perform a full backup on the disaster recovery Database Server:

- 1. Follow the instructions in the section on Creating a Credential.
- 2. Follow the instructions in the section on Configuring Backups.
- 3. Depending on the type of backup you are defining, select the **Configuration Backup on DR** or **Full Backup on DR** checkbox.
- 4. Complete the remaining fields on that page as needed, and then click [Save].
- 5. If necessary, follow the instructions in the section on Mounting Backup Files.
- 6. To restore the backup, follow the instructions in the section on **Restoring Backups**.

NOTE: After you define configuration or full backups on the Disaster Recovery Database Server, you should disable any other existing backups. However, you can continue to use standard DR Backup to back up your Disaster Recovery system.

Configuration Backup on a Disaster Recovery Database Server

To perform a configuration backup on the Disaster Recovery Database Server:

- 1. Go to the **Backup Management** page (System > Settings > Backup).
- 2. In the Configuration Backup pane, select the Configuration Backup on DR checkbox.
- 3. Complete the remaining fields on that page as needed, and then click [Save].
- 4. Follow the instructions in the section on Creating a Credential.
- 5. Following the instructions in the section on **Defining a Configuration Backup**.
- 6. To restore the backup, follow the steps in the section Restoring a Configuration Backup.

NOTE: If you enabled configuration backups on the Disaster Recovery Database Server, you should disable standard configuration backups.

Full Backup on a Disaster Recovery Database Server

To perform a full backup on the Disaster Recovery Database Server:

- 1. Go to the **Backup Management** page (System > Settings > Backup).
- 2. In the **Full Backup** pane, select the **Full Backup on DR** checkbox.
- 3. Complete the remaining fields on that page as needed, and then click [Save].
- 4. Follow the instructions in the section on Creating a Credential.
- 5. Following the instructions in the section on **Defining a Full Backup**.
- 6. To restore the backup, follow the steps in the section Restoring a Full Backup.

NOTE: If you enabled full backups on the Disaster Recovery Database Server, you should disable standard full backups.

Chapter

13

Viewing License Data

Overview

This chapter describes license data for SL1.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon
- To view a page containing all of the menu options, click the Advanced menu icon (...).


Viewing License Information

The License Information modal enables you to:

- View a list of all third-party licenses that are aligned with SL1
- Search for specific licenses
- View the full text of each license


To view license information:

1. Click the Toolbox button in the upper-right of the SL1 browser session and then select License Information.



The License Information modal appears. All of the licenses that are aligned with SL1 are listed.

2. On the **License Information** modal, you can do the following:



- To view any license in its entirety, click its right-arrow icon. When you do, the icon becomes a downarrow, and the full license information appears.
- To view all of the licenses in their entirety, click the **Expand All** link.
- To view only the condensed information for each license, click the **Collapse All** link.
- To search for a specific license, type part or all of its name in the search box in the upper-right of the page and then press the **Enter** key.

Chapter

14

Subscription Data

Overview

If you have a subscription license, you can use the **Subscription Usage** page (System > Monitor > System Usage > Subscription button) to:

- View current or historical subscription license usage graphs
- Download subscription license usage data for manual upload to the ScienceLogic billing server
- Upload a receipt from the ScienceLogic billing server

If your SL1 system is configured to communicate with the ScienceLogic billing server, usage data will be sent automatically from your SL1 system to the ScienceLogic billing server once a day. After the ScienceLogic billing server receives the usage data, SL1 will automatically mark the license usage file as delivered.

If your SL1 system is not configured to communicate with the ScienceLogic billing server or if the connection to the ScienceLogic billing server fails, you can manually upload usage data to the ScienceLogic billing server.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon (=).
- To view a page containing all of the menu options, click the Advanced menu icon (...).

This chapter covers the following topics:

Ensuring Accurate Data	358
Viewing Subscription Usage	358
Viewing Delivery Status	361
Manually Uploading License Usage to ScienceLogic	362
Data Retention Settings for Licensing	363

Ensuring Accurate Data


If the reports described in this chapter do not appear to be correct, validate your configuration by opening the **Subscription Usage** page (System > Monitor > System Usage > Subscription button):

- For secure/air-gapped systems, the latest "Summary Date" value will be within the last 48 hours
- For systems that connect to ScienceLogic, the latest "Summary Date" value will be within the last 48 hours, and the "Delivery Status" is "1".

Viewing Subscription Usage

IMPORTANT: ScienceLogic uses the data collected for each device to assign a license to the device, and you are billed based on the number of device licenses you consume. The rules that govern how licenses are assigned are based on your subscription with ScienceLogic. Certain types of devices do not count against your device license usage in SL1. For more information, see the Non-billable Devices section.


The **Subscription Usage** page (System > Monitor > System Usage > Subscription button) provides a visual overview of your device license usage, including historical and current information. The information available in each panel of the page is described in this section and is accessible from the drop down menu in the top right of the page.



Current License Usage Totals


The bar chart in the upper-left corner of the **Subscription Usage** page shows the current total consumption of device licenses by license type. Each bar represents a license type. You can hover over a bar to see the number of

licenses currently being consumed for that type. In the example below, we have four license types. We see that we are currently using 12 Ratio licenses.



Historical License Usage Totals

The line graph in the upper-right corner of the **Subscription Usage** page shows subscription license usage over time by license type. You can hover over a data point to see how many licenses of a given type were in use at that point in time.



A Date Range selector lets you narrow your view by using one of the following:


- All
- Current Quarter
- Last Quarter
- Current & Last Quarter
- Last Year

Whereas the "Current License Usages Totals" bar chart showed us that the most used license type currently is the Ratio license, the historical graph shows us that the Non-Billable license type is the most used over the given time range.

Current License Totals

The Current License usage table in the lower half of the **Subscription Usage** page lets you view information about your current subscription license usage in one of two ways:


Current License Usage by Device. Choose "Current License Usage" from the drop-down list. Provides a
list of all devices and the licenses they are using. You can search the table or filter on Device Name, Class,
Organization, Category, or License Type.




NOTE: You can click on a device to open the **Device Investigator** page for the device. For more information, see **Using the Device Investigator** in the online help.

TIP: If you are looking for a specific device license or licenses, click the gear icon (to the right of the **Search** field and select *Advanced*. For more information, see the "Performing an Advanced Search" topic in the **Introduction to SL1** manual.

• Current License Counts by Device Class. Choose "Current License Counts" from the drop-down list. Provides a list of all device classes that are associated with devices in the system, the device category, the total licenses currently consumed by devices of that device class, and a breakdown count for each license type for the device class. You can filter this table by device Class or Category.



 Current License Counts by Device Category. Choose "Current License Category" from the drop-down list. Provides the Total number of licensed categories, their Test status, and number of Tests by Category.



TIP: The "Current License Category" category information also auto-populates and can be displayed in the "Current License Totals" bar chart above.

Viewing Delivery Status

The **License Data Delivery Status** page displays the status of one or more daily license usage files. To view the **License Data Delivery Status** page:

- 1. Go to the **Subscription Usage** page (System > Monitor > System Usage > Subscription button).
- 2. Click the [License Data Delivery Status] button.
- 3. The **License Data Delivery Status** modal appears and displays a list of daily license usage files. For each daily license usage file, the **License Data Delivery Status** page displays the following:
 - Summary Date. Date associated with the daily license-usage file.
 - Delivery Status. Possible values are:
 - ° "O" (zero). File has not been uploaded to the ScienceLogic billing server.
 - "1" (one). File has been uploaded to the ScienceLogic billing server and may be deleted from the SL1 system by the automated maintenance process.

Viewing Delivery Status 361

Summary Size. Size of the daily license usage file.

Manually Uploading License Usage to ScienceLogic

If your SL1 system is configured to communicate with ScienceLogic, usage data will automatically be sent to the ScienceLogic billing server once a day. After the ScienceLogic billing server receives the usage data, SL1 will automatically mark the license usage file as delivered.

If your SL1 system is not configured to communicate with ScienceLogic or if the connection to the ScienceLogic billing server fails:

- You can use the License Data Delivery Status page to manually download the daily license-usage file.
- You can then log in to the ScienceLogic billing server and manually upload the daily license-usage file.
- You can then use the **License Data Delivery Status** page to upload the ScienceLogic "receipt" to your SL1 system, allowing SL1 to mark the license usage file as delivered.
- License usage files will not be deleted from your system until they are delivered.

Downloading the Daily License Usage File

If your SL1 system is not configured to communicate with ScienceLogic or if the connection to the ScienceLogic billing server fails, you can use the **License Data Delivery Status** page to manually download the daily license usage file. You can then log in to the ScienceLogic Licensing and Billing server and manually upload the daily license usage file.

To download the daily license-usage file using the License Data Delivery Status page:

- 1. Go to the **Subscription Usage** page (System > Monitor > System Usage > Subscription button).
- 2. Click [License Data Delivery Status].
- 3. Select one or more daily license usage files to download to your local computer, and then click the **[Download]** button.

NOTE: If the download size exceeds 50MB, the [**Download**] button is disabled.

4. The daily license usage file is saved to your local computer. The downloaded file is usually named "license_data.json.gz".

Manually Uploading the Daily License Usage File to ScienceLogic

After downloading the daily license usage file to your local computer, you can manually upload the file to the ScienceLogic billing server. To do this:

- 1. Log in to the ScienceLogic billing system.
- 2. Go to the **Subscription Data** page (Preferences > Account > Subscription Billing).
- 3. In the Subscription Data page, go to the Subscription Data Update pane. Use the [Browse] button to

find the daily license-usage file that you downloaded to your local computer.

4. Click the [Get Update] button to upload the daily license-usage file to the ScienceLogic server.



5. The ScienceLogic server will provide a "receipt" file for you to download. This file is usually called "status_updated.json.gz". You must upload this receipt to your SL1 system.

Uploading the ScienceLogic Receipt

After uploading the daily license usage file to the ScienceLogic Billing server, the ScienceLogic server will provide a "receipt" file for you to download. This file is usually called "status updated.json.gz".

You must upload this "receipt" file to your SL1 system to inform your SL1 system that the upload was successful and that the SL1 system may delete the daily license usage file.

To upload the "receipt" file:

- 1. Go to the **Subscription Usage** page (System > Monitor > System Usage > Subscription button).
- 2. Click [License Data Delivery Status].
- 3. In the Status Update File field, click [Choose File] and browse to locate the "receipt" file.
- 4. Click the [Upload] button to upload the "receipt" file to your SL1 system.

Data Retention Settings for Licensing

The **Data Retention Settings** page contains settings for subscribers.

To adjust these settings:


- 1. Go to the **Data Retention Settings** page (System > Settings > Data Retention).
- 2. The following sliders appear under the Subscription Data Retention heading:
 - Subscriber Device Configuration Data. For users with a subscriber license. Number of months to retain the files and database tables that contain configuration information for a device. Default value is two months.
 - Subscriber Device Usage Data. For users with a subscriber license. Number of months to retain information on total number of events and total number of tickets. Default value is two months.

- Subscriber System Configuration Data. For users with a subscriber license. Number of months to retain the files and database tables that contain configuration information for the SL1 system. Default value is three months.
- Subscriber System Usage Data. For users with a subscriber license. Number of months to retain information on total number of events and total number of tickets. Default value is three months.
- Subscriber Device Type Data. For users with a subscriber license. Number of months to retain the files and database tables that map each device to a device category, as per your subscriber license. Default value is three months.
- Subscriber Daily Delivery Data. For users with a subscriber license. Number of months to retain the "crunched" license usage data that is calculated each day using the Subscriber Device Configuration Data, Subscriber System Configuration Data, Subscriber System Usage Data, and Subscriber Device Type Data. SL1 will not prune data that has not yet been delivered to the ScienceLogic Licensing and Billing server. Default value is three months.

The **Data Retention Settings** page contains settings for feature data retention as well. This data is applicable to all systems.

To adjust these settings:

- 1. Go to the **Data Retention Settings** page (System > Settings > Data Retention).
- 2. The following sliders appear under the **Feature Data Retention** heading:
 - Feature Configuration Data. Feature data is information about how SL1 is being used, including configuration data and performance metrics. Number of months to retain raw feature configuration values. Default value is six months.
 - Feature Performance Data. Feature data is information about how SL1 is being used, including configuration data and performance metrics. Number of months to retain raw performance metric values. Default value is six months.
 - Feature Performance Data Aggregation Daily. For users with a subscriber license. Number of months to retain the files and database tables that contain aggregated daily-performance values. Default value is six months.
 - Feature Performance Data Aggregation Hourly. For users with a subscriber license. Number of months to retain the files and database tables that contain hourly-performance values. Default value is six months.



Chapter

15

CAC Authentication

Overview

This chapter describes how SL1 supports Common Access Card (CAC) authentication. The **Client Certificate** & **CAC Authentication** page (System > Settings > Authentication > Admin SSL Certificates, or System > Settings > Authentication > SSL Certificates in the classic SL1 user interface) allows you to define a check for SSL certificate that controls whether the login page is displayed to the end user.

This feature is primarily used to authenticate Common Access Card (CAC) users against a Department of Defense (DoD) issued server-side certificate; however, based on your business needs, this feature can also be used with your own client/server certificates.

NOTE: You can use CAC authentication to log in to either the current SL1 user interface ("AP2") or the classic SL1 user interface. Follow the steps described in this chapter to configure your CAC authentication, regardless of which user interface you use.

NOTE: Currently, SL1 does not support client-side certificate authentication for login to the console, either through SSH or through a keyboard connected to the appliance.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon (=).
- To view a page containing all of the menu options, click the Advanced menu icon (---).

This chapter covers the following topics:

sing CAC Authentication3	67
erequisites3	868

Importing SSL Certificates	369
Extracting the Common Name from a Certificate for Authentication	370
Defining the Client Certificate Chain	371
Verifying SSL Certificate File Import and Resolving Issues	373
Clearing the SL1 Cache and Restarting NGINX	374
Testing the Configuration	374
Troubleshooting CAC Authentication	375
Accessing the Appliance without CAC Authentication	377
Special Circumstance: Multiple Levels of Intermediate Certificates	377

Using CAC Authentication

SL1 supports CAC authentication. The Client Certificate & CAC Authentication page allows you to define a check for SSL certificate that controls whether the login page is displayed to the end user. This feature is primarily used to authenticate Common Access Card (CAC) users against a Department of Defense (DoD) issued server-side certificate; however, based on your business needs, this feature can also be used with your own client/server certificates.

The CAC is a United States DoD smartcard issued as standard identification for Active Duty Military personnel, reserve personnel, civilian employees, and eligible contractor personnel. A User Principal Name (UPN) is recommended, and in some instances required, when using CAC.

CAC provides applications with a more secure way to authenticate the identity of a user, application, or device. However, even if a user authenticates with a certificate, it does not mean that they user is authorized to access the requested data. For more information on authentication and authorization, see the DoD documentation on authentication and authorization for DoD web servers.

DoD has implemented an external interoperability strategy for secure information sharing with external partners. Some DoD industry partners have implemented corporate PKIs, and others have obtained certificates from approved commercial PKIs. Some DoD international allied and coalition partners also have established PKIs to issue certificates to their personnel. Systems and applications with user populations that hold approved external credentials should be configured to accept those credentials rather than requiring the users to obtain Common Access Cards (CACs) or External Certification Authority (ECA) certificates. For the complete list of DoD approved external PKIs and interoperability tools, see the DoD documentation on interoperarability.

DoD policy requires that external credentials have an assurance level of medium hardware or higher, so systems accepting external credentials must have an assurance level enforcement capability. Depending on technology, this can be accomplished through use of the Interoperability Root CAs (IRCAs) or implementation of a local certificate policy object identifier (OID) filtering solution such as the DoD PKE Trust Anchor Constraints Tools (TACT). For a complete list of approved partner OIDs, see the DoD documentation on the approved assurance levels from external partner PKIs.

Systems and applications typically have configuration properties that control security settings related to PKI functionality. Security settings should be configured to support all desired PKI functions and comply with DoD authentication policy.

SL1 allows you to configure appliances that provide the user interface (Administration Portal, All-In-One Appliance, or the Database Server) for use with DoD certificates or your own certificates.

The CAC is used as the user's authentication to SL1. If the Authentication Profile (System > Settings > Authentication > Profiles) contains both the "CAC/Client Cert" and "EM7 Login Page" credential sources and a CAC is not presented or is invalid, then the ScienceLogic login page is presented to the end user.

NOTE: You can use CAC authentication to log in to either the current SL1 user interface ("AP2") or the classic SL1 user interface. Follow the steps described in this chapter to configure your CAC authentication, regardless of which user interface you use.

NOTE: Currently, SL1 does not support client-side certificate authentication for login to the console, either through SSH or through a keyboard connected to the appliance.

Prerequisites

To use client certificate authentication with SL1, you must first meet the following requirements:

- 1. Organizations must be created and configured. For more information, see "Creating and Editing Organizations" in the **Organizations and Users** manual.
- 2. An LDAP or AD Credential must be configured with a Service Account that has the appropriate permissions to query AD, typically read access.
- 3. Create one or more User Policies if you will use SL1 authentication. You do not need to configure user policies if you are using Active Directory (AD) or LDAP. For more information, see "Creating a User Policy" in the **Organizations and Users** manual.
- 4. If you are using LDAP or Active Directory as your user store, you must configure this as your Authentication Resource before setting up your Authentication Profile. For more information, see <u>Authentication</u> <u>Resources</u>.
- 5. Configure an Authentication Profile for CAC authentication. When setting up your Authentication Profile for CAC, align the "CAC/Client Cert" credential with the profile as the first credential source. You can align the EM7 Login Page as a secondary credential source for administrator access, but this is not required. For more information, see Creating an Authentication Profile.
- 6. Configure an emergency account ("break glass" account) for the Database Server. Because CAC will work only with the Database Server's DNS name, an emergency account ensures that the em7admin account is used only as a last resort.
- 7. Go to the Authentication Profiles page (System > Settings > Authentication > Profiles). Select the wrench icon () for the default profile. In the Authentication Profile Editor page, in the Aligned Credential Sources field, delete any existing CAC/Client Cert credentials.
- 8. Your users must have either:
 - Valid CACs with valid client-side certificates already loaded onto the cards, or
 - Valid client-side certificates installed in their web browser.
- 9. If CACs are used, the browser through which the user logs on to the user interface must be able to read security certificates from the cards.
- 10. The Administration Portal, All-In-One Appliance, or the Database Server will request a certificate from the CAC or client web server only when the appliance uses HTTPS. In SL1 12.2.0 and above, the use of HTTPS is enforced by default. In SL1 versions prior to 12.2.0, you must go to the **Behavior Settings** page (System > Settings > Behavior), and select the **Force Secure HTTPS** setting checkbox.

368 Prerequisites

NOTE: In SL1 12.2.0 and above, the **Force Secure HTTPS** setting does not appear as an option on the **Behavior Settings** page.

11. On the **SSL Certificates** page (System > Settings > Authentication > Admin SSL Certificates, or System > Settings > Authentication > SSL Certificates in the classic SL1 user interface), you must install the certificate chain in PEM format on the Administration Portal, All-In-One Appliance, or the Database Server. A certificate chain usually includes a root CA certificate and an intermediate certificate. Your organization might require multiple intermediate certificates to provide access to all users. To learn more about importing a certificate, see the section *Importing an SSL Certificate*.

NOTE: If you want to extract part of the Common Name to customize the username that is displayed in SL1 after CAC authentication, you can edit the ScienceLogic configuration file to customize the displayed username. You do not need to do this if you are using the msUPN. For more information, see *Extracting the Common Name from a Certificate for Authentication*.

12. In the Client Certificate & CAC Authentication page (System > Settings > Authentication > CAC Client Cert Auth, or System > Settings > Authentication > CAC/ClientCert Auth in the classic SL1 user interface), you must configure the server-side certificate and test it against your client-side certificate. For more information, see Defining the Client Certificate Chain.

Importing SSL Certificates

Secure Sockets Layer, or SSL, is a protocol for securely transmitting data via the Internet. SSL uses a private key to encrypt data to be transferred over an Internet connection. In SL1, you can import server-side SSL certificate files, including DoD certificate files used in CAC authentication, to the Administration Portal, All-In-One Appliance, or the Database Server.

Note the following:

- You must have one root certificate and one certificate for each intermediate authority in the client certificate chain. If you have users with CACs issued by different intermediate authorities, you must import SSL certificates for all possible client authentication chains into SL1.
- All SSL certificates must be in PEM format.
- You can test your SSL certificate files by using the following command, where <certificate_file_name> is the full name of the certificate file:

```
openssl x509 -text -noout -in <certificate_file_name>
```

TIP: It is a best practice to check each certificate file before attempting to import the file. If you encounter an error, resolve that error before you continue.

To import an SSL certificate for CAC authentication:

- 1. Go to the **SSL Certificates** page (System > Settings > Authentication > Admin SSL Certificates, or System > Settings > Authentication > SSL Certificates in the classic SL1 user interface).
- 2. In the SSL Certificates page, click the [Actions] menu. Select *Import PEM Certificate File*. The Import Certificate File (PEM format) modal appears.
- 3. In the **Import Certificate File (PEM format)** modal, enter the following:
 - Description. Description of the certificate.
 - CA File. Browse for the server-side certificate file on your local computer.
- 4. Click the **[Save]** button to load the certificate to the Administration Portal, All-In-One Appliance, or the Database Server.
- 5. Repeat these steps for each certificate file you want to import. When finished, verify that all of your certificates appear in the listing shown on the SSL Certificates page (System > Settings > Authentication > Admin SSL Certificates, or System > Settings > Authentication > SSL Certificates in the classic SL1 user interface).

TIP: A best practice is to make note of the value in the Hash field shown for each certificate and verify that the hash values match the symlink files in the /var/lib/em7/certs directory on the appliance after completing the configuration of your client certificate chain. You will use these hash values in **Verifying SSL Certificate File Import and Resolving Issues**.

Extracting the Common Name from a Certificate for Authentication

By default, the certificate configuration file (em7_certificate.conf) is configured to display the full common name (CN) of the CAC user as the username in SL1 after authentication. If this meets your requirements, then you do not need to update the configuration file and can skip this section.

NOTE: If you are using the Microsoft User Principal Name (MS UPN) in your certificates, you do not need to make any edits in the configuration file.

However, if you require that SL1 use only a portion of the CN, then you can edit the certificate configuration file to parse out a username from the CN in the certificate.

For example, in some instances you might want to use an employee's ID number as the username. To do that, you must edit the Nginx configuration file.

To do so:

- 1. Log in to the console of the SL1 appliance as the root user.
- 2. Navigate to the directory /etc/nginx/conf.d/:

cd /etc/nginx/conf.d/

3. Open the file em7 certificate.conf with a text editor like vi:

```
vi em7_certificate.conf
```

4. Modify the file to extract the CN from the full Distinguished Name (DN) found in the certificate based on how you want to map the username to an LDAP system or how you want the usernames to look if you are using SL1 internal as the backend of your authentication configuration.

This is the default configuration of the file:

```
# Create the Username for EM7 to use from the Certificate
# Default: Pull the Common Name from the DN.
map $ssl_client_s_dn $ssl_client_username {
      ~/?CN=(?<CN>[^/,]+) $CN;
}
```

Modify the string to extract the name. The following is a regular expression that extracts the CN from the full DN) found in the certificate:

```
map ssl_client_s_dn ssl_client_username { ~/CN=[A-Z\.]+(?<num>[0-9]+) }num; }
```

5. Save and quit (:wq) the file.

Defining the Client Certificate Chain

After importing your SSL Certificates, you must consolidate the SSL PEM certificates into a combined file (emt_combined.crt). On the CAC/ClientCert Auth menu, select all of the desired SSL PEM certificates. After saving, SL1 will update the em7_combined.crt file with all of the selected SSL PEM certificates. SL1 will then use only the selected PEM certificates for validating and authenticating users.

You can also define some custom settings for client-side certificate authentication. You can define error messages that are displayed to the end user if authentication fails. Optionally, you can also define IP addresses in this modal for which the user interface will not perform certificate authentication, if you have not already created an Authentication Profile for this purpose. See Accessing the Appliance without CAC Authentication for more information.

When authentication is successful, the user interface displays the ScienceLogic Login page to the user.

To define the authentication settings:

- 1. Access the user interface with your CAC or a browser with your client-side certificate installed.
- Go to the Client Certificate & CAC Authentication page (System > Settings > Authentication > CAC Client Cert Auth, or System > Settings > Authentication > CAC/ClientCert Auth in the classic SL1 user interface).
- 3. Supply a value in each of the following fields:
 - Root CA Certificates. Select all root and intermediate certificates that make up the chain from a list
 of certificates installed on the SSL Certificates page (System > Settings > Authentication > Admin
 SSL Certificates, or System > Settings > Authentication > SSL Certificates in the classic SL1 user
 interface). Your client-side certificate will be authenticated against the selected server-side root and
 intermediate certificates.
 - Auth Failure Message. Enter text for the error message that appears to users if authentication fails.

CAUTION: You cannot save your authentication settings until you enter text in the "Auth Failure Message" field.

• Ignore Networks. In this field, you can enter a list of networks and hosts from which certificate authentication is not required. During each login, the platform will compare the client's IP address to the list entered in this field. If the client's IP address is included in this field, SL1 will not require certificate authentication from that client.

NOTE: If you are using Authentication Profiles to configure access from specific resources from which certificate authentication is not required, you do not need to use the *Ignore Networks* field. For more information, see Accessing the Appliance without CAC Authentication.

- In the *Ignore Networks* field, you can enter one or more IP addresses, each separated by a new-line character (press the [**<Enter>**] key).
- In the list of IPs to ignore, you can enter only the first octet, only the first and second octet, only the first, second, and third octet, or all four octets. SL1 will interpret the entry as if the rightmost octet is followed by * (asterisk).

For example:

- 192.168.10.142 will allow a single host to log in to the user interface without certificate authentication
- 192 behaves the same as entering 192*. This will allow all hosts included in 192.0.0.1 through 192.254.254.254 to log in to the user interface without certificate authentication
- 192.168.10.24 behaves the same as entering 192.168.10.24*. This will allow all hosts 192.168.10.24, 192.168.10.240, 192.168.10.241, 192.168.10.242, 192.168.10.243, 192.168.10.244, 192.168.10.245, 192.168.10.246, 192.168.10.247, 192.168.10.248, and 192.168.10.249

4. Click the [Save] button to save your settings. The user interface displays the message:

Settings Saved Successfully. Configuration must be tested in order to take effect.

CAUTION: Do not click the Test link at this time.

Verifying SSL Certificate File Import and Resolving Issues

After you have imported your SSL certificates and configured your client certificate chain, it is important to verify the your certificate files were imported correctly and are valid in SL1.

To verify that your SSL certificate files were imported correctly:

- 1. Either go to the console of the SL1 appliance where you imported the SSL certificates, or use SSH to log in.
- 2. Navigate to the /var/lib/em7/certs directory. At the shell prompt, enter:

```
ls -1
```

3. Review the list of hash symlink files in the directory and compare them to the list of certificates on the SSL Certificates page. Ensure that the hash values shown in SL1 match the hash symlink files. Note that the hash symlink in the /var/lib/em7/certs directory (in blue text) for a certificate file is appended with ".0", as shown in the image below.

```
rwxrwxrwx.
             s-em7-http s-em7-core
                                          Jun 25 03:41 4f5db21f.0 ->
                                       21 Jun 25 03:41 60085f15.0 -> DoD
rwxrwxrwx.
                                       21 Jun 25 03:41 9cf5f371.0 -> DoD
rwxrwxrwx.
                                                                                        .pem
             s-em7-http s-em7-core
                                              25 03:41 d7fc5635.0 -> DoD
             s-em7-http s-em7-core
                                              25 03:35
             s-em7-http s-em7-core
                                                                          pem
             s-em7-http s-em7-core
                                     1753 Jun
                                          Jun
             s-em7-http
                                     1753 Jun
             s-em7-http
                        s-em7-core
             s-em7-http
                        s-em7-core
             s-em7-http s-em7-core
                                          Jun 25
                                                 03:41 ec465775.0 ->
                                          Jun 25
             s-em7-core s-em7-core
                                     1489 Jun
                                                 00:35 em7 default.crt
             s-em7-core s-em7-core
                                                 00:35 em7_import_dodeca2.cac
                                                 00:35 em7
                                                            import_dodeca.cac
                                                 00:35 em7_import_rel3_dodroot_1024.cac
                                          Jun
                   -core s-em7-core
                                          Jun
                                                            import rel3 dodroot
                                                       f9b9dee864d0b27dda9dde4bbdfb9cf7.sync
                                          Jun
```

All of the following must be true. If any of these are not true, then the certificate file was not imported and saved correctly in SL1:

- One hash symlink file should exist in the directory for each of the imported certificate files.
- The file size of the "em7_combined.crt" file is equal to the combined file sizes of all of the certificate (.pem) files. (The file "em7_combined.crt" is not equal to the "em7_default.crt" file.)
- When you view the contents of the "em7_combined.crt" file using cat or similar command, the file is
 the concatenation of all of the certificate (.pem) files. NGINX references the "em7_combined.crt" file
 as the file containing the client certificate chain.
- 4. If any of the conditions listed above are not true, then the certificate file was not imported and saved correctly in SL1. To resolve the problem:
 - a. Log in to the SL1 appliance user interface.
 - b. Go to the **Client Certificate & CAC Authentication** page (System > Settings > Authentication > CAC Client Cert Auth, or System > Settings > Authentication > CAC/ClientCert Auth in the classic SL1 user interface).
 - c. Edit the Auth Failure Message field. Make a change to the section.
 - d. Click [Save].
 - e. Repeat steps 1-3 to verify your certificate files.

Clearing the SL1 Cache and Restarting NGINX

Before you proceed to testing the configuration, you must clear the SL1 cache, restart nginx, and close any browsers you have open. This will ensure the best outcome when testing.

- 1. Log in to the user interface on the SL1 appliance.
- 2. Click on the [Toolbox] button () and choose Misc > Clear SL1 System Cache.
- 3. Log out of the SL1 appliance.
- 4. Either go to the console of the SL1 appliance where you imported the SSL certificates, or use SSH to log in to the appliance.
- 5. Run the following command to restart nginx:

```
sudo systemctl restart nginx
```

6. Close any open browsers that have been used to access the appliance.

Testing the Configuration

After you define the certificate authentication settings, you must test your client-side certificate against the server-side certificate you selected in the **Root CA Certificates** field. Testing your configuration is required to prevent an incorrect configuration from preventing administrator access to the user interface. If the test is successful, the certificate authentication settings will be applied. If the test is unsuccessful, the certificate authentication settings will not be applied.

To test certificate authentication settings:

- With your CAC inserted in the reader, access the user interface of your SL1 appliance using the IP address
 or domain name defined in the AP Hostname Pattern field of the CAC Authentication Profile (System
 > Settings > Authentication > Profiles). Log in with an administrator account.
- Go to the Client Certificate & CAC Authentication page (System > Settings > Authentication > CAC Client Cert Auth, or System > Settings > Authentication > CAC/ClientCert Auth in the classic SL1 user interface).
- 3. After defining the certificate, you will see the following message at the top of the pane:

Configuration must be tested in order to take effect: TEST.

- 4. Click the **TEST** link. SL1 will attempt to authenticate your client-side certificate against the selected server-side certificate.
- 5. If the test authentication is successful, SL1 will display the following message at the top of the pane and end users with the appropriate client certificate or CAC can now access the user interface using client certificate authentication:

Configuration verified and enabled.

- 6. A new field, Client Cert / CAC Auth, appears with a default value of Allowed. Do not edit this field.
- 7. Set the Certificate User Field to "Common Name" (default) or "MS UPN".

NOTE: If you are using LDAP or Active Directory (AD) for user authentication, set this field to "MS UPN".

- 8. Select the [Save] button to save the setting in the Client Cert / CAC Auth field.
- 9. If the test authentication is unsuccessful, the user interface will display the following message at the top of the pane. The settings will not be applied, and client certificate authentication will not be used until the problem is corrected:

ERROR: configuration was not successfully tested with CAC or Client Certificate.

NOTE: If you experience the error above, double-check the following: verify there are not any simple mistakes by reviewing any information you manually entered; check to see if there is a mismatch between the certificate chain installed in nginx versus what the browser uses; make sure the cert file names do not contain spaces or blanks in the file name.

Troubleshooting CAC Authentication

There are a few common issues you might experience while testing CAC authentication. If your test is unsuccessful, review the following troubleshooting steps.

Failed to Identify Personal Identity Verification (PIV) Card

If you receive the "Failed to identify PIV card" message, verify the following:

- All root and intermediate certificates have been uploaded in a PEM format.
- All root and intermediate certificates have not expired and are configured properly.
- The client certificate has not expired.
- Customer username information is in the Microsoft User Principal Name (MS UPN and not the Common Name (CN).

Failed CAC Authentication After Disaster Recovery (DR) Failover

If your CAC authentication testing fails after DR failover, verify the following:

- The DR node domain has been added to the Auth Profile for pattern matching.
- The DR has all of the required certificates. (You might be required to manually upload and save the certificates again.)

NOTE: For more information, see Disaster Recovery with Two Appliances.

Failed CAC Authentication After Setting Up High Availability (HA)

Assuming you have deployed an SL1 distributed system with one Database Server and two or more Administration Portals and your CAC authentication testing fails after setting up HA, you must ensure the following:

The first Administration Portal where you configured CAC is working and you authenticated with CAC
before verifying that the second or third Administration Portal actually works. You should not have the
CAC/Client Cert in the aligned credential source on the default profile but in a new profile created for CAC
only.

NOTE: ScienceLogic suggests having at least two profiles (a default profile and a CAC profile). You should enter an AP Hostname Pattern on the CAC profile but keep the AP Hostname Pattern blank on the default profile.

- Upon successful CAC login on the first Administration Portal, you will notice that any login attempts to the second or third Administration Portal will fail. For this, you need to first verify that the content of the /var/lib/em7/certs contains the PEM files that are identical to the first Administration Portal. You must also ensure that the hash files representing your PEM files are identical to the first Administration Portal and that the combined file is identical to the first Administration Portal.
- Once verified, restart nginx on the second and third Administration Portals and ensure that nginx is running correctly.

• Verify that you can log in with CAC from the second or third Administration Portals as you have done with the first Administration Portal.

NOTE: For more information, see High Availability with Two Appliances

Accessing the Appliance without CAC Authentication

In certain circumstances, you might need to access your SL1 Appliance without using CAC authentication. For example, the following are some reasons you might want to use another authentication type:

- For use during initial setup
- For appliance access when a certificate has expired
- For maintenance or administrator accounts
- For certain internal networks that will not require certificate authentication

You can configure the appliance to accept a login in these cases in two ways:

- By configuring an Authentication Profile to use an alternative authentication resource (for example, EM7 Internal) for certain networks or hosts. For more information, see the chapter on "Authentication Profiles" in the **System Administration** manual.
- By using the Ignore Networks field on the Client Certificate & CAC Authentication page (System > Settings > Authentication > CAC Client Cert Auth, or System > Settings > Authentication > CAC/ClientCert Auth in the classic SL1 user interface). For more information, see Defining the Client Certificate Chain.

Special Circumstance: Multiple Levels of Intermediate Certificates

By default, SL1 is configured to handle the typical certificate hierarchy, which comprises three levels: root, intermediate, and client certificates. This represents a depth of 2 from the root to the client certificate. If your organization will use CAC authentication in which you have multiple levels of intermediate certificates in the hierarchy, you will need to change this setting (ssl verify depth) as described in the procedure below.

To update the value of ssl verify depth:

- 1. Log in to the console of the ScienceLogic appliance as the root user.
- 2. Navigate to the directory /etc/ngnix/conf.d/:

cd /etc/ngnix/conf.d/

3. Open the file em7ngx web ui.conf with a text editor like vi:

vi em7ngx web ui.conf

4. Edit the ssl_verify_depth value to be the depth from client certificate to the root certificate (for example, 3):

5. Save and quit (:wq) the file.

Chapter

16

Authentication Profiles and Resources

Overview

This chapter describes the following topics:

- Authentication Profiles. Policies that align user accounts with one or more types of authentication.
- Authentication Resources. Configuration policies that describe how SL1 should communicate with a user store.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon
- To view a page containing all of the menu options, click the Advanced menu icon (...).

This chapter covers the following topics:

Authentication Profiles	380
Authentication Resources	385

Authentication Profiles

Authentication profiles are policies that align user accounts with one or more types of authentication:

- Alignment by pattern matching. SL1 examines the URL or IP address that a user enters in a browser to connect to an Administration Portal, Database Server, or All-In-One Appliance. If the URL or IP address matches the criteria specified in an authentication profile, SL1 will automatically use the matching profile to perform user authentication.
- Credential Source. Specifies from where SL1 should extract the username and password or certificate to be
 authenticated. These credentials are passed to SL1 through HTTP. SL1 then passes the credentials to each
 authentication resource specified in the authentication profile (for example, CAC/
 Client Cert). The authentication resources communicate with user stores that can authenticate the
 credentials entered by a user.
- Authentication Resource. Specifies the connector to use to communicate with the user store, the credential to use to connect to the user store (if applicable), such as your Active Directory server, and the URLs to examine during authentication. Authentication Resource also maps attributes from the user's account in the user store to fields in the ScienceLogic user account. For details on creating an authentication resource, see the section on Authentication Resources.

NOTE: If you will be using Single Sign-On (SSO) as your method of authentication, your SSO resource must be placed in its own Authentication Profile, since it will take priority over any other authentication method defined. If you have multiple SSO resources, each *must* be in its own profile.

Viewing the List of Authentication Profiles

To view a list of all authentication profiles in SL1:

- 1. Go to the **Authentication Profiles** page (System > Settings > Authentication > Profiles).
- 2. The following information is displayed about each authentication profile:
- Profile Name. Name of the authentication profile.
- ID. Unique numeric ID, automatically assigned by SL1 to each authentication profile.
- Hostname Pattern. This field is used to match the URL or IP address that a user enters in a browser to
 connect to an Administration Portal, Database Server, or All-In-One Appliance. If the URL or IP address
 matches the value in this field, SL1 applies the authentication profile to the user for the current session.
- **Priority Order**. If your SL1 System includes multiple authentication profiles, SL1 evaluates the authentication profiles in priority order, ascending. This column displays the priority order value for the authentication profiles, where 0 (zero) is the highest priority.
- Edited By. The user who created or last edited the authentication profile.
- Last Edited. Date and time the authentication profile was created or last edited.

TIP: To sort the list of authentication profiles, click on a column heading. The list will be sorted by the column value, in ascending order. To sort by descending order, click the column heading again. The *Last Edited* column sorts by descending order on the first click; to sort by ascending order, click the column heading again.

Filtering the List of Authentication Profiles

You can filter the list of authentication profiles on the **Authentication Profiles** page by one or more of the following parameters: **Profile Name**, **ID**, **Hostname Pattern**, **Priority Order**, **Edited By**, and **Last Edited**. The list of authentication profiles is dynamically updated as you select each filter.

For each filter, except **Last Edited**, you must enter text to match against. SL1 will search for authentication profiles that match the text, including partial matches, and will filter while you type. Text matches are not case-sensitive. You can use the following special characters in each filter except **Last Edited**:

- , (comma). Specifies an "or" operation. For example:
 - "dell, micro" would match all values that contain the string "dell" OR the string "micro".
- & (ampersand). Specifies an "and" operation. For example:
 - "dell & micro" would match all values that contain the string "dell" AND the string "micro".
- ! (exclamation mark). Specifies a "not" operation. For example:
 - "!dell" would match all values that do not contain the string "dell".
- ^ (caret mark). Specifies "starts with". For example:
 - "^ micro" would match all strings that start with "micro", like "microsoft".
 - "^" will include all rows that have a value in the column.
 - "! ^ " will include all rows that have no value in the column.
- \$ (dollar sign). Specifies "ends with". For example:
 - "\$ware" would match all strings that end with "ware", like "VMware".
 - "\$" will include all rows that have a value in the column.
 - "!\$" will include all rows that have no value in the column.

By default, the cursor is placed in the first Filter-While-You-Type field. You can use the <Tab> key or your mouse to move your cursor through the fields.

Only authentication profiles that meet all the following filter criteria will be displayed in the **Authentication Profiles** page:

- **Profile Name**. Name of the authentication profile. You can enter text to match, including special characters, and the **Authentication Profiles** page will display only authentication profiles that have a matching name.
- *ID*. Unique numeric ID, automatically assigned by SL1 to each authentication profile. You can enter text to match, including special characters, and the **Authentication Profiles** page will display only authentication profiles that have a matching ID.
- Hostname Pattern. This field is used to match the URL or IP address that a user enters in a browser to connect to an Administration Portal, Database Server, or All-In-One Appliance. If the URL or IP address matches the value in this field, SL1 applies the authentication profile to the user for the current session. You can enter text to match, including special characters, and the Authentication Profiles page will display only authentication profiles that have a matching hostname pattern.
- **Priority Order**. You can enter text to match, including special characters, and the **Authentication Profiles** page will display only authentication profiles that have a matching priority number.
- *Edited By*. The user who created or last edited the authentication profile. You can enter text to match, including special characters, and the **Authentication Profiles** page will display only authentication profiles that have been created or edited by a matching username.
- Last Edited. Date and time the authentication profiles was created or last edited. You can select from a list of time periods. The Authentication Profiles page will display only authentication profiles that have been created or edited within that time period.

The "default" Authentication Profile

SL1 includes a default authentication profile, for which the following rules apply:

- You cannot delete the default profile.
- If an **AP Hostname Pattern** fails to match all the other authentication profiles, SL1 applies the *default* authentication profile.
- For users running version 7.7 or earlier of SL1 who apply one or more patches to upgrade to version 7.8, the **default** profile allows ScienceLogic authentication to perform as it did prior to version 7.8.
 - ° On patched systems, the default profile is included in the patch.
 - On patched systems, the default profile is pre-configured to allow ScienceLogic administrators to log in via the ScienceLogic login page and the authentication resource EM7 Internal.
 - On patched systems, the default profile is pre-configured to allow credentials via CAC/Client Certificate, HTTP Auth, or the EM7 Login Page.
 - ° On patched systems, the default profile is pre-configured to use all legacy authentication resources: SSO (legacy), LDAP/AD (legacy), and EM7 Internal.

NOTE: Administrators can edit the default profile and use the new, non-legacy authentication resources but are not required to do so.

- For users who installed version 7.8 or later of SL1 using an ISO, initially the default profile is pre-configured
 to allow ScienceLogic administrators to log in via CAC/Client Certificate, HTTP Auth, or the EM7 Login Page
 and the authentication resource EM7 Internal. This allows administrators to log in and perform initial
 configuration on the SL1 system.
 - ° On ISO systems, the default profile is included in the patch.
 - On ISO systems, the default profile is pre-configured to allow credentials via CAC/Client Certificate, HTTP Auth, or the EM7 Login Page.
 - ° On ISO systems, the default profile is pre-configured to use only the authentication resource EM7 Internal.

NOTE: After initial configuration, administrators can edit the **default** profile as best fits their organization.

Creating an Authentication Profile

To create a new authentication profile:

- 1. Go to the **Authentication Profiles** page (System > Settings > Authentication > Profiles).
- 2. Click the [Create] button. The Authentication Profile Editor modal appears.
- 3. Enter values in the following fields:
 - Name. Name of the authentication profile.
 - **Priority Order**. If your SL1 System includes multiple authentication profiles, SL1 evaluates the authentication profiles in ascending priority order. SL1 will apply the authentication profile that matches the hostname or IP in the current URL AND has the lowest value in the **Priority Order** field.
 - Pattern Type. Specifies how SL1 will evaluate the value in the AP Hostname Pattern field. Choices are:
 - ^o Wildcard. SL1 will perform a text match, with wildcard characters (asterisks).
 - Regex. SL1 will use regular expressions to compare the AP Hostname Pattern to the current session information.
 - AP Hostname Pattern. This field is used to match the URL or IP address that a user enters in a browser to connect to an Administration Portal, Database Server, or All-In-One Appliance. If the URL or IP address matches the value in this field, SL1 applies the authentication profile to the user for the current session.
 - ° For example, if you specify "*" (asterisk), any IP address or URL will match. SL1 will then apply this authentication profile to every session on an Administration Portal, Database Server, or All-In-One Appliance.

- If you enter "192.168.38.235", SL1 will apply the authentication profile to each session on an Administration Portal, Database Server, or All-In-One Appliance where the user enters "192.168.38.235" into the browser.
- ^o If you enter "*.sciencelogic.local", SL1 will apply the authentication profile to each session on an Administration Portal, Database Server, or All-In-One Appliance where the user enters a URL ending with ".sciencelogic.local" into the browser.

NOTE: Do not include underscores (_) in the **AP Hostname Pattern** field. URLs with underscores are not considered valid in SL1 authentication profiles.

Available Credential Sources. This field tells SL1 how to retrieve the user's credentials from the
HTTP request to SL1. To align a credential source with the authentication profile, highlight the
credential source and click the right-arrow button. You can select zero, one, or multiple credential
sources for the authentication profile. Initially, this pane displays a list of all the credential sources:

NOTE: If you will be using CAC authentication, align the CAC/Client Cert credential source. If this is your primary method of logging in to SL1, align CAC/Client Cert as the number one credential source. ScienceLogic recommends having EM7 Login Page aligned, as well, for administrator or maintenance access.

- ° CAC/Client Cert. SL1 will retrieve a certificate from the HTTP request.
- EM7 Login Page. SL1 will retrieve a user name and password from the ScienceLogic login page fields.
- ^o HTTP Auth. SL1 will retrieve a user name and password from the HTTP request.

NOTE: If you are using Single Sign-On (SSO) authentication, the **Available Credential Sources** field is ignored. You do not have to align a credential source because credentials are submitted directly to an Identity Provider (IdP) instead of SL1.

- Aligned Credentials Sources. This field displays the list of credential sources that have been aligned
 with the authentication profile. The authentication profile will examine each credential source in the
 order in which it appears in this list. When the authentication profile find the user's credential, the
 authentication profile stops examining any remaining credential sources in the list.
- Available Authentication Resources. This field tells SL1 which authentication resources to use to
 authenticate the retrieved credentials. To align an authentication resource with the authentication
 profile, highlight the authentication resource and click the right-arrow button. You must select at least
 one authentication resource (but can select more than one). For details on creating an authentication
 resource, see the section on Authentication Resources.
- Aligned Authentication Resources. This field displays the list of authentication resources that have been aligned with the authentication profile. The authentication profile will examine each

authentication resource in the order in which it appears in this list. When an authentication resource successfully authenticates the user, the authentication profile stops executing any remaining authentication resources in the list.

4. Click the [Save] button to save your changes to the new authentication profile.

Editing an Authentication Profile

The Authentication Profiles page allows you to edit an existing authentication profile. To do so:

- 1. Go to the **Authentication Profiles** page (System > Settings > Authentication > Profiles).
- 2. Find the authentication profile that you want to edit. Click its wrench icon (🎤).
- The Authentication Profile Editor modal page appears. In this page, you can edit the value of one or more fields.
- 4. Click the [Save] button to save your changes to the authentication profile.

Deleting One or More Authentication Profiles

The Authentication Profiles page allows you to delete one or more authentication profiles from SL1. To do so:

- 1. Go to the **Authentication Profiles** page (System > Settings > Authentication > Profiles).
- 2. Select the checkbox of each authentication profile that you want to delete.
- 3. Click the **Select Actions** menu (in the lower right), select *DELETE Authentication Profile*, and then click the **[Go]** button. The selected authentication profiles will be deleted.

NOTE: You cannot delete the *default* authentication profile.

Authentication Resources

An authentication resource is a configuration policy that describes how SL1 should communicate with a user store. An authentication resource specifies the connector to use to communicate with the user store, the credential to use to connect to the user store (if applicable), and the URLs to examine during authentication. An authentication resource also maps attributes from the user's account in the user store to fields in the ScienceLogic user account.

Viewing the List of Authentication Resources

The Authentication Resource Manager page displays a list of all authentication resources in the SL1 System.

To view the list of authentication resources:

- 1. Go to the **Authentication Resource Manager** page (System > Settings > Authentication > Resources).
- 2. The following information is displayed about each authentication resource:

- TIP: To sort the list of authentication resources, click on a column heading. The list will be sorted by the column value, in ascending order. To sort by descending order, click the column heading again. The Last Edited column sorts by descending order on the first click; to sort by ascending order, click the column heading again
 - Resource Name. Name of the authentication resource.
 - ID. Unique numeric ID, automatically assigned by SL1 to each authentication resource.
 - Type. Specifies the user store that is associated with the resource. Possible types are:
 - ° EM7 Internal. The authentication resource communicates and passes information to and from the ScienceLogic Database.
 - LDAP/AD. The authentication resource communicates and passes information to and from an LDAP server or Active Directory server.
 - ° SSO. The authentication resource communicates and passes information to and from a SAML Identity Provider (IdP) or Service Provider (SP).
 - **Connector**. The software that allows communication between the authentication resource and the user store. Possible connectors are:
 - ° EM7 Internal. Software that communicates with the ScienceLogic Database.
 - LDAP/AD. Software that communicates with an LDAP server or Active Directory server.
 - * LDAP/AD Legacy. Software that communicates with an LDAP server or Active Directory server for ScienceLogic servers that were configured prior to version 7.8 of SL1. SL1 Systems that were upgraded to version 7.8 using patches can continue to use the same authentication methods without making changes to user accounts or the LDAP server or Active Directory server.
 - OneLogin. Software that communicates with a SAML Identity Provider (IdP).
 - SimpleSAML Legacy. Software that communicates with a SAML Identity Provider (IdP) and Service Provider (SP) for ScienceLogic servers that were configured prior to version 7.8 of SL1. SL1 Systems that were upgraded to version 7.8 using patches can continue to use the same authentication methods without making changes to user accounts, the SAML configuration, or the SSO provider.
 - Edited By. The user who created or last edited the authentication resource.
 - Last Edited. Date the time the authentication resource was created or last edited.

Filtering the List of Authentication Resources

You can filter the list of authentication resources on the **Authentication Resource Manager** page by one or more of the following parameters: **Resource Name**, **ID**, **Type**, **Connector**, **Edited By**, and **Last Edited**. The list of authentication resources is dynamically updated as you select each filter. For each filter except **Last Edited**, you must enter text to match against. SL1 will search for authentication resources that match the text, including partial matches. Text matches are not case-sensitive. You can use the following special characters in each filter except **Last Edited**:

- , (comma). Specifies an "or" operation. For example:
 - "dell, micro" would match all values that contain the string "dell" OR the string "micro".
- & (ampersand). Specifies an "and" operation. For example:
 - "dell & micro" would match all values that contain the string "dell" AND the string "micro".
- ! (exclamation mark). Specifies a "not" operation. For example:
 - "!dell" would match all values that do not contain the string "dell".
- ^ (caret mark). Specifies "starts with". For example:
 - "^ micro" would match all strings that start with "micro", like "microsoft".
 - "^" will include all rows that have a value in the column.
 - "! ^ " will include all rows that have no value in the column.
- \$ (dollar sign). Specifies "ends with". For example:
 - "\$ware" would match all strings that end with "ware", like "VMware".
 - "\$" will include all rows that have a value in the column.
 - "!\$" will include all rows that have no value in the column.

By default, the cursor is placed in the first Filter-While-You-Type field. You can use the **<Tab>** key or your mouse to move your cursor through the fields.

Only authentication resources that meet all the following filter criteria will be displayed in the **Authentication Resource Manager** page:

- **Resource Name**. Name of the authentication resource. You can enter text to match, including special characters, and the **Authentication Resource Manager** page will display only authentication resources that have a matching name.
- *ID*. Unique numeric ID, automatically assigned by SL1 to each authentication resource. You can enter text to match, including special characters, and the **Authentication Resource Manager** page will display only authentication resources that have a matching ID.
- Type. Specifies the user store that is associated with the resource. You can enter text to match, including special characters, and the Authentication Resource Manager page will display only authentication resources that have a matching type.
- **Connector**. The specific software that allows communication between the authentication resource and the user store. You can enter text to match, including special characters, and the **Authentication Resource**Manager page will display only authentication resources that have a matching connector.
- Last Edited. Date and time the authentication resources was created or last edited. You can select from a list of time periods. The Authentication Resource Manager page will display only authentication resources that have been created or edited within that time period.

• *Edited By*. ScienceLogic user who created or last edited the authentication resource. You can enter text to match, including special characters, and the **Authentication Resource Manager** page will display only authentication resources that have been created or edited by a matching username.

The "EM7 Internal" Resource

The EM7 Internal resource allows you to access the user store in the ScienceLogic database.

- By default, each SL1 System, whether upgraded to version 7.8 or built from a 7.8 ISO, includes the EM7 Internal authentication resource.
- You cannot create an EM7 Internal authentication resource.
- You cannot edit or delete the EM7 Internal authentication resource included with your SL1 System.
- Each SL1 System can include only one the EM7 Internal authentication resource.

Creating an LDAP/AD Authentication Resource

The LDAP/AD Auth Resource Editor page allows you to define an authentication resource for use with an LDAP/AD user store. An LDAP/AD authentication resource specifies the connector (communication software) to use to communicate with the LDAP/AD user store and the credential to use to connect to the user store. An LDAP/AD authentication resource can also map attributes from the user's LDAP/AD account to fields in the ScienceLogic user account.

ScienceLogic administrators can use LDAP or Active Directory to authenticate ScienceLogic users. There are two ways to use LDAP or Active Directory authentication with SL1:

- You can configure SL1 to automatically create user accounts for existing LDAP or Active Directory users and then always use LDAP or Active Directory to authenticate those users when they log in to SL1.
- You can use LDAP or Active Directory to authenticate one or more ScienceLogic users when they log in to SL1.

To create an LDAP/AD authentication resource:

- 1. Go to the **Authentication Resource Manager** page (System > Settings > Authentication > Resources).
- 2. Click the [Actions] menu and then select Create LDAP/AD Resource. The LDAP/AD Auth Resource Editor modal page appears.
- 3. Enter values in the following fields:

Basic Settings

- Name. Name of the LDAP/AD authentication resource.
- User Display Name. Select what name to display from the following options:
 - disable. Uses the current default behavior, which displays the user's username in the SL1 user interface and logs.
 - ° email address. Displays the user's email address in the SL1 user interface and logs.
 - ° user principal name. Displays the value from the UPN field on this page in the SL1 user interface and logs.

- **UPN**. "User principal name." If you select *user principal name* in the **User Display Name** field, then the value from this field displays in the SL1 user interface and audit logs. This field is blank by default for all existing (pre-11.2.1) authentication resources, but can be manually updated. For new authentication resources, enter one of the following:
 - email address. Displays the user's email address in the SL1 user interface and audit logs.
 - ° user principal name. Displays the value from the UPN field on this page in the SL1 user interface and audit logs.
- Read Credential. Credential that allows SL1 to read data from an LDAP or Active Directory server. Select from a list of all LDAP and Active Directory credentials to which you have access. If this field has been set to a credential to which you do not have access, this field will display the value Restricted Credential. If you set this field to a different credential, the entry for Restricted Credential will be removed from the field; you will not be able to re-align the field with the Restricted Credential.
- Write Credential. Credential that allows SL1 to write data to an LDAP or Active Directory server. Select from a list of all LDAP and Active Directory credentials to which you have access. If this field has been set to a credential to which you do not have access, this field will display the value Restricted Credential. If you set this field to a different credential, the entry for Restricted Credential will be removed from the field; you will not be able to re-align the field with the Restricted Credential.

NOTE: Your organization membership(s) might affect the list of credentials you can see in the **Read**Credential field and the Write Credential field. For details, see the **Discovery & Credentials**manual.

- **User Name Suffix**. Optional field. Because SL1 can authenticate against multiple LDAP or Active Directory servers, there is a risk of collision among user names. In this field, you can enter a string to append to the user name to minimize the risk of collision. For example:
 - Suppose we entered @ad.local in this field.
 - ^o Suppose the next LDAP/AD user logs in to SL1 with the user name **bishopbrennan**.
 - SL1 will log that user in as bishopbrennan@ad.local.

NOTE: A best practice to avoid collisions is to use email addresses as user names.

• **Search Filter**. Specifies where to find the user's account information in LDAP or Active Directory. You must tell SL1 where to find the LDAP or AD attribute that maps to the user's account name in SL1.

For example, an LDAP user might use his/her uid value to log in to SL1. In the ScienceLogic account, that uid value will then become the user's **Account Login Name**.

You can use the following variables in the search filter:

° [%u]. ScienceLogic login name.

- ° %e. Email address.
- ° An example search filter for LDAP might be:

```
(&(objectClass=person)(uid=%u))
```

This says to search in the object class called "person" for the uid that matches the ScienceLogic login name (entered when the user logs in to SL1 and then stored in the variable %u).

° An example search filter for Active Directory might be:

```
(sAMAccountName=%u)
```

This says to search for the samaccountname attribute that matches the ScienceLogic login name (entered when the user logs in to SL1 and then stored in the variable %u).

- ^o For more information on the syntax of LDAP and AD search filters, see <u>RFC 4515</u>.
- Sync directory values to EM7 on login. If an LDAP or AD administrator makes changes to an LDAP or AD account, SL1 will automatically retrieve those updates and apply them to the user's account in SL1 (in the Account Properties page) the next time the user logs in to SL1. (For more information about user account properties, see the Organizations & Users manual.)
- Sync EM7 values to directory on save. If a ScienceLogic administrator made changes to the ScienceLogic account, SL1 will automatically write those changes to the user's account in LDAP or Active Directory.

NOTE: The Sync EM7 values to directory on save option requires a write credential.

Attribute Mapping

If you have configured SL1 to automatically create ScienceLogic accounts for LDAP or AD users, these fields specify the LDAP or AD attribute value that will be automatically inserted into each field in each user's **Account Properties** page. (For more information about user account properties, see the **Organizations** & **Users** manual.)

SL1 automatically populates as many of these fields as possible. You can edit or delete the default values provided by SL1. For example, SL1 automatically inserts the value of the LDAP/AD attribute "sn" (surname) into the *Last Name* field in each user's **Account Properties** page.

NOTE: SL1 requires that the LDAP or AD attribute name that you specify in each field uses **all lower-case** characters.

- First Name. Specifies the LDAP or AD attribute value that will be automatically inserted into the First
 Name field in each user's Account Properties page. By default, SL1 inserts the value of the
 LDAP/AD attribute "givenname" into this field.
- Last Name. Specifies the LDAP or AD attribute value that will be automatically inserted into the Last
 Name field in each user's Account Properties page. By default, SL1 inserts the value of the
 LDAP/AD attribute "sn" into this field.
- *Title*. Specifies the LDAP or AD attribute value that will be automatically inserted into the *Title* field in each user's **Account Properties** page.
- **Department**. Specifies the LDAP or AD attribute value that will be automatically inserted into the **Department** field in each user's **Account Properties** page.
- Phone. Specifies the LDAP or AD attribute value that will be automatically inserted into the Phone
 field in each user's Account Properties page. By default, SL1 inserts the value of the LDAP/AD
 attribute "telephonenumber" into this field.
- Fax. Specifies the LDAP or AD attribute value that will be automatically inserted into the Fax field in each user's Account Properties page.
- Mobile. Specifies the LDAP or AD attribute value that will be automatically inserted into the Mobile
 field in each user's Account Properties page. By default, SL1 inserts the value of the LDAP/AD
 attribute "mobile" into this field.
- **Pager**. Specifies the LDAP or AD attribute value that will be automatically inserted into the **Pager** field in each user's **Account Properties** page.
- Primary Email. Specifies the LDAP or AD attribute value that will be automatically inserted into the
 Primary Email field in each user's Account Properties page. By default, SL1 inserts the value of the
 LDAP/AD attribute "mail" into this field.
- **Secondary Email**. Specifies the LDAP or AD attribute value that will be automatically inserted into the **Secondary Email** field in each user's **Account Properties** page.
- Street Address. Specifies the LDAP or AD attribute value that will be automatically inserted into the
 Street Address field in each user's Account Properties page. By default, SL1 inserts the value of the
 LDAP/AD attribute "streetaddress" into this field.
- **Suite/Building**. Specifies the LDAP or AD attribute value that will be automatically inserted into the **Suite/Building** field in each user's **Account Properties** page.
- City. Specifies the LDAP or AD attribute value that will be automatically inserted into the City field in
 each user's Account Properties page. By default, SL1 inserts the value of the LDAP/AD attribute "I"
 into this field.
- State. Specifies the LDAP or AD attribute value that will be automatically inserted into the State field
 in each user's Account Properties page. By default, SL1 inserts the value of the LDAP/AD attribute
 "st" into this field.
- Postal Code. Specifies the LDAP or AD attribute value that will be automatically inserted into the
 Postal Code field in each user's Account Properties page. By default, SL1 inserts the value of the
 LDAP/AD attribute "postalcode" into this field.
- Country. Specifies the LDAP or AD attribute value that will be automatically inserted into the Country field in each user's Account Properties page.

- Organization. Specifies the LDAP or AD attribute value that will be used to automatically define the
 Primary Organization field in each user's **Account Permissions** page. You must also specify one of
 the following:
 - directory attribute specifies organization ID. If selected, the attribute in the **Organization** field specifies an organization ID.
 - directory attribute specifies organization name. If selected, the attribute in the **Organization** field specifies an organization name.
 - directory attribute specifies organization CRM ID. If selected, the attribute in the **Organization** field specifies the CRM ID of an organization.

NOTE: To use Attribute Mapping for **Organization**, your LDAP/AD schema must include an attribute that maps to ScienceLogic Organization names, Organization IDs, or Organization CRM IDs.

NOTE: When you create a new LDAP/AD user, you must align a user policy with that user. If the aligned user policy specifies an organization for the user, the value from the user policy will overwrite the value from Attribute Mapping.

User Policy Alignment

- Type. Specifies whether SL1 should automatically create ScienceLogic accounts for each LDAP or
 Active Directory user in the search base (which is specified in the credential), whether SL1 should
 simply use LDAP or Active Directory to authenticate one or more users, or whether SL1 will refuse to
 authenticate specific users. Choices are:
 - Do not authenticate new users from directory. Only those users who have an account already created in SL1 can log in to SL1. However, if one or more users' **Account Permissions** page specifies LDAP /Active Directory in the **Authentication Method** field, SL1 will authenticate those users with either LDAP or Active Directory, using the settings and credentials specified in this page.
 - Static policy alignment. If an LDAP or AD user logs in to SL1 using the LDAP or AD attribute specified in the **Search Filter** field, SL1 will automatically create an account for that user. SL1 will use **one user policy** (specified in the **Policy** field) to create all imported LDAP or AD user accounts. SL1 will also use the settings and credentials specified in this page when creating the account.
 - Dynamic policy alignment. If an LDAP or AD user logs in to SL1 using the LDAP or AD attribute specified in the Search Filter field, SL1 will automatically create an account for that user. SL1 will choose from among multiple user policies to create imported LDAP or AD user accounts. For example, some imported user accounts might use "user policy A"; other imported user accounts might use "user policy B". SL1 will also use the settings and credentials specified in this page when creating the account.

NOTE: If you selected Static policy alignment in the Type field, you must supply a value in the Policy field:

Policy. Specifies the user policy to use to automatically create a ScienceLogic account for each LDAP or AD user. Select from a list of all user policies that specify LDAP /Active Directory in the Authentication Method field.

NOTE: If you selected *Dynamic policy alignment* in the **Type** field, you must supply values in the **Attribute**, **Value**, and **Policy** fields.

- Attribute. Specifies the LDAP or AD attribute you want to use to differentiate imported user accounts.
 For example, you could select the attribute "department" and then assign different user policies to
 import user accounts from different departments. You can also use this field to exclude LDAP or
 AD accounts for which you do not want to create a ScienceLogic account.
- Value. Specifies the LDAP or AD attribute value. That is, you specify one of the possible values for the
 attribute (specified in the Attribute field). SL1 will compare the value in this field to the retrieved value
 for the Attribute.
- Policy. Choose one of the following:
 - Do Not Authenticate. If selected, if the retrieved value of the specified **Attribute** matches the value in the **Value** field, the user is not authenticated. This setting applies to new users for whom LDAP or Active Directory would have to create a new account in SL1 and for users who already have an account in SL1.
 - * the policy you want to associate with that value. Select from a list of all user policies that specify LDAP /Active Directory in the **Authentication Method** field.
 - For example, suppose you specified "department" in the Attribute field. Suppose that the "department" attribute could have two possible values: "Sales" or "NOC".
 - Suppose you created two user policies. One user policy, called "Sales User Policy", includes the appropriate ticket queues and access keys for Sales personnel. Another user policy, called "NOC User Policy", include the appropriate ticket queues and access keys for NOC personnel.
 - In one of the Value fields, you could specify "Sales". In the corresponding Policy field, you could then specify "Sales User Policy".
 - In the next Value field, you could specify "NOC". In the corresponding Policy field, you could specify "NOC User Policy.
 - After defining these two Value fields and corresponding Policy fields, user accounts from the Sales department would be imported into SL1 using the Sales User Policy. User accounts from the NOC department would be imported into SL1 using the NOC User Policy.
- To define additional Value and Policy fields, click on the green plus-sign () icon.
- 4. Click the [Save] button to save your changes to the new authentication resource.

Creating an SSO Authentication Resource

The **SSO Auth Resource Editor** page allows you to define an authentication resource for use with a SAML IdP. An SSO authentication resource specifies the connector (communication software) to use to communicate with the SAML IdP and the URLs to use to send and retrieve information from the SAML IdP. An SSO authentication resource can also maps attributes from the user's SSO account to fields in the ScienceLogic user account.

ScienceLogic administrators can use SSO to authenticate ScienceLogic users. There are two ways to use SSO authentication with SL1:

- You can configure SL1 to automatically create user accounts for existing SSO users and then always use SSO to authenticate those users when they log in to SL1.
- You can use SSO to authenticate one or more ScienceLogic users when they log in to SL1.

To create an SSO authentication resource:

- 1. Go to the **Authentication Resource Manager** page (System > Settings > Authentication > Resources).
- 2. Click the [Actions] menu and then select Create SSO Resource. The SSO Auth Resource Editor page appears.
- 3. Enter values in the following fields:

Basic Settings

- Name. Name of the SSO authentication resource.
- *IdP Entity ID*. Globally unique name for the identity provider or service provider, in the format of an absolute URL.
- *IdP Cert Fingerprint*. The SHA1 certificate fingerprint, provided by the identity provider or service provider.
- User Name Suffix. Optional field. Because a user can authenticate against multiple SSO servers, there is a risk of collision among user names. In this field, you can enter a string to append to the ScienceLogic user name to minimize risk of collision. For example:
 - ° Suppose we entered @ad.local in this field.
 - Suppose the next LDAP/AD user logs in to SL1 with the user name bishopbrennan.
 - SL1 will log in that user as bishopbrennan@ad.local.

NOTE: A best practice to avoid collisions is to use email addresses as user names.

- IdP SSO URL. The URL to which SL1 will send login requests to the IdP. This field must contain an
 absolute URL.
- *IdP SLS URL*. Optional field. If you want each user to be automatically logged out of the IdP when that user logs out of SL1, enter the URL to which SL1 will post the logout request to the IdP. If you leave this field blank, a user can log out of SL1 without automatically logging out of the IdP.

• Sync directory values to EM7 on login. If an SSO administrator makes changes to an SSO account, SL1 will automatically retrieve those updates and apply them to the user's account in SL1 (in the Account Properties page) the next time the user logs in to SL1. (For more information about user account properties, see the Organizations & Users manual.)

Attribute Mapping

If you have configured SL1 to automatically create ScienceLogic accounts for SSO users, these fields specify the SAML attribute value that will be automatically inserted into each field in each user's **Account Properties** page. (For more information about user account properties, see the **Organizations & Users** manual.)

SL1 automatically populates as many of these fields as possible. You can edit or delete the default values provided by SL1. For example, SL1 automatically inserts the value of the SAML attribute "sn" (surname) into the *Last Name* field in each user's *Account Properties* page.

NOTE: SL1 requires that the SAML attribute name that you specify in each field uses all lowercase characters.

- First Name. Specifies the SAML attribute value that will be automatically inserted into the First
 Name field in each user's Account Properties page. By default, SL1 inserts the value of the SAML
 attribute "givenname" into this field.
- Last Name. Specifies the SAML attribute value that will be automatically inserted into the Last Name
 field in each user's Account Properties page. By default, SL1 inserts the value of the SAML attribute
 "sn" into this field.
- *Title*. Specifies the SAML attribute value that will be automatically inserted into the *Title* field in each user's **Account Properties** page.
- **Department**. Specifies the SAML attribute value that will be automatically inserted into the **Department** field in each user's **Account Properties** page.
- Phone. Specifies the SAML attribute value that will be automatically inserted into the Phone field in
 each user's Account Properties page. By default, SL1 inserts the value of the SAML attribute
 "telephonenumber" into this field.
- Fax. Specifies the SAML attribute value that will be automatically inserted into the Fax field in each user's Account Properties page.
- Mobile. Specifies the SAML attribute value that will be automatically inserted into the Mobile field in
 each user's Account Properties page. By default, SL1 inserts the value of the SAML attribute "mobile"
 into this field.
- **Pager**. Specifies the SAML attribute value that will be automatically inserted into the **Pager** field in each user's **Account Properties** page.
- Primary Email. Specifies the SAML attribute value that will be automatically inserted into the Primary
 Email field in each user's Account Properties page. By default, SL1 inserts the value of the SAML
 attribute "mail" into this field.
- Secondary Email. Specifies the SAML attribute value that will be automatically inserted into the Secondary Email field in each user's Account Properties page.

- Street Address. Specifies the SAML attribute value that will be automatically inserted into the Street
 Address field in each user's Account Properties page. By default, SL1 inserts the value of the SAML
 attribute "streetaddress" into this field.
- Suite/Building. Specifies the SAML attribute value that will be automatically inserted into the Suite/Building field in each user's Account Properties page.
- City. Specifies the SAML attribute value that will be automatically inserted into the City field in each
 user's Account Properties page. By default, SL1 inserts the value of the SAML attribute "I" into this
 field
- **State**. Specifies the SAML attribute value that will be automatically inserted into the **State** field in each user's **Account Properties** page. By default, SL1 inserts the value of the SAML attribute "st" into this field.
- Postal Code. Specifies the SAML attribute value that will be automatically inserted into the Postal
 Code field in each user's Account Properties page. By default, SL1 inserts the value of the SAML
 attribute "postalcode" into this field.
- Country. Specifies the SAML attribute value that will be automatically inserted into the Country field in each user's Account Properties page.
- Organization. Specifies the SAML attribute value that will be used to automatically define the
 Primary Organization field in each user's Account Permissions page. You must also specify one of
 the following:
 - directory attribute specifies organization ID. The attribute in the **Organization** field specifies an organization ID.
 - directory attribute specifies organization name. The attribute in the **Organization** field specifies an organization name.
 - directory attribute specifies organization CRM ID. The attribute in the **Organization** field specifies the CRM ID of an organization.

NOTE: To use Attribute Mapping for **Organization**, your SAML schema must include an attribute that maps to All-In-One Appliance Organization names, Organization IDs, or Organization CRM IDs.

NOTE: When you create a new SSO user, you must align a user policy with that user. If the aligned user policy specifies an organization for the user, the value from the user policy will overwrite the value from Attribute Mapping.

User Policy Alignment

- Type. Specifies whether SL1 should automatically create ScienceLogic accounts for each SSO user, whether SL1 should simply use SSO to authenticate one or more users, or whether SL1 will refuse to authenticate specific users. Choices are:
 - Do not authenticate new users. Only those users who have an account already created in SL1 can log in to SL1, which will authenticate those users with SSO using the settings specified in this page.

- Static policy alignment. If an SSO user tries to access SL1, SL1 will automatically create an account for that user. SL1 will use one user policy (specified in the *Policy* field) to create the imported SSO user accounts for this authentication resource. SL1 will also use the settings specified in this page when creating the account.
- Dynamic policy alignment. If an SSO users tries to access SL1, SL1 will automatically create an account for that user. SL1 will choose from among **multiple user policies** to create imported SSO user accounts for this authentication resource. For example, some imported user accounts might use "user policy A"; other imported user accounts might use "user policy B". SL1 will also use the settings specified in this page when creating the account.

NOTE: If you selected Static policy alignment in the Type field, you must supply a value in the Policy field.

Policy. Specifies the user policy to use to automatically create a ScienceLogic account for each SSO user. Select from a list of all user policies.

NOTE: If you selected *Dynamic policy alignment* in the **Type** field, you must supply values in the **Attribute**, **Value**, and **Policy** fields.

- Attribute. Specifies the SAML attribute you want to use to differentiate imported user accounts. For example, you could select the attribute department and then assign different user policies to import user accounts from different departments. You can also use this field to exclude SSO accounts for which you do not want to allow authentication.
- Value. Specifies the SAML attribute value. That is, you specify one of the possible values for the
 attribute (specified in the Attribute field). SL1 will compare the value in this field to the retrieved value
 for the Attribute.
- **Policy**. Choose one of the following:
 - Do Not Authenticate. If the retrieved value of the specified Attribute matches the value in the Value field, the user is not authenticated. This setting applies to new users for whom SSO would have to create a new account in SL1 and for users who already have an account in SL1.
 - * the policy you want to associate with that value. Select from a list of all user policies that specify SSO in the **Authentication Method** field.
 - For example, suppose you specified department in the **Attribute** field. Suppose that the department attribute could have two possible values: Sales or NOC.
 - Suppose you created two user policies. One user policy, called Sales User Policy, includes the appropriate ticket queues and access keys for Sales personnel. Another user policy, called NOC User Policy, includes the appropriate ticket queues and access keys for NOC personnel.
 - In one of the **Value** fields, you could specify Sales. In the corresponding **Policy** field, you could then specify Sales User Policy.

Authentication Resources 397

- You could then click on the plus-sign icon (*) and add another Value field and another Policy field.
- In the next Value field, you could specify NOC. In the corresponding Policy field, you could specify NOC User Policy.
- After defining these two Value fields and the corresponding Policy fields, user accounts from the Sales department would be imported into SL1 using the Sales User Policy.
- User accounts from the NOC department would be imported into SL1 using the NOC User Policy.
- To define additional Value and Policy fields, click on the green plus-sign icon (*).
- 4. Click the [Save] button to save your changes to the new authentication resource.

Editing an Authentication Resource

The Authentication Resource Manager page allows you to edit an existing authentication resource. To do so:

- 1. Go to the **Authentication Resource Manager** page (System > Settings > Authentication > Resources).
- 2. Find the authentication resource that you want to edit. Click its wrench icon (🎤).
 - For LDAP/AD Resources, the LDAP/AD Auth Resource Editor page appears. In this page, you can
 you can edit the values for one or more fields. For more information, see the Creating an LDAP/AD
 Authentication Resource section.
 - For SSO Resources, SSO Auth Resource Editor page appears. In this page, you can you can edit the
 values for one or more fields. For more information, see the Creating an SSO Authentication
 Resource section.
- 3. Click the [Save] button to save your changes to the authentication resource.

Deleting an Authentication Resource

The **Authentication Resource Manager** page allows you to delete one or more authentication resources from SL1. To do so:

- 1. Go to the **Authentication Resource Manager** page (System > Settings > Authentication > Resources).
- 2. Select the checkbox (☑) of each authentication resource that you want to delete.
- 3. Click the **Select Actions** menu (in the lower right), select *DELETE Authentication Resource*, and then click the **[Go]** button. The selected authentication resources will be deleted.

NOTE: You cannot delete the EM7 Internal authentication resource.

398 Authentication Resources

Chapter

17

Installing an SSL Certificate

Overview

This chapter describes how to acquire and install an SSL certificate for your SL1 system.

SSL is an acronym for Secure Sockets Layer. SSL is a protocol for securely transmitting data via the internet. SSL uses a private key to encrypt data to be transferred over the Internet connection. Usually, URLs that include "HTTPS" are using SSL for security. To implement SSL, an SSL certificate resides on the web server and is used to encrypt the data and to identify the website.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon (=).
- To view a page containing all of the menu options, click the Advanced menu icon (...).

This chapter covers the following topics:

Using SSL Certificates	400
Certificates for ScienceLogic Servers	400
Requesting a Commercial SSL Certificate	400
Creating Your Own Certificate	402
Installing the Certificate on an SL1 Appliance	404

Using SSL Certificates

SSL is an acronym for Secure Sockets Layer. SSL is a protocol for securely transmitting data via the internet. SSL uses a private key to encrypt data to be transferred over the Internet connection. Usually, URLs that include "HTTPS" are using SSL for security.

To implement SSL, an SSL certificate resides on the web server and is used to encrypt the data and to identify the website. The SSL certificate contains information about the certificate holder, the domain for which the certificate was issued, the name of the Certificate Authority who issued the certificate, and the root and the country in which the certificate was issued.

There are two ways to acquire an SSL certificate:

- You can purchase a certificate from a vendor (called a "certificate authority"), such as VeriSign or GeoTrust.
- You can "self-sign" your own certificate. Using available tools (both open source and proprietary), you can
 create and sign your own SSL certificate instead of purchasing from a certificate authority.

SL1 includes a self-signed certificate from ScienceLogic. Self-signed certificates can trigger a warning message in some browsers. For this reasons, some customers might prefer to purchase an SSL certificate from a certificate authority and install the certificate on one or more servers.

Certificates for ScienceLogic Servers

Each SL1 appliance includes a self-signed certificate from ScienceLogic.

Each SL1 appliance uses the Nginx web server and OpenSSL.

If you want to use commercial SSL certificates with SL1, you must purchase certificates for the following SL1 appliances:

- For each Administration Portal, Database Server, or All-In-One Appliance you must purchase **two** certificates, one for the standard user interface and one for the Configuration Utility.
- For each Data Collector, you must purchase one certificate, for use with the Configuration Utility.
- For each Message Collector, you must purchase one certificate, for use with the Configuration Utility.

Requesting a Commercial SSL Certificate

To purchase a commercial SSL certificate, you must first create a private key and then use the private key to create a Certificate Signing Request (CSR). You must then send the CSR to a Certificate Authority (CA). Some well-known CAs are VeriSign, GeoTrust, Thawte, GoDaddy, and Comodo. The CA will charge you a fee and send you a certificate for use with your private key.

To create a CSR, perform the following on each SL1 appliance.

1. Either go to the console of the SL1 appliance or use SSH to access the server. Open a shell session on the SL1 appliance. Log in as "em7admin".

400 Using SSL Certificates

2. Generate a private key for the server. To do this, enter the following at the shell prompt:

```
sudo openssl genrsa -aes256 -out [keyname].key 4096
```

where:

• [keyname] is a name for the private key. For example, you might want to name the private key for an administration portal adminport.key.

NOTE: Make sure the file is **not** named **silossl.key**, which is the name of the pre-existing ScienceLogic, self-signed certificate file.

3. Enter a passphrase for the key when prompted.

TIP: A best practice is to make a backup copy of the key file and the passphrase and store both in a secure location.

4. Remove the passphrase from the key before generating a Certificate Signing Request (CSR). To do this, enter the following command at the shell prompt, inserting the keyname you used where indicated:

```
sudo openssl rsa -in [keyname].key -out [keyname].key.insecure
```

5. Create a Certificate Signing Request (CSR) for the private key you created in the previous steps. To do this, enter the following command at the shell prompt:

```
sudo openssl req -new -key [keyname].key.insecure -out [keyname].csr
```

where:

• [keyname] is a name for the CSR for the specific server. For example, you might want to name the private key for an administration portal adminport.key and name the CSR for that key adminport.csr.

NOTE: Make sure the keyname is **not** *silossl.key*. This is the name of the pre-existing ScienceLogic, self-signed certificate file.

- 6. Enter the demographic information for your key.
 - Enter a two-letter Country Name (for example, US).
 - Enter your State or Province full name (for example, Virginia).
 - Enter your Locality Name or city (for example, Reston).
 - Enter your Organization Name or company (for example, ScienceLogic).
 - Enter the Common Name, that is, your server's hostname (for example, myhost.sciencelogic.com).

- Enter your Email Address. This is where you want communication from the Certificate Authority to be sent.
- 7. Send the .csr file you generated to a Certificate Authority. The Certificate Authority will provide details on how to send the .csr file. The Certificate Authority will then send you a .crt file. The .crt file is the public key that matches your private key for the SL1 appliance. Some Certificate Authorities, e.g. GoDaddy, might use an intermediate certificate to sign the provided certificate. If an intermediate certificate is used, the Certificate Authority will provide a bundle of chained certificates in a second .crt file.

Creating Your Own Certificate

There are two reasons you might create your own SSL certificate:

- If your organization is a root Certificate Authority (for example, some departments of the United States government), you can create your own private key and public key for each ScienceLogic server.
- If your security requirements permit a self-signed certificate, you can create your own private key and public key for each SL1 appliance.

NOTE: Remember to create key pairs for all for each SL1 appliance in your SL1 system, and also remember to create two key pairs for each Administration Portal in your SL1 system.

NOTE: If your organization is a Certificate Authority, see your organization's internal documentation on creating a certificate for NGINX.

To create a self-signed certificate:

- 1. Either go to the console of the SL1 appliance or use SSH to open a shell session on the SL1 appliance.
- 2. Log in as an administrator (such as em7admin).
- 3. Generate a private key for the server. To do this, enter the following at the shell prompt:

```
sudo openssl genrsa -aes256 -out [keyname].key 4096
```

where [keyname] is a name for the private key. For example, you might want to name the private key for an Administration Portal adminport.key.

CAUTION: Make sure the file is **not** named **silossl.key**.. This is the name of the pre-existing ScienceLogic, self-signed certificate file.

4. Enter a passphrase for the key when prompted.

TIP: A best practice is to make a backup copy of the key file and the passphrase and store both in a secure location.

5. Remove the passphrase from the key before you continue. To do this, enter the following command at the shell prompt, inserting the keyname you used where indicated:

```
sudo openssl rsa -in [keyname].key -out [keyname].key.insecure
```

6. Create a self-signed certificate based on the private key you generated in the previous steps. To do this, enter the following at the shell prompt:

```
sudo openssl req -new -x509 -nodes -sha1 -days 365 -key [keyname].key
-out [keyname].crt
```

where:

- [keyname].key is the private key for the SL1 appliance.
- [keyname].crt is the public key (certificate) for the SL1 appliance.

For example, you might want to name the private key for an Administration Portal adminport.key, and name the certificate file for that key adminport.crt. The resulting .crt file is the public key that matches your private key for the SL1 appliance.

CAUTION: Make sure the files are **not** named **silossl.crt** and **silossl.key**. These are the names of the pre-existing ScienceLogic, self-signed certificate files.

- 7. Copy your private key and certificate files to /etc/nginx.
- 8. **On Collectors**. Add the private key and certificate file to each Collector for the Configuration Utility. To do this, add the names of the new .key and .crt files to the following files:

```
/etc/nginx/conf.d/em7ngx web ui.conf
```

/etc/nginx/conf.d/em7ngx em7proxy web ui.conf

9. On the Administration Portal, Database Server, or All-in-One Appliance. Add the private key and certificate file for the user interface. To do this, add the names of the new .key and .crt files to the following files:

/etc/nginx/conf.d/em7ngx web ui.conf

/etc/nginx/conf.d/em7ngx em7proxy web ui.conf

10. Restart the Web Configuration Utility and web server by entering the following command:

```
sudo systemctl restart nginx
```

Installing the Certificate on an SL1 Appliance

ScienceLogic does not provide support for third party certificates. Be advised that installing a new SSL certificate can affect the operation of SSL services.

Most certificate authorities provide support and resources on installing and enabling their certificates in Nginx web servers. If you have questions, please refer to your Certificate Authority.

WARNING: The following steps will stop and restart the SL1 appliance and temporarily make the Administration Portal site unavailable. Confirm with your System Administrator that you are permitted to restart the ScienceLogic Web Service.

NOTE: These instructions assume that you are familiar with the Linux shell and the "vi" editor.

To install a commercial SSL certificate on a SL1 appliance, perform the following:

- 1. Purchase a certificate from a certificate authority.
- 2. Copy the certificate files (*.key and all *.crt files) to a server that can access the SL1 appliance via SFTP.

NOTE: Make sure the files are **not** named **silossl.crt** and **silossl.key**. These are the names of the pre-existing ScienceLogic, self-signed certificate files.

- 3. Use SFTP or SCP to copy the .crt file(s) and the .key file to the SL1 appliance in the /etc/nginx directory.
- 4. Either go to the console of the SL1 appliance or use SSH to access the server. Open a shell session on the SL1 appliance. Log in as "em7admin".
- 5. If an intermediate certificate has been used to sign the certificate file, execute the following commands to combine the server certificate and the bundle of chained certificates provided by the Certificate Authority, entering the server certificate name, bundle name, and combined certificate name where indicated:

```
cd /etc/nginx
```

```
cat [server certificate name].crt [bundle name].crt > [combined
certificate name].crt
```

Use the combined .crt file name when updating the nginx configuration.

- 6. For each appliance, edit the following files to configure the certificate for the Configuration Utility:
 - /etc/nginx/conf.d/em7webconfig.conf
 - /etc/nginx/conf.d/em7 sladmin.conf

• Edit the following lines, removing references to silossl.crt and silossl.key and replacing with the names of the new .key and .crtfiles:

```
ssl_certificate /etc/nginx/[name of .crt file];
ssl_certificate_key /etc/nginx/[name of .key file];
```

- 7. In addition, for each Administration Portal, Database Server, and All-In-One Appliance, you must also edit the following files to configure the certificate for the user interface:
 - /etc/nginx/conf.d/em7ngx web ui.conf
 - /etc/nginx/conf.d/em7ngx_em7proxy_web_ui.conf
 - Edit the following lines, removing references to silossl.pem and silossl.key and replacing with the names of the new key files:

```
ssl_certificate /etc/nginx/[name of .crt file];
ssl_certificate_key /etc/nginx/[name of .key file];
```

- 8. Next, you will need to restart the webconfig and webserver. To do this, execute the following command:
 - For all appliances, enter:

```
sudo systemctl restart nginx
```

- 9. To test the SSL certificate, open a browser session and connect to the Administration Portal, Database Server, or All-In-One Appliance using https.
 - From the Administration Portal, go to System > Settings > Appliances.
 - In the Appliance Manager page, select the toolbox icon () for each server. Notice that the URL for the Configuration Utility includes https.

Chapter

18

Managing Host Files

Overview

The **Host File Entry Manager** page allows you to edit and manage host files for all of the Data Collectors from a single page in the SL1 system. When you create or edit an entry in the **Host File Entry Manager** page, SL1 automatically sends an update to every Data Collector in the specified Collector Group.

The Host File Entry Manager page is helpful when:

- The SL1 system does not reside in the end-customer's domain
- The SL1 system does not have line-of-sight to an end-customer's DNS service
- A customer's DNS service cannot resolve a host name for a device that the SL1 system monitors

You can create host file entries for each device managed by the SL1 system. You can create duplicate host file entries, one for each Collection Group, to ensure that all Collection Groups can resolve all host names for monitored devices.

Use the following menu options to navigate the SL1 user interface:

- To view a pop-out list of menu options, click the menu icon (=).
- To view a page containing all of the menu options, click the Advanced menu icon (...).

This chapter covers the following topics:

Viewing the List of Host Entries	407
Creating a New Host Entry	407
Editing a Host Entry	408
Using an Existing Host File Entry to Create a New Host File Entry (Save As)	408
Deleting One or More Host Entries	409

Viewing the List of Host Entries

To view the list of host entries, perform the following steps:

- 1. Go to the **Host File Entry Manager** page (System > Customize > Host Files).
- 2. The **Host File Entry Manager** page displays the following about each host entry:
 - IP Address. The IP address to resolve with the host name.
 - Hostnames and Aliases. The host name to align with the specified IP address. You can also include a space-delimited list of aliases for the host name.
 - **Description**. Description of the host entry.
 - Organization. Organization associated with the host.
 - **CUG**. The Collector Group to which SL1 will send the host entry. The host entry will be added to the host file on each Data Collection Server in the Collector Group.
 - Edited By . User who created or last edited the host entry.
 - Last Edit. Date the host entry was created or last edited.

Creating a New Host Entry

To create a host file entry:

- 1. Go to the **Host File Entry Manager** page (System > Customize > Host Files).
- 2. Click the [Action] menu and choose Create New Entry. The Create New Host File Entry modal page appears.
- 3. In the Create New Host File Entry modal page, supply values in the following fields:
 - IP Address. The IP address to resolve with the hostname.

NOTE: Server hostnames should be aligned to external IP addresses when supporting Network Address Translation (NAT) environments.

- Hostnames and Aliases. The hostname to align with the specified IP address. You can also include a space-delimited list of aliases for the host name.
- **Description**. Description of the host entry. This field is not written to the host file. This field is for administrators to use when managing host file entries.
- Organization. Organization associated with the host. You can select from a list of all existing organizations. This field is not written to the host file. This field is for administrators to use when managing host file entries. For example, a service provider could assign each customer its own organization and then use this field to manage host file entries for each customer.

4. Click the [Save] button to save the new host entry.

Editing a Host Entry

To edit a host entry, perform the following steps:

- 1. Go to the **Host File Entry Manager** page (System > Customize > Host Files).
- 2. Click the wrench icon () for the host file entry you want to edit. The **Editing Host File Entry** modal page appears, populated with values from the selected host file entry.
- 3. In the Editing Host File Entry modal page, you can edit one or more of the following fields:
 - IP Address. The IP address to resolve with the host name.
 - Hostnames and Aliases. The host name to align with the specified IP address. You can also include
 a space-delimited list of aliases for the host name.
 - **Description**. Description of the host entry. This field is not written to the host file. This field is for administrators to use when managing host file entries.
 - Organization. Organization associated with the host. You can select from a list of all existing organizations. This field is not written to the host file. This field is for administrators to use when managing host file entries. For example, a service provider could assign each customer its own organization and then use this field to manage host file entries for each customer.
- 4. Click the [Save] button to save your changes.

Using an Existing Host File Entry to Create a New Host File Entry (Save As)

To create a new host entry, using an existing host entry as the template:

- 1. Go to the **Host File Entry Manager** page (System > Customize > Host Files).
- 2. Click the wrench icon () for the host file entry you want to edit. The **Editing Host File Entry** modal page appears, populated with values from the selected host file entry.
- 3. In the Editing Host File Entry modal page, you can edit one or more of the following fields:
 - IP Address. The IP address to resolve with the host name.
 - **Hostnames and Aliases**. The host name to align with the specified IP address. You can also include a space-delimited list of aliases for the host name.
 - **Description**. Description of the host entry. This field is not written to the host file. This field is for administrators to use when managing host file entries.
 - Organization. Organization associated with the host. You can select from a list of all existing organizations. This field is not written to the host file. This field is for administrators to use when managing host file entries. For example, a service provider could assign each customer its own organization and then use this field to manage host file entries for each customer.

Editing a Host Entry 408

4. Click the [Save As] button to save your changes as a new host file entry. A pop-up message appears, asking if you want to save your edits as a new entry. Click the [OK] button.

Deleting One or More Host Entries

To delete one or more host entries, perform the following steps:

- 1. Go to the **Host File Entry Manager** page (System > Customize > Host Files).
- 2. Select the checkbox (2) for each host file entry you want to delete.
- 3. Click the **Select Action** field in the lower right, then select DELETE Host File Entry. Click the **[Go]** button.

© 2003 - 2024, ScienceLogic, Inc.

All rights reserved.

LIMITATION OF LIABILITY AND GENERAL DISCLAIMER

ALL INFORMATION AVAILABLE IN THIS GUIDE IS PROVIDED "AS IS," WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED. SCIENCELOGIC™ AND ITS SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT.

Although ScienceLogic[™] has attempted to provide accurate information on this Site, information on this Site may contain inadvertent technical inaccuracies or typographical errors, and ScienceLogic[™] assumes no responsibility for the accuracy of the information. Information may be changed or updated without notice. ScienceLogic[™] may also make improvements and / or changes in the products or services described in this Site at any time without notice.

Copyrights and Trademarks

ScienceLogic, the ScienceLogic logo, and EM7 are trademarks of ScienceLogic, Inc. in the United States, other countries, or both.

Below is a list of trademarks and service marks that should be credited to ScienceLogic, Inc. The ® and ™ symbols reflect the trademark registration status in the U.S. Patent and Trademark Office and may not be appropriate for materials to be distributed outside the United States.

- ScienceLogic[™]
- EM7™ and em7™
- Simplify IT™
- Dynamic Application[™]
- Relational Infrastructure Management[™]

The absence of a product or service name, slogan or logo from this list does not constitute a waiver of ScienceLogic's trademark or other intellectual property rights concerning that name, slogan, or logo.

Please note that laws concerning use of trademarks or product names vary by country. Always consult a local attorney for additional guidance.

Other

If any provision of this agreement shall be unlawful, void, or for any reason unenforceable, then that provision shall be deemed severable from this agreement and shall not affect the validity and enforceability of any remaining provisions. This is the entire agreement between the parties relating to the matters contained herein.

In the U.S. and other jurisdictions, trademark owners have a duty to police the use of their marks. Therefore, if you become aware of any improper use of ScienceLogic Trademarks, including infringement or counterfeiting by third parties, report them to Science Logic's legal department immediately. Report as much detail as possible about the misuse, including the name of the party, contact information, and copies or photographs of the potential misuse to: legal@sciencelogic.com. For more information, see https://sciencelogic.com/company/legal.



800-SCI-LOGIC (1-800-724-5644)

International: +1-703-354-1010