

Pre Requisites

- The minimum EM7 version is 7.3.4.
- Before you can monitor devices using this powerpack, you will need credentials to an active powershell proxy with the lync powershell module installed and powershell remote execution privileges (execution policy unrestricted) on the various Lync servers you want to monitor
- This powerpack is meant to run on Lync Server Standard Edition 2010. Please note there is no edge support
- As there are many dynamic apps running at the same time, make sure the powershell proxy is sized accordingly.

Install Instructions

1. Install an ssh proxy, using the instructions on the following page:
https://portal.sciencelogic.com/files/documentation/7_3/monitoring_windows/sciencelogic_monitoring_windows.htm
2. Make sure there is a credential for the powershell proxy (a template is included in the powerpack as lync credential template)
3. Make sure that the powershell proxy has the lync module installed (If it is not installed, insert the lync server install media and install the management tools. Alternatively, if all pre-requisites are already installed, the file ocscore.msc on the lync install the lync module)
4. Copy lync_perf_count.ps to C:\Cygwin\Home\em7test and make sure the file is readable by the em7proxy user.
Note: the file is included in the powerpack in the documentation tab
5. Install the lync powerpack (attached) module on the em7 system that will be monitoring the lync lab
6. Go to system->discovery and create a new discovery session
 1. add the ip addresses for the powershell proxy and the lync server(s) in the ip address discovery list
 2. In the other credentials box, pick your em7 lync powershell proxy credentials
 3. Make sure the discover non snmp devices box is selected
7. Launch discovery and wait a few minutes for the apps to align (Be patient, it can take a very long time)

Copyright (c) 2003-2014 ScienceLogic

This software is the copyrighted work of ScienceLogic.

Use of the Software is governed by the terms of the software license agreement, which accompanies or is included with the Software ("License Agreement"). An end user is not permitted to install any Software that is accompanied by or includes a License Agreement, unless he or she first agrees to the License Agreement terms.

The Software is made available solely for use by end users according to the License Agreement. Any reproduction or redistribution of the Software not in accordance with the License Agreement is expressly prohibited by law, and may result in severe civil and criminal penalties. Violators will be prosecuted to the maximum extent possible.

WITHOUT LIMITING THE FOREGOING, COPYING OR REPRODUCTION OF THE SOFTWARE TO ANY OTHER SERVER OR LOCATION FOR FURTHER REPRODUCTION OR REDISTRIBUTION IS EXPRESSLY PROHIBITED.

THE SOFTWARE IS WARRANTED, IF AT ALL, ONLY ACCORDING TO THE TERMS OF THE LICENSE AGREEMENT. EXCEPT AS WARRANTED IN THE LICENSE AGREEMENT, SCIENCELOGIC HEREBY DISCLAIMS ALL WARRANTIES AND CONDITIONS WITH REGARD TO THE SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES AND CONDITIONS OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, TITLE AND NON-INFRINGEMENT.