



SL1 PowerFlow PowerPack Release Notes

Version 101

Table of Contents

Overview	3
Before You Install	3
Installing ScienceLogic: Integration Service PowerPack version 101	3
Features	4
Issues Addressed	4

Overview

The *ScienceLogic: Integration Service* PowerPack version 101 includes the ability to create an alert in the associated SL1 system if an integration application in the PowerFlow fails. This version resolves an issue where the previous content libraries were missing from the PowerPack.

- **Minimum Required Version of the PowerFlow:** 1.7.1
- **Minimum Required SL1 Version:** 8.7.0
- **Support Status:** GA

This document describes:

- [Pre-install information](#)
- [The features included in version 101](#)
- [The issues addressed in version 101](#)

Before You Install

Ensure that you are running version 8.7.0 or later of SL1 before installing *ScienceLogic: Integration Service* PowerPack version 101.

NOTE: For details on upgrading SL1, see the appropriate ScienceLogic [Release Notes](#).

Installing ScienceLogic: Integration Service PowerPack version 101

TIP: By default, installing a new version of a PowerPack will overwrite all content in that PowerPack that has already been installed on the target system. You can use the **Enable Selective PowerPack Field Protection** setting in the **Behavior Settings** page (System > Settings > Behavior) in SL1 to prevent the new version of the PowerPack from overwriting local changes for some commonly customized fields.

NOTE: If you are currently using the Dynamic Applications in the *ScienceLogic: Integration Service* PowerPack to monitor devices, collection errors might occur for one or two polling cycles during the installation of a new version. To prevent collection errors during an upgrade, you can optionally disable collection for monitored devices before performing the following steps and re-enable collection after the upgrade.

To install the *ScienceLogic: Integration Service* PowerPack for the first time, perform the following steps:

1. See the [Before You Install](#) section. If you have not done so already, upgrade your system to the 8.7.0 or later release.
2. Download version 101 of the *ScienceLogic: Integration Service* PowerPack from the Customer Portal to a local computer.
3. Go to the **PowerPack Manager** page (System > Manage > PowerPacks). Click the Actions menu and choose *Import PowerPack*. When prompted, import version 101 of the *ScienceLogic: Integration Service* PowerPack.
4. After importing the PowerPack, you will be prompted to install the PowerPack. Click the Install button to install the PowerPack.
5. See the *Integration Service Platform* manual for instructions on using the PowerPack.

Features

ScienceLogic: Integration Service PowerPack version 101 includes the following features:

- The "ScienceLogic: Integration Service Queue Configuration" Dynamic Application, which monitors the status of the PowerFlow RabbitMQ service
- This PowerPack also includes the "REST: Performance Metrics Monitor" Dynamic Application, which monitors outgoing REST requests from SL1 to the PowerFlow
- Event Policies and corresponding alerts that are triggered when an integration application in the PowerFlow fails
- A Device Class for the PowerFlow
- A Sample Credential for connecting to the PowerFlow
- Dashboards that display information about the PowerFlow
- ScienceLogic Libraries that are utilized by this PowerPack:
 - content
 - content_cache
 - silo_core
 - silo_core_rest
 - silo_credentials

Issues Addressed

The following addressed issue is included in PowerFlow version 101:

- This release resolves an issue where the previous content libraries were missing from the PowerPack.

© 2003 - 2020, ScienceLogic, Inc.

All rights reserved.

LIMITATION OF LIABILITY AND GENERAL DISCLAIMER

ALL INFORMATION AVAILABLE IN THIS GUIDE IS PROVIDED "AS IS," WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED. SCIENCELOGIC™ AND ITS SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT.

Although ScienceLogic™ has attempted to provide accurate information on this Site, information on this Site may contain inadvertent technical inaccuracies or typographical errors, and ScienceLogic™ assumes no responsibility for the accuracy of the information. Information may be changed or updated without notice. ScienceLogic™ may also make improvements and / or changes in the products or services described in this Site at any time without notice.

Copyrights and Trademarks

ScienceLogic, the ScienceLogic logo, and EM7 are trademarks of ScienceLogic, Inc. in the United States, other countries, or both.

Below is a list of trademarks and service marks that should be credited to ScienceLogic, Inc. The ® and ™ symbols reflect the trademark registration status in the U.S. Patent and Trademark Office and may not be appropriate for materials to be distributed outside the United States.

- ScienceLogic™
- EM7™ and em7™
- Simplify IT™
- Dynamic Application™
- Relational Infrastructure Management™

The absence of a product or service name, slogan or logo from this list does not constitute a waiver of ScienceLogic's trademark or other intellectual property rights concerning that name, slogan, or logo.

Please note that laws concerning use of trademarks or product names vary by country. Always consult a local attorney for additional guidance.

Other

If any provision of this agreement shall be unlawful, void, or for any reason unenforceable, then that provision shall be deemed severable from this agreement and shall not affect the validity and enforceability of any remaining provisions. This is the entire agreement between the parties relating to the matters contained herein.

In the U.S. and other jurisdictions, trademark owners have a duty to police the use of their marks. Therefore, if you become aware of any improper use of ScienceLogic Trademarks, including infringement or counterfeiting by third parties, report them to Science Logic's legal department immediately. Report as much detail as possible about the misuse, including the name of the party, contact information, and copies or photographs of the potential misuse to: legal@sciencelogic.com



ScienceLogic

800-SCI-LOGIC (1-800-724-5644)

International: +1-703-354-1010